

NASM - The Netwide Assembler

version 2.16rc0-20200614



© 1996–2017 The NASM Development Team — All Rights Reserved

This document is redistributable under the license given in the file "LICENSE" distributed in the NASM archive.

Contents

Chapter 1: Introduction	17
1.1 What Is NASM?.	17
1.1.1 License Conditions	17
Chapter 2: Running NASM	19
2.1 NASM Command-Line Syntax	19
2.1.1 The -o Option: Specifying the Output File Name	19
2.1.2 The -f Option: Specifying the Output File Format	20
2.1.3 The -l Option: Generating a Listing File	20
2.1.4 The -L Option: Additional or Modified Listing Info	20
2.1.5 The -M Option: Generate Makefile Dependencies.	20
2.1.6 The -MG Option: Generate Makefile Dependencies.	21
2.1.7 The -MF Option: Set Makefile Dependency File.	21
2.1.8 The -MD Option: Assemble and Generate Dependencies	21
2.1.9 The -MT Option: Dependency Target Name	21
2.1.10 The -MQ Option: Dependency Target Name (Quoted)	21
2.1.11 The -MP Option: Emit phony targets	21
2.1.12 The -MW Option: Watcom Make quoting style	21
2.1.13 The -F Option: Selecting a Debug Information Format	21
2.1.14 The -g Option: Enabling Debug Information.	22
2.1.15 The -X Option: Selecting an Error Reporting Format	22
2.1.16 The -Z Option: Send Errors to a File.	22
2.1.17 The -s Option: Send Errors to stdout	22
2.1.18 The -i Option: Include File Search Directories	22
2.1.19 The -p Option: Pre-Include a File	23
2.1.20 The -d Option: Pre-Define a Macro	23
2.1.21 The -u Option: Undefine a Macro	23
2.1.22 The -E Option: Preprocess Only.	23
2.1.23 The -a Option: Don't Preprocess At All	24
2.1.24 The -O Option: Specifying Multipass Optimization	24
2.1.25 The -t Option: Enable TASM Compatibility Mode.	24
2.1.26 The -w and -W Options: Enable or Disable Assembly Warnings	24
2.1.27 The -v Option: Display Version Info	28
2.1.28 The --(g l) prefix, --(g l) postfix Options.	28

2.1.29 The --pragma Option	28
2.1.30 The --before Option	29
2.1.31 The --limit-X Option	29
2.1.32 The --keep-all Option.	29
2.1.33 The --no-line Option	29
2.1.34 The NASMENV Environment Variable	29
2.2 Quick Start for MASM Users	30
2.2.1 NASM Is Case-Sensitive	30
2.2.2 NASM Requires Square Brackets For Memory References.	30
2.2.3 NASM Doesn't Store Variable Types	30
2.2.4 NASM Doesn't ASSUME.	31
2.2.5 NASM Doesn't Support Memory Models	31
2.2.6 Floating-Point Differences	31
2.2.7 Other Differences.	31
2.2.8 MASM compatibility package.	31
Chapter 3: The NASM Language	33
3.1 Layout of a NASM Source Line	33
3.2 Pseudo-Instructions	34
3.2.1 DB and Friends: Declaring Initialized Data	34
3.2.2 RESB and Friends: Declaring Uninitialized Data	34
3.2.3 INCBIN: Including External Binary Files	34
3.2.4 EQU: Defining Constants	35
3.2.5 TIMES: Repeating Instructions or Data.	35
3.3 Effective Addresses	35
3.4 Constants	37
3.4.1 Numeric Constants	37
3.4.2 Character Strings.	37
3.4.3 Character Constants	38
3.4.4 String Constants	38
3.4.5 Unicode Strings	39
3.4.6 Floating-Point Constants.	39
3.4.7 Packed BCD Constants	40
3.5 Expressions	40
3.5.1 : Bitwise OR Operator	40
3.5.2 ^: Bitwise XOR Operator	41
3.5.3 &: Bitwise AND Operator	41

3.5.4 << and >>: Bit Shift Operators	41
3.5.5 + and -: Addition and Subtraction Operators.	41
3.5.6 *, /, //, % and %%: Multiplication and Division	41
3.5.7 Unary Operators	41
3.6 SEG and WRT	41
3.7 STRICT: Inhibiting Optimization	42
3.8 Critical Expressions	42
3.9 Local Labels	43
Chapter 4: The NASM Preprocessor	45
4.1 Single-Line Macros	45
4.1.1 The Normal Way: %define	45
4.1.2 Resolving %define: %xdefine.	46
4.1.3 Macro Indirection: %[...]	47
4.1.4 Concatenating Single Line Macro Tokens: %+	48
4.1.5 The Macro Name Itself: %? and %??	48
4.1.6 Undefining Single-Line Macros: %undef.	49
4.1.7 Preprocessor Variables: %assign	49
4.1.8 Defining Strings: %defstr.	49
4.1.9 Defining Tokens: %deftok.	49
4.1.10 Defining Aliases: %defalias.	50
4.1.11 Conditional Comma Operator: %,	50
4.2 String Manipulation in Macros.	50
4.2.1 Concatenating Strings: %strcat	50
4.2.2 String Length: %strlen	50
4.2.3 Extracting Substrings: %substr	51
4.3 Multi-Line Macros: %macro.	51
4.3.1 Overloading Multi-Line Macros.	52
4.3.2 Macro-Local Labels	52
4.3.3 Greedy Macro Parameters	53
4.3.4 Macro Parameters Range	54
4.3.5 Default Macro Parameters	54
4.3.6 %0: Macro Parameter Counter	55
4.3.7 %00: Label Preceding Macro	55
4.3.8 %rotate: Rotating Macro Parameters.	55
4.3.9 Concatenating Macro Parameters	56
4.3.10 Condition Codes as Macro Parameters	57

4.3.11	Disabling Listing Expansion	58
4.3.12	Undefining Multi-Line Macros: %unmacro	58
4.4	Conditional Assembly	58
4.4.1	%ifdef: Testing Single-Line Macro Existence	59
4.4.2	%ifmacro: Testing Multi-Line Macro Existence	59
4.4.3	%ifctx: Testing the Context Stack	59
4.4.4	%if: Testing Arbitrary Numeric Expressions	60
4.4.5	%ifidn and %ifidni: Testing Exact Text Identity	60
4.4.6	%ifid, %ifnum, %ifstr: Testing Token Types.	60
4.4.7	%iftoken: Test for a Single Token	61
4.4.8	%ifempty: Test for Empty Expansion	61
4.4.9	%ifenv: Test If Environment Variable Exists.	62
4.5	Preprocessor Loops: %rep	62
4.6	Source Files and Dependencies	62
4.6.1	%include: Including Other Files	63
4.6.2	%pathsearch: Search the Include Path.	63
4.6.3	%depend: Add Dependent Files	63
4.6.4	%use: Include Standard Macro Package	63
4.7	The Context Stack	64
4.7.1	%push and %pop: Creating and Removing Contexts	64
4.7.2	Context-Local Labels.	64
4.7.3	Context-Local Single-Line Macros	65
4.7.4	Context Fall-Through Lookup (<i>deprecated</i>)	65
4.7.5	%repl: Renaming a Context	66
4.7.6	Example Use of the Context Stack: Block IFs	66
4.8	Stack Relative Preprocessor Directives	67
4.8.1	%arg Directive	67
4.8.2	%stacksize Directive	68
4.8.3	%local Directive	68
4.9	Reporting User-Defined Errors: %error, %warning, %fatal.	69
4.10	%pragma: Setting Options.	70
4.10.1	Preprocessor Pragmas	70
4.11	Other Preprocessor Directives	70
4.11.1	%line Directive	70
4.11.2	%!variable: Read an Environment Variable.	71
4.11.3	%clear: Clear All Macro Definitions	71

Chapter 5: Standard Macros	73
5.1 NASM Version Macros	73
5.1.1 <code>__?NASM_VERSION_ID?__</code> : NASM Version ID	73
5.1.2 <code>__?NASM_VER?__</code> : NASM Version string	73
5.2 <code>__?FILE?__</code> and <code>__?LINE?__</code> : File Name and Line Number.	73
5.3 <code>__?BITS?__</code> : Current Code Generation Mode	74
5.4 <code>__?OUTPUT_FORMAT?__</code> : Current Output Format	74
5.5 <code>__?DEBUG_FORMAT?__</code> : Current Debug Format	74
5.6 Assembly Date and Time Macros	74
5.7 <code>__?USE_package?__</code> : Package Include Test.	75
5.8 <code>__?PASS?__</code> : Assembly Pass.	75
5.9 Structure Data Types	75
5.9.1 STRUC and ENDSTRUC: Declaring Structure Data Types.	75
5.9.2 ISTRUC, AT and IEND: Declaring Instances of Structures	76
5.10 Alignment Control	77
5.10.1 ALIGN and ALIGNB: Code and Data Alignment.	77
5.10.2 SECTALIGN: Section Alignment	78
Chapter 6: Standard Macro Packages	79
6.1 <code>altreg</code> : Alternate Register Names	79
6.2 <code>smartalign</code> : Smart ALIGN Macro	79
6.3 <code>fp</code> : Floating-point macros	80
6.4 <code>ifunc</code> : Integer functions	80
6.4.1 Integer logarithms	80
6.5 <code>masm</code> : MASM compatibility	80
Chapter 7: Assembler Directives	81
7.1 BITS: Specifying Target Processor Mode	81
7.1.1 USE16 & USE32: Aliases for BITS	82
7.2 DEFAULT: Change the assembler defaults	82
7.2.1 REL & ABS: RIP-relative addressing	82
7.2.2 BND & NOBND: BND prefix	82
7.3 SECTION or SEGMENT: Changing and Defining Sections	82
7.3.1 The <code>__?SECT?__</code> Macro.	82
7.4 ABSOLUTE: Defining Absolute Labels.	83
7.5 EXTERN: Importing Symbols from Other Modules	84
7.6 REQUIRED: Importing Symbols from Other Modules	84
7.7 GLOBAL: Exporting Symbols to Other Modules	85

7.8 COMMON: Defining Common Data Areas	85
7.9 STATIC: Local Symbols within Modules	85
7.10 (G L) PREFIX, (G L) POSTFIX: Mangling Symbols.	86
7.11 CPU: Defining CPU Dependencies	86
7.12 FLOAT: Handling of floating-point constants	87
7.13 [WARNING]: Enable or disable warnings	87
Chapter 8: Output Formats.	89
8.1 bin: Flat-Form Binary Output	89
8.1.1 ORG: Binary File Program Origin	89
8.1.2 bin Extensions to the SECTION Directive	89
8.1.3 Multisection Support for the bin Format.	90
8.1.4 Map Files	90
8.2 ith: Intel Hex Output	90
8.3 srec: Motorola S-Records Output	90
8.4 obj: Microsoft OMF Object Files.	91
8.4.1 obj Extensions to the SEGMENT Directive	91
8.4.2 GROUP: Defining Groups of Segments	92
8.4.3 UPPERCASE: Disabling Case Sensitivity in Output	93
8.4.4 IMPORT: Importing DLL Symbols	93
8.4.5 EXPORT: Exporting DLL Symbols.	93
8.4.6 . . start: Defining the Program Entry Point.	94
8.4.7 obj Extensions to the EXTERN Directive.	94
8.4.8 obj Extensions to the COMMON Directive.	94
8.4.9 Embedded File Dependency Information.	95
8.5 win32: Microsoft Win32 Object Files	95
8.5.1 win32 Extensions to the SECTION Directive	95
8.5.2 win32: Safe Structured Exception Handling	96
8.5.3 Debugging formats for Windows	97
8.6 win64: Microsoft Win64 Object Files	97
8.6.1 win64: Writing Position-Independent Code	97
8.6.2 win64: Structured Exception Handling	98
8.7 coff: Common Object File Format	101
8.8 macho32 and macho64: Mach Object File Format	101
8.8.1 macho extensions to the SECTION Directive	101
8.8.2 Thread Local Storage in Mach-O: macho special symbols and WRT	102
8.8.3 macho specific directive subsections_via_symbols	102

8.8.4	macho specific directive <code>no_dead_strip</code>102
8.8.5	macho specific extensions to the GLOBAL Directive: <code>private_extern</code>102
8.9	<code>elf32</code> , <code>elf64</code> , <code>elfx32</code> : Executable and Linkable Format Object Files103
8.9.1	ELF specific directive <code>osabi</code>103
8.9.2	ELF extensions to the SECTION Directive103
8.9.3	Position-Independent Code: ELF Special Symbols and WRT104
8.9.4	Thread Local Storage in ELF: <code>elf</code> Special Symbols and WRT105
8.9.5	<code>elf</code> Extensions to the GLOBAL Directive.105
8.9.6	<code>elf</code> Extensions to the EXTERN Directive.106
8.9.7	<code>elf</code> Extensions to the COMMON Directive106
8.9.8	16-bit code and ELF106
8.9.9	Debug formats and ELF106
8.10	<code>aout</code> : Linux <code>a.out</code> Object Files106
8.11	<code>aoutb</code> : NetBSD/FreeBSD/OpenBSD <code>a.out</code> Object Files.106
8.12	<code>as86</code> : Minix/Linux <code>as86</code> Object Files107
8.13	<code>rdf</code> : Relocatable Dynamic Object File Format107
8.13.1	Requiring a Library: The LIBRARY Directive107
8.13.2	Specifying a Module Name: The MODULE Directive107
8.13.3	<code>rdf</code> Extensions to the GLOBAL Directive107
8.13.4	<code>rdf</code> Extensions to the EXTERN Directive108
8.14	<code>dbg</code> : Debugging Format108
Chapter 9:	Writing 16-bit Code (DOS, Windows 3/3.1)109
9.1	Producing <code>.EXE</code> Files109
9.1.1	Using the <code>obj</code> Format To Generate <code>.EXE</code> Files.109
9.1.2	Using the <code>bin</code> Format To Generate <code>.EXE</code> Files.110
9.2	Producing <code>.COM</code> Files111
9.2.1	Using the <code>bin</code> Format To Generate <code>.COM</code> Files.111
9.2.2	Using the <code>obj</code> Format To Generate <code>.COM</code> Files.111
9.3	Producing <code>.SYS</code> Files112
9.4	Interfacing to 16-bit C Programs112
9.4.1	External Symbol Names112
9.4.2	Memory Models.113
9.4.3	Function Definitions and Function Calls114
9.4.4	Accessing Data Items116
9.4.5	<code>c16.mac</code> : Helper Macros for the 16-bit C Interface116
9.5	Interfacing to Borland Pascal Programs117

9.5.1 The Pascal Calling Convention118
9.5.2 Borland Pascal Segment Name Restrictions119
9.5.3 Using c16 . mac With Pascal Programs119
Chapter 10: Writing 32-bit Code (Unix, Win32, DJGPP)121
10.1 Interfacing to 32-bit C Programs121
10.1.1 External Symbol Names121
10.1.2 Function Definitions and Function Calls121
10.1.3 Accessing Data Items123
10.1.4 c32 . mac: Helper Macros for the 32-bit C Interface123
10.2 Writing NetBSD/FreeBSD/OpenBSD and Linux/ELF Shared Libraries124
10.2.1 Obtaining the Address of the GOT124
10.2.2 Finding Your Local Data Items125
10.2.3 Finding External and Common Data Items125
10.2.4 Exporting Symbols to the Library User126
10.2.5 Calling Procedures Outside the Library127
10.2.6 Generating the Library File127
Chapter 11: Mixing 16- and 32-bit Code129
11.1 Mixed-Size Jumps129
11.2 Addressing Between Different-Size Segments129
11.3 Other Mixed-Size Instructions130
Chapter 12: Writing 64-bit Code (Unix, Win64)133
12.1 Register Names in 64-bit Mode133
12.2 Immediates and Displacements in 64-bit Mode133
12.3 Interfacing to 64-bit C Programs (Unix)134
12.4 Interfacing to 64-bit C Programs (Win64)135
Chapter 13: Troubleshooting.137
13.1 Common Problems137
13.1.1 NASM Generates Inefficient Code137
13.1.2 My Jumps are Out of Range137
13.1.3 ORG Doesn't Work137
13.1.4 TIMES Doesn't Work138
Appendix A: Ndisasm.139
A.1 Introduction.139
A.2 Running NDISASM.139
A.2.1 COM Files: Specifying an Origin.139
A.2.2 Code Following Data: Synchronisation139

A.2.3 Mixed Code and Data: Automatic (Intelligent) Synchronisation140
A.2.4 Other Options140
Appendix B: Instruction List143
B.1 Introduction143
B.1.1 Special instructions (pseudo-ops)143
B.1.2 Conventional instructions143
B.1.3 Katmai Streaming SIMD instructions (SSE -- a.k.a. KNI, XMM, MMX2)170
B.1.4 Introduced in Deschutes but necessary for SSE support172
B.1.5 XSAVE group (AVX and extended state).172
B.1.6 Generic memory operations172
B.1.7 New MMX instructions introduced in Katmai172
B.1.8 AMD Enhanced 3DNow! (Athlon) instructions172
B.1.9 Willamette SSE2 Cacheability Instructions173
B.1.10 Willamette MMX instructions (SSE2 SIMD Integer Instructions)173
B.1.11 Willamette Streaming SIMD instructions (SSE2).175
B.1.12 Prescott New Instructions (SSE3)176
B.1.13 VMX/SVM Instructions.177
B.1.14 Extended Page Tables VMX instructions.177
B.1.15 Tejas New Instructions (SSSE3)177
B.1.16 AMD SSE4A178
B.1.17 New instructions in Barcelona178
B.1.18 Penryn New Instructions (SSE4.1).178
B.1.19 Nehalem New Instructions (SSE4.2).179
B.1.20 Intel SMX179
B.1.21 Geode (Cyrix) 3DNow! additions180
B.1.22 Intel new instructions in ???180
B.1.23 Intel AES instructions180
B.1.24 Intel AVX AES instructions.180
B.1.25 Intel instruction extension based on pub number 319433-030 dated October 2017.180
B.1.26 Intel AVX instructions180
B.1.27 Intel Carry-Less Multiplication instructions (CLMUL)193
B.1.28 Intel AVX Carry-Less Multiplication instructions (CLMUL)193
B.1.29 Intel Fused Multiply-Add instructions (FMA)194
B.1.30 Intel post-32 nm processor instructions197
B.1.31 VIA (Centaur) security instructions198
B.1.32 AMD Lightweight Profiling (LWP) instructions.198

B.1.33 AMD XOP and FMA4 instructions (SSE5)198
B.1.34 Intel AVX2 instructions201
B.1.35 Intel Transactional Synchronization Extensions (TSX).204
B.1.36 Intel BMI1 and BMI2 instructions, AMD TBM instructions205
B.1.37 Intel Memory Protection Extensions (MPX)206
B.1.38 Intel SHA acceleration instructions206
B.1.39 AVX-512 mask register instructions206
B.1.40 AVX-512 mask register instructions (aliases requiring explicit size support).208
B.1.41 AVX-512 instructions209
B.1.42 Intel memory protection keys for userspace (PKU aka PKEYs).247
B.1.43 Read Processor ID.247
B.1.44 New memory instructions.247
B.1.45 Processor trace write248
B.1.46 Instructions from the Intel Instruction Set Extensions,248
B.1.47 doc 319433-034 May 2018.248
B.1.48 Galois field operations (GFNI)248
B.1.49 AVX512 Vector Bit Manipulation Instructions 2248
B.1.50 AVX512 VNNI250
B.1.51 AVX512 Bit Algorithms.250
B.1.52 AVX512 4-iteration Multiply-Add250
B.1.53 AVX512 4-iteration Dot Product.250
B.1.54 Intel Software Guard Extensions (SGX)250
B.1.55 Systematic names for the hinting nop instructions250
Appendix C: NASM Version History255
C.1 NASM 2 Series255
C.1.1 Version 2.15255
C.1.2 Version 2.14.03256
C.1.3 Version 2.14.02256
C.1.4 Version 2.14.01256
C.1.5 Version 2.14256
C.1.6 Version 2.13.03257
C.1.7 Version 2.13.02257
C.1.8 Version 2.13.01258
C.1.9 Version 2.13258
C.1.10 Version 2.12.02259
C.1.11 Version 2.12.01259

C.1.12 Version 2.12260
C.1.13 Version 2.11.09260
C.1.14 Version 2.11.08260
C.1.15 Version 2.11.07260
C.1.16 Version 2.11.06261
C.1.17 Version 2.11.05261
C.1.18 Version 2.11.04261
C.1.19 Version 2.11.03261
C.1.20 Version 2.11.02261
C.1.21 Version 2.11.01261
C.1.22 Version 2.11261
C.1.23 Version 2.10.09262
C.1.24 Version 2.10.08262
C.1.25 Version 2.10.07263
C.1.26 Version 2.10.06263
C.1.27 Version 2.10.05263
C.1.28 Version 2.10.04263
C.1.29 Version 2.10.03263
C.1.30 Version 2.10.02263
C.1.31 Version 2.10.01263
C.1.32 Version 2.10263
C.1.33 Version 2.09.10264
C.1.34 Version 2.09.09264
C.1.35 Version 2.09.08264
C.1.36 Version 2.09.07264
C.1.37 Version 2.09.06264
C.1.38 Version 2.09.05264
C.1.39 Version 2.09.04264
C.1.40 Version 2.09.03264
C.1.41 Version 2.09.02265
C.1.42 Version 2.09.01265
C.1.43 Version 2.09265
C.1.44 Version 2.08.02266
C.1.45 Version 2.08.01266
C.1.46 Version 2.08266
C.1.47 Version 2.07266

C.1.48 Version 2.06267
C.1.49 Version 2.05.01267
C.1.50 Version 2.05267
C.1.51 Version 2.04268
C.1.52 Version 2.03.01269
C.1.53 Version 2.03269
C.1.54 Version 2.02269
C.1.55 Version 2.01270
C.1.56 Version 2.00270
C.2 NASM 0.98 Series271
C.2.1 Version 0.98.39271
C.2.2 Version 0.98.38271
C.2.3 Version 0.98.37272
C.2.4 Version 0.98.36272
C.2.5 Version 0.98.35272
C.2.6 Version 0.98.34272
C.2.7 Version 0.98.33273
C.2.8 Version 0.98.32273
C.2.9 Version 0.98.31273
C.2.10 Version 0.98.30274
C.2.11 Version 0.98.28274
C.2.12 Version 0.98.26274
C.2.13 Version 0.98.25alt274
C.2.14 Version 0.98.25274
C.2.15 Version 0.98.24p1274
C.2.16 Version 0.98.24274
C.2.17 Version 0.98.23274
C.2.18 Version 0.98.22274
C.2.19 Version 0.98.21274
C.2.20 Version 0.98.20274
C.2.21 Version 0.98.19275
C.2.22 Version 0.98.18275
C.2.23 Version 0.98.17275
C.2.24 Version 0.98.16275
C.2.25 Version 0.98.15275
C.2.26 Version 0.98.14275

C.2.27 Version 0.98.13275
C.2.28 Version 0.98.12275
C.2.29 Version 0.98.11275
C.2.30 Version 0.98.10275
C.2.31 Version 0.98.09275
C.2.32 Version 0.98.08276
C.2.33 Version 0.98.09b with John Coffman patches released 28-Oct-2001276
C.2.34 Version 0.98.07 released 01/28/01.276
C.2.35 Version 0.98.06f released 01/18/01276
C.2.36 Version 0.98.06e released 01/09/01276
C.2.37 Version 0.98p1277
C.2.38 Version 0.98bf (bug-fixed)277
C.2.39 Version 0.98.03 with John Coffman's changes released 27-Jul-2000277
C.2.40 Version 0.98.03277
C.2.41 Version 0.98280
C.2.42 Version 0.98p9281
C.2.43 Version 0.98p8281
C.2.44 Version 0.98p7281
C.2.45 Version 0.98p6281
C.2.46 Version 0.98p3.7282
C.2.47 Version 0.98p3.6282
C.2.48 Version 0.98p3.5282
C.2.49 Version 0.98p3.4282
C.2.50 Version 0.98p3.3283
C.2.51 Version 0.98p3.2283
C.2.52 Version 0.98p3-hpa283
C.2.53 Version 0.98 pre-release 3283
C.2.54 Version 0.98 pre-release 2284
C.2.55 Version 0.98 pre-release 1284
C.3 NASM 0.9 Series285
C.3.1 Version 0.97 released December 1997285
C.3.2 Version 0.96 released November 1997285
C.3.3 Version 0.95 released July 1997287
C.3.4 Version 0.94 released April 1997289
C.3.5 Version 0.93 released January 1997289
C.3.6 Version 0.92 released January 1997290

C.3.7 Version 0.91 released November 1996290
C.3.8 Version 0.90 released October 1996291
Appendix D: Building NASM from Source.293
D.1 Building from a Source Archive293
D.2 Building from the git Repository.293
Appendix E: Contact Information295
E.1 Website295
E.1.1 User Forums295
E.1.2 Development Community295
E.2 Reporting Bugs295

Chapter 1: Introduction

1.1 What Is NASM?

The Netwide Assembler, NASM, is an 80x86 and x86-64 assembler designed for portability and modularity. It supports a range of object file formats, including Linux and *BSD a.out, ELF, Mach-O, 16-bit and 32-bit .obj (OMF) format, COFF (including its Win32 and Win64 variants.) It can also output plain binary files, Intel hex and Motorola S-Record formats. Its syntax is designed to be simple and easy to understand, similar to the syntax in the Intel Software Developer Manual with minimal complexity. It supports all currently known x86 architectural extensions, and has strong support for macros.

NASM also comes with a set of utilities for handling its own RDOFF2 object-file format.

1.1.1 License Conditions

Please see the file LICENSE, supplied as part of any NASM distribution archive, for the license conditions under which you may use NASM. NASM is now under the so-called 2-clause BSD license, also known as the simplified BSD license.

Copyright 1996-2017 the NASM Authors - All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Chapter 2: Running NASM

2.1 NASM Command-Line Syntax

To assemble a file, you issue a command of the form

```
nasm -f <format> <filename> [-o <output>]
```

For example,

```
nasm -f elf myfile.asm
```

will assemble `myfile.asm` into an ELF object file `myfile.o`. And

```
nasm -f bin myfile.asm -o myfile.com
```

will assemble `myfile.asm` into a raw binary file `myfile.com`.

To produce a listing file, with the hex codes output from NASM displayed on the left of the original sources, use the `-l` option to give a listing file name, for example:

```
nasm -f coff myfile.asm -l myfile.lst
```

To get further usage instructions from NASM, try typing

```
nasm -h
```

The option `--help` is an alias for the `-h` option.

If you use Linux but aren't sure whether your system is a `.out` or ELF, type

```
file nasm
```

(in the directory in which you put the NASM binary when you installed it). If it says something like

```
nasm: ELF 32-bit LSB executable i386 (386 and up) Version 1
```

then your system is ELF, and you should use the option `-f elf` when you want NASM to produce Linux object files. If it says

```
nasm: Linux/i386 demand-paged executable (QMAGIC)
```

or something similar, your system is `a.out`, and you should use `-f aout` instead (Linux `a.out` systems have long been obsolete, and are rare these days.)

Like Unix compilers and assemblers, NASM is silent unless it goes wrong: you won't see any output at all, unless it gives error messages.

2.1.1 The `-o` Option: Specifying the Output File Name

NASM will normally choose the name of your output file for you; precisely how it does this is dependent on the object file format. For Microsoft object file formats (`obj`, `win32` and `win64`), it will remove the `.asm` extension (or whatever extension you like to use – NASM doesn't care) from your source file name and substitute `.obj`. For Unix object file formats (`aout`, `as86`, `coff`, `elf32`, `elf64`, `elfx32`, `ieee`, `macho32` and `macho64`) it will substitute `.o`. For `dbg`, `rdf`, `ith` and `srec`, it will use `.dbg`, `.rdf`, `.ith` and `.srec`, respectively, and for the `bin` format it will simply remove the extension, so that `myfile.asm` produces the output file `myfile`.

If the output file already exists, NASM will overwrite it, unless it has the same name as the input file, in which case it will give a warning and use `nasm.out` as the output file name instead.

For situations in which this behaviour is unacceptable, NASM provides the `-o` command-line option, which allows you to specify your desired output file name. You invoke `-o` by following it with the name you wish for the output file, either with or without an intervening space. For example:

```
nasm -f bin program.asm -o program.com
nasm -f bin driver.asm -o driver.sys
```

Note that this is a small `o`, and is different from a capital `O`, which is used to specify the number of optimisation passes required. See section 2.1.24.

2.1.2 The `-f` Option: Specifying the Output File Format

If you do not supply the `-f` option to NASM, it will choose an output file format for you itself. In the distribution versions of NASM, the default is always `bin`; if you've compiled your own copy of NASM, you can redefine `OF_DEFAULT` at compile time and choose what you want the default to be.

Like `-o`, the intervening space between `-f` and the output file format is optional; so `-f elf` and `-fel` are both valid.

A complete list of the available output file formats can be given by issuing the command `nasm -h`.

2.1.3 The `-l` Option: Generating a Listing File

If you supply the `-l` option to NASM, followed (with the usual optional space) by a file name, NASM will generate a source-listing file for you, in which addresses and generated code are listed on the left, and the actual source code, with expansions of multi-line macros (except those which specifically request no expansion in source listings: see section 4.3.11) on the right. For example:

```
nasm -f elf myfile.asm -l myfile.lst
```

If a list file is selected, you may turn off listing for a section of your source with `[list -]`, and turn it back on with `[list +]`, (the default, obviously). There is no "user form" (without the brackets). This can be used to list only sections of interest, avoiding excessively long listings.

2.1.4 The `-L` Option: Additional or Modified Listing Info

Use this option to specify listing output details.

Supported options are:

- Lb show builtin macro packages (standard and %use)
- Ld show byte and repeat counts in decimal, not hex
- Le show the preprocessed input
- Lf ignore `.no`list and force listing output
- Lm show multi-line macro calls with expanded parameters
- Lp output a list file in every pass, in case of errors
- Ls show all single-line macro definitions
- Lw flush the output after every line (very slow!)
- L+ enable *all* listing options

These options can be enabled or disabled at runtime using the `%pragma list options` directive:

```
%pragma list options [+|-]flags...
```

2.1.5 The `-M` Option: Generate Makefile Dependencies

This option can be used to generate makefile dependencies on stdout. This can be redirected to a file for further processing. For example:

```
nasm -M myfile.asm > myfile.dep
```

2.1.6 The `-MG` Option: Generate Makefile Dependencies

This option can be used to generate makefile dependencies on stdout. This differs from the `-M` option in that if a nonexisting file is encountered, it is assumed to be a generated file and is added to the dependency list without a prefix.

2.1.7 The `-MF` Option: Set Makefile Dependency File

This option can be used with the `-M` or `-MG` options to send the output to a file, rather than to stdout. For example:

```
nasm -M -MF myfile.dep myfile.asm
```

2.1.8 The `-MD` Option: Assemble and Generate Dependencies

The `-MD` option acts as the combination of the `-M` and `-MF` options (i.e. a filename has to be specified.) However, unlike the `-M` or `-MG` options, `-MD` does *not* inhibit the normal operation of the assembler. Use this to automatically generate updated dependencies with every assembly session. For example:

```
nasm -f elf -o myfile.o -MD myfile.dep myfile.asm
```

If the argument after `-MD` is an option rather than a filename, then the output filename is the first applicable one of:

- the filename set in the `-MF` option;
- the output filename from the `-o` option with `.d` appended;
- the input filename with the extension set to `.d`.

2.1.9 The `-MT` Option: Dependency Target Name

The `-MT` option can be used to override the default name of the dependency target. This is normally the same as the output filename, specified by the `-o` option.

2.1.10 The `-MQ` Option: Dependency Target Name (Quoted)

The `-MQ` option acts as the `-MT` option, except it tries to quote characters that have special meaning in Makefile syntax. This is not foolproof, as not all characters with special meaning are quotable in Make. The default output (if no `-MT` or `-MQ` option is specified) is automatically quoted.

2.1.11 The `-MP` Option: Emit phony targets

When used with any of the dependency generation options, the `-MP` option causes NASM to emit a phony target without dependencies for each header file. This prevents Make from complaining if a header file has been removed.

2.1.12 The `-MW` Option: Watcom Make quoting style

This option causes NASM to attempt to quote dependencies according to Watcom Make conventions rather than POSIX Make conventions (also used by most other Make variants.) This quotes `#` as `$#` rather than `\#`, uses `&` rather than `\` for continuation lines, and encloses filenames containing whitespace in double quotes.

2.1.13 The `-F` Option: Selecting a Debug Information Format

This option is used to select the format of the debug information emitted into the output file, to be used by a debugger (or *will be*). Prior to version 2.03.01, the use of this switch did *not* enable output of the selected debug info format. Use `-g`, see section 2.1.14, to enable output. Versions 2.03.01 and later automatically enable `-g` if `-F` is specified.

A complete list of the available debug file formats for an output format can be seen by issuing the command `nasm -h`. Not all output formats currently support debugging output.

This should not be confused with the `-f dbg` output format option, see section 8.14.

2.1.14 The `-g` Option: Enabling Debug Information.

This option can be used to generate debugging information in the specified format. See section 2.1.13. Using `-g` without `-F` results in emitting debug info in the default format, if any, for the selected output format. If no debug information is currently implemented in the selected output format, `-g` is *silently ignored*.

2.1.15 The `-X` Option: Selecting an Error Reporting Format

This option can be used to select an error reporting format for any error messages that might be produced by NASM.

Currently, two error reporting formats may be selected. They are the `-Xvc` option and the `-Xgnu` option. The GNU format is the default and looks like this:

```
filename.asm:65: error: specific error message
```

where `filename.asm` is the name of the source file in which the error was detected, `65` is the source file line number on which the error was detected, `error` is the severity of the error (this could be warning), and `specific error message` is a more detailed text message which should help pinpoint the exact problem.

The other format, specified by `-Xvc` is the style used by Microsoft Visual C++ and some other programs. It looks like this:

```
filename.asm(65) : error: specific error message
```

where the only difference is that the line number is in parentheses instead of being delimited by colons.

See also the Visual C++ output format, section 8.5.

2.1.16 The `-Z` Option: Send Errors to a File

Under MS-DOS it can be difficult (though there are ways) to redirect the standard-error output of a program to a file. Since NASM usually produces its warning and error messages on `stderr`, this can make it hard to capture the errors if (for example) you want to load them into an editor.

NASM therefore provides the `-Z` option, taking a filename argument which causes errors to be sent to the specified files rather than standard error. Therefore you can redirect the errors into a file by typing

```
nasm -Z myfile.err -f obj myfile.asm
```

In earlier versions of NASM, this option was called `-E`, but it was changed since `-E` is an option conventionally used for preprocessing only, with disastrous results. See section 2.1.22.

2.1.17 The `-s` Option: Send Errors to `stdout`

The `-s` option redirects error messages to `stdout` rather than `stderr`, so it can be redirected under MS-DOS. To assemble the file `myfile.asm` and pipe its output to the more program, you can type:

```
nasm -s -f obj myfile.asm | more
```

See also the `-Z` option, section 2.1.16.

2.1.18 The `-i` Option: Include File Search Directories

When NASM sees the `%include` or `%pathsearch` directive in a source file (see section 4.6.1, section 4.6.2 or section 3.2.3), it will search for the given file not only in the current directory, but also in any

directories specified on the command line by the use of the `-i` option. Therefore you can include files from a macro library, for example, by typing

```
nasm -ic:\macro\lib\ -f obj myfile.asm
```

(As usual, a space between `-i` and the path name is allowed, and optional).

Prior NASM 2.14 a path provided in the option has been considered as a verbatim copy and providing a path separator been up to a caller. One could implicitly concatenate a search path together with a filename. Still this was rather a trick than something useful. Now the trailing path separator is made to always present, thus `-i foo` will be considered as the `-i foo/` directory.

If you want to define a *standard* include search path, similar to `/usr/include` on Unix systems, you should place one or more `-i` directives in the `NASMENV` environment variable (see section 2.1.34).

For Makefile compatibility with many C compilers, this option can also be specified as `-I`.

2.1.19 The `-p` Option: Pre-Include a File

NASM allows you to specify files to be *pre-included* into your source file, by the use of the `-p` option. So running

```
nasm myfile.asm -p myinc.inc
```

is equivalent to running `nasm myfile.asm` and placing the directive `%include "myinc.inc"` at the start of the file.

`--include` option is also accepted.

For consistency with the `-I`, `-D` and `-U` options, this option can also be specified as `-P`.

2.1.20 The `-d` Option: Pre-Define a Macro

Just as the `-p` option gives an alternative to placing `%include` directives at the start of a source file, the `-d` option gives an alternative to placing a `%define` directive. You could code

```
nasm myfile.asm -dFOO=100
```

as an alternative to placing the directive

```
%define FOO 100
```

at the start of the file. You can miss off the macro value, as well: the option `-dFOO` is equivalent to coding `%define FOO`. This form of the directive may be useful for selecting assembly-time options which are then tested using `%ifdef`, for example `-dDEBUG`.

For Makefile compatibility with many C compilers, this option can also be specified as `-D`.

2.1.21 The `-u` Option: Undefine a Macro

The `-u` option undefines a macro that would otherwise have been pre-defined, either automatically or by a `-p` or `-d` option specified earlier on the command lines.

For example, the following command line:

```
nasm myfile.asm -dFOO=100 -uFOO
```

would result in `FOO` *not* being a predefined macro in the program. This is useful to override options specified at a different point in a Makefile.

For Makefile compatibility with many C compilers, this option can also be specified as `-U`.

2.1.22 The `-E` Option: Preprocess Only

NASM allows the preprocessor to be run on its own, up to a point. Using the `-E` option (which requires no arguments) will cause NASM to preprocess its input file, expand all the macro references, remove all

the comments and preprocessor directives, and print the resulting file on standard output (or save it to a file, if the `-o` option is also used).

This option cannot be applied to programs which require the preprocessor to evaluate expressions which depend on the values of symbols: so code such as

```
%assign tablesize ($-tablestart)
```

will cause an error in preprocess-only mode.

For compatibility with older version of NASM, this option can also be written `-e`. `-E` in older versions of NASM was the equivalent of the current `-Z` option, section 2.1.16.

2.1.23 The `-a` Option: Don't Preprocess At All

If NASM is being used as the back end to a compiler, it might be desirable to suppress preprocessing completely and assume the compiler has already done it, to save time and increase compilation speeds. The `-a` option, requiring no argument, instructs NASM to replace its powerful preprocessor with a stub preprocessor which does nothing.

2.1.24 The `-O` Option: Specifying Multipass Optimization

Using the `-O` option, you can tell NASM to carry out different levels of optimization. Multiple flags can be specified after the `-O` options, some of which can be combined in a single option, e.g. `-Oxv`.

- `-O0`: No optimization. All operands take their long forms, if a short form is not specified, except conditional jumps. This is intended to match NASM 0.98 behavior.
- `-O1`: Minimal optimization. As above, but immediate operands which will fit in a signed byte are optimized, unless the long form is specified. Conditional jumps default to the long form unless otherwise specified.
- `-Ox` (where `x` is the actual letter `x`): Multipass optimization. Minimize branch offsets and signed immediate bytes, overriding size specification unless the `strict` keyword has been used (see section 3.7). For compatibility with earlier releases, the letter `x` may also be any number greater than one. This number has no effect on the actual number of passes.
- `-Ov`: At the end of assembly, print the number of passes actually executed.

The `-Ox` mode is recommended for most uses, and is the default since NASM 2.09.

Note that this is a capital `O`, and is different from a small `o`, which is used to specify the output file name. See section 2.1.1.

2.1.25 The `-t` Option: Enable TASM Compatibility Mode

NASM includes a limited form of compatibility with Borland's TASM. When NASM's `-t` option is used, the following changes are made:

- local labels may be prefixed with `@@` instead of `.`
- size override is supported within brackets. In TASM compatible mode, a size override inside square brackets changes the size of the operand, and not the address type of the operand as it does in NASM syntax. E.g. `mov eax, [DWORD val]` is valid syntax in TASM compatibility mode. Note that you lose the ability to override the default address type for the instruction.
- unprefixed forms of some directives supported (`arg`, `elif`, `else`, `endif`, `if`, `ifdef`, `ifdifi`, `ifndef`, `include`, `local`)

2.1.26 The `-w` and `-W` Options: Enable or Disable Assembly Warnings

NASM can observe many conditions during the course of assembly which are worth mentioning to the user, but not a sufficiently severe error to justify NASM refusing to generate an output file. These

conditions are reported like errors, but come up with the word 'warning' before the message. Warnings do not prevent NASM from generating an output file and returning a success status to the operating system.

Some conditions are even less severe than that: they are only sometimes worth mentioning to the user. Therefore NASM supports the `-w` command-line option, which enables or disables certain classes of assembly warning. Such warning classes are described by a name, for example `label-orphan`; you can enable warnings of this class by the command-line option `-w+label-orphan` and disable it by `-w-label-orphan`.

The current warning classes are:

- `all` is a group alias for *all* warning classes. Thus, `-w+all` enables all available warnings, and `-w-all` disables warnings entirely (since NASM 2.13).
- `bad-pragma` is a backwards compatibility alias for `pragma-bad`.
- `bnd` warns about ineffective use of the BND prefix when the JMP instruction is converted to the SHORT form. This should be extremely rare since the short JMP only is applicable to jumps inside the same module, but if it is legitimate, it may be necessary to use `bnd jmp dword`.

Enabled by default.

- `environment` warns if a nonexistent environment variable is accessed using the `%!preprocessor` construct (see section 4.11.2.) Such environment variables are treated as empty (with this warning issued) starting in NASM 2.15; earlier versions of NASM would treat this as an error.

Enabled by default.

- `float` is a group alias for all warning classes prefixed by `float-`; currently `float-denorm`, `float-overflow`, `float-too-long`, and `float-underflow`.
- `float-denorm` warns about denormal floating point constants.

Disabled by default.

- `float-overflow` warns about floating point underflow.

Enabled by default.

- `float-too-long` warns about too many digits in floating-point numbers.

Enabled by default.

- `float-underflow` warns about floating point underflow (a nonzero constant rounded to zero.)

Disabled by default.

- `hle` warns about invalid use of the HLE XACQUIRE or XRELEASE prefixes.

Enabled by default.

- `label` is a group alias for all warning classes prefixed by `label-`; currently `label-orphan`, `label-redef`, and `label-redef-late`.

- `label-orphan` warns about source lines which contain no instruction but define a label without a trailing colon. This is most likely indicative of a typo, but is technically correct NASM syntax (see section 3.1.)

Enabled by default.

- `label-redef` warns if a label is defined more than once, but the value is identical. It is an unconditional error to define the same label more than once to *different* values.

Disabled by default.

- `label-redef-late` the value of a label changed during the final, code-generation pass. This may be the result of strange use of the preprocessor. This is very likely to produce incorrect code and may end up being an unconditional error in a future version of NASM.

Enabled and promoted to error by default.

- `lock` warns about `LOCK` prefixes on unlockable instructions.

Enabled by default.

- `macro` is a group alias for all warning classes prefixed by `macro-`; currently `macro-defaults`, `macro-params-legacy`, `macro-params-multi`, and `macro-params-single`.

- `macro-defaults` warns when a macro has more default parameters than optional parameters. See section 4.3.5 for why might want to disable this warning.

Enabled by default.

- `macro-params` is a group alias for all warning classes prefixed by `macro-params-`; currently `macro-params-legacy`, `macro-params-multi`, and `macro-params-single`.

- `macro-params-legacy` warns about multi-line macros being invoked with the wrong number of parameters, but for bug-compatibility with NASM versions older than 2.15, NASM tried to fix up the parameters to match the legacy behavior and call the macro anyway. This can happen in certain cases where there are empty arguments without braces, sometimes as a result of macro expansion.

The legacy behavior is quite strange and highly context-dependent, and can be disabled with:

```
%pragma preproc sane_empty_expansion true
```

It is highly recommended to use this option in new code.

Enabled by default.

- `macro-params-multi` warns about multi-line macros being invoked with the wrong number of parameters. See section 4.3.1 for an example of why you might want to disable this warning.

Enabled by default.

- `macro-params-single` warns about single-line macros being invoked with the wrong number of parameters.

Enabled by default.

- `negative-rep` warns about negative counts given to the `%rep` preprocessor directive.

Enabled by default.

- `not-my-pragma` is a backwards compatibility alias for `pragma-na`.

- `number-overflow` covers warnings about numeric constants which don't fit in 64 bits.

Enabled by default.

- `obsolete` is a group alias for all warning classes prefixed by `obsolete-`; currently `obsolete-nop`, `obsolete-removed`, and `obsolete-valid`.

- `obsolete-nop` warns for an instruction which has been removed from the architecture, but has been architecturally defined to be a noop for future CPUs.

Enabled by default.

- `obsolete-removed` warns for an instruction which has been removed from the architecture, and is no longer included in the CPU definition given in the `[CPU]` directive, for example `POP CS`, the opcode for which, `0Fh`, instead is an opcode prefix on CPUs newer than the first generation 8086.

Enabled by default.

- `obsolete-valid` warns for an instruction which has been removed from the architecture, but is still valid on the specific CPU given in the CPU directive. Code using these instructions is most likely not forward compatible.

Enabled by default.

- `orphan-labels` is a backwards compatibility alias for `label-orphan`.
- `other` specifies any warning not included in any specific warning class.

Enabled by default.

- `phase` warns about symbols having changed values during the second-to-last assembly pass. This is not inherently fatal, but may be a source of bugs.

Disabled by default.

- `pragma` is a group alias for all warning classes prefixed by `pragma-`; currently `pragma-bad`, `pragma-empty`, `pragma-na`, and `pragma-unknown`.

- `pragma-bad` warns about a malformed or otherwise unparsable `%pragma` directive.

Disabled by default.

- `pragma-empty` warns about a `%pragma` directive containing nothing. This is treated identically to `%pragma ignore` except for this optional warning.

Disabled by default.

- `pragma-na` warns about a `%pragma` directive which is not applicable to this particular assembly session. This is not yet implemented.

Disabled by default.

- `pragma-unknown` warns about an unknown `%pragma` directive. This is not yet implemented for most cases.

Disabled by default.

- `ptr` warns about keywords used in other assemblers that might indicate a mistake in the source code. Currently only the MASM PTR keyword is recognized.

Enabled by default.

- `regsize` warns about a register with implicit size (such as EAX, which is always 32 bits) been given an explicit size specification which is inconsistent with the size of the named register, e.g. `WORD EAX`, `DWORD EAX` or `WORD AX` are permitted, and do not trigger this warning. Some registers which *do not* imply a specific size, such as `K0`, may need this specification unless the instruction itself implies the instruction size:

```

KMOVW K0,[foo]           ; Permitted, KMOVW implies 16 bits
KMOV  WORD K0,[foo]      ; Permitted, WORD K0 specifies instruction size
KMOV  K0,WORD [foo]      ; Permitted, WORD [foo] specifies instruction size
KMOV  K0,[foo]           ; Not permitted, instruction size ambiguous

```

Enabled by default.

- `unknown-pragma` is a backwards compatibility alias for `pragma-unknown`.
- `unknown-warning` warns about a `-w` or `-W` option or a `[WARNING]` directive that contains an unknown warning name or is otherwise not possible to process.

Disabled by default.

- `user` controls output of `%warning` directives (see section 4.9).

Enabled by default.

- `warn-stack-empty` a [WARNING POP] directive was executed when the warning stack is empty. This is treated as a [WARNING *all] directive.

Enabled by default.

- `zeroing` a RESx directive was used in a section which contains initialized data, and the output format does not support this. Instead, this will be replaced with explicit zero content, which may produce a large output file.

Enabled by default.

- `zext-reloc` warns that a relocation has been zero-extended due to limitations in the output format.

Enabled by default.

Since version 2.15, NASM has group aliases for all prefixed warnings, so they can be used to enable or disable all warnings in the group. For example, `-w+float` enables all warnings with names starting with `float-*`.

Since version 2.00, NASM has also supported the gcc-like syntax `-Wwarning-class` and `-Wno-warning-class` instead of `-w+warning-class` and `-w-warning-class`, respectively; both syntaxes work identically.

The option `-w+error` or `-Werror` can be used to treat warnings as errors. This can be controlled on a per warning class basis (`-w+error=warning-class` or `-Werror=warning-class`); if no `warning-class` is specified NASM treats it as `-w+error=all`; the same applies to `-w-error` or `-Wno-error`, of course.

In addition, you can control warnings in the source code itself, using the [WARNING] directive. See section 7.13.

2.1.27 The `-v` Option: Display Version Info

Typing `NASM -v` will display the version of NASM which you are using, and the date on which it was compiled.

You will need the version number if you report a bug.

For command-line compatibility with Yasm, the form `--v` is also accepted for this option starting in NASM version 2.11.05.

2.1.28 The `--(g|l)prefix`, `--(g|l)postfix` Options.

The `--(g)prefix` options prepend the given argument to all `extern`, `common`, `static`, and `global` symbols, and the `--lprefix` option prepends to all other symbols. Similarly, `--(g)postfix` and `--lpostfix` options append the argument in the exactly same way as the `--xxprefix` options does.

Running this:

```
nasm -f macho --gprefix _
```

is equivalent to place the directive with `%pragma macho gprefix _` at the start of the file (section 7.10). It will prepend the underscore to all global and external variables, as C requires it in some, but not all, system calling conventions.

2.1.29 The `--pragma` Option

NASM accepts an argument as `%pragma` option, which is like placing a `%pragma` preprocess statement at the beginning of the source. Running this:

```
nasm -f macho --pragma "macho gprefix _"
```

is equivalent to the example in section 2.1.28.

2.1.30 The `--before` Option

A preprocess statement can be accepted with this option. The example shown in section 2.1.29 is the same as running this:

```
nasm -f macho --before "%pragma macho gprefix _"
```

2.1.31 The `--limit-X` Option

This option allows user to setup various maximum values for these:

- `--limit-passes`: Number of maximum allowed passes. Default is effectively unlimited.
- `--limit-stalled-passes`: Maximum number of allowed unfinished passes. Default is 1000.
- `--limit-macro-levels`: Define maximum depth of macro expansion (in preprocess). Default is 10000
- `--limit-macro-tokens`: Maximum number of tokens processed during single-line macro expansion. Default is 10000000.
- `--limit-mmacros`: Maximum number of multi-line macros processed before returning to the top-level input. Default is 100000.
- `--limit-rep`: Maximum number of allowed preprocessor loop, defined under `%rep`. Default is 1000000.
- `--limit-eval`: This number sets the boundary condition of allowed expression length. Default is 8192 on most systems.
- `--limit-lines`: Total number of source lines as allowed to be processed. Default is 2000000000.

In example, running this limits the maximum line count to be 1000.

```
nasm --limit-lines 1000
```

2.1.32 The `--keep-all` Option

This option prevents NASM from deleting any output files even if an error happens.

2.1.33 The `--no-line` Option

If this option is given, all `%line` directives in the source code are ignored. This can be useful for debugging already preprocessed code. See section 4.11.1.

2.1.34 The `NASMENV` Environment Variable

If you define an environment variable called `NASMENV`, the program will interpret it as a list of extra command-line options, which are processed before the real command line. You can use this to define standard search directories for include files, by putting `-i` options in the `NASMENV` variable.

The value of the variable is split up at white space, so that the value `-s -ic:\nasmlib\` will be treated as two separate options. However, that means that the value `-dNAME="my name"` won't do what you might want, because it will be split at the space and the NASM command-line processing will get confused by the two nonsensical words `-dNAME="my and name"`.

To get round this, NASM provides a feature whereby, if you begin the `NASMENV` environment variable with some character that isn't a minus sign, then NASM will treat this character as the separator character for options. So setting the `NASMENV` variable to the value `!-s!-ic:\nasmlib\` is equivalent to setting it to `-s -ic:\nasmlib\`, but `!-dNAME="my name"` will work.

This environment variable was previously called NASM. This was changed with version 0.98.31.

2.2 Quick Start for MASM Users

If you're used to writing programs with MASM, or with TASM in MASM-compatible (non-Ideal) mode, or with a86, this section attempts to outline the major differences between MASM's syntax and NASM's. If you're not already used to MASM, it's probably worth skipping this section.

2.2.1 NASM Is Case-Sensitive

One simple difference is that NASM is case-sensitive. It makes a difference whether you call your label `foo`, `Foo` or `FOO`. If you're assembling to DOS or OS/2 `.OBJ` files, you can invoke the `UPPERCASE` directive (documented in section 8.4) to ensure that all symbols exported to other code modules are forced to be upper case; but even then, *within* a single module, NASM will distinguish between labels differing only in case.

2.2.2 NASM Requires Square Brackets For Memory References

NASM was designed with simplicity of syntax in mind. One of the design goals of NASM is that it should be possible, as far as is practical, for the user to look at a single line of NASM code and tell what opcode is generated by it. You can't do this in MASM: if you declare, for example,

```
foo    equ    1
bar    dw    2
```

then the two lines of code

```
    mov    ax,foo
    mov    ax,bar
```

generate completely different opcodes, despite having identical-looking syntaxes.

NASM avoids this undesirable situation by having a much simpler syntax for memory references. The rule is simply that any access to the *contents* of a memory location requires square brackets around the address, and any access to the *address* of a variable doesn't. So an instruction of the form `mov ax,foo` will *always* refer to a compile-time constant, whether it's an `EQU` or the address of a variable; and to access the *contents* of the variable `bar`, you must code `mov ax,[bar]`.

This also means that NASM has no need for MASM's `OFFSET` keyword, since the MASM code `mov ax,offset bar` means exactly the same thing as NASM's `mov ax,bar`. If you're trying to get large amounts of MASM code to assemble sensibly under NASM, you can always code `%define offset` to make the preprocessor treat the `OFFSET` keyword as a no-op.

This issue is even more confusing in a86, where declaring a label with a trailing colon defines it to be a 'label' as opposed to a 'variable' and causes a86 to adopt NASM-style semantics; so in a86, `mov ax,var` has different behaviour depending on whether `var` was declared as `var: dw 0` (a label) or `var dw 0` (a word-size variable). NASM is very simple by comparison: *everything* is a label.

NASM, in the interests of simplicity, also does not support the hybrid syntaxes supported by MASM and its clones, such as `mov ax,table[bx]`, where a memory reference is denoted by one portion outside square brackets and another portion inside. The correct syntax for the above is `mov ax,[table+bx]`. Likewise, `mov ax,es:[di]` is wrong and `mov ax,[es:di]` is right.

2.2.3 NASM Doesn't Store Variable Types

NASM, by design, chooses not to remember the types of variables you declare. Whereas MASM will remember, on seeing `var dw 0`, that you declared `var` as a word-size variable, and will then be able to fill in the ambiguity in the size of the instruction `mov var,2`, NASM will deliberately remember nothing about the symbol `var` except where it begins, and so you must explicitly code `mov word [var],2`.

For this reason, NASM doesn't support the LODS, MOVS, STOS, SCAS, CMPS, INS, or OUTS instructions, but only supports the forms such as LODSB, MOVSW, and SCASD, which explicitly specify the size of the components of the strings being manipulated.

2.2.4 NASM Doesn't ASSUME

As part of NASM's drive for simplicity, it also does not support the ASSUME directive. NASM will not keep track of what values you choose to put in your segment registers, and will never *automatically* generate a segment override prefix.

2.2.5 NASM Doesn't Support Memory Models

NASM also does not have any directives to support different 16-bit memory models. The programmer has to keep track of which functions are supposed to be called with a far call and which with a near call, and is responsible for putting the correct form of RET instruction (RETN or RETF; NASM accepts RET itself as an alternate form for RETN); in addition, the programmer is responsible for coding CALL FAR instructions where necessary when calling *external* functions, and must also keep track of which external variable definitions are far and which are near.

2.2.6 Floating-Point Differences

NASM uses different names to refer to floating-point registers from MASM: where MASM would call them ST(0), ST(1) and so on, and a86 would call them simply 0, 1 and so on, NASM chooses to call them st0, st1 etc.

As of version 0.96, NASM now treats the instructions with 'nowait' forms in the same way as MASM-compatible assemblers. The idiosyncratic treatment employed by 0.95 and earlier was based on a misunderstanding by the authors.

2.2.7 Other Differences

For historical reasons, NASM uses the keyword TWORD where MASM and compatible assemblers use TBYTE.

NASM does not declare uninitialized storage in the same way as MASM: where a MASM programmer might use `stack db 64 dup (?)`, NASM requires `stack resb 64`, intended to be read as 'reserve 64 bytes'. For a limited amount of compatibility, since NASM treats ? as a valid character in symbol names, you can code `? equ 0` and then writing `dw ?` will at least do something vaguely useful. DUP is still not a supported syntax, however.

In addition to all of this, macros and directives work completely differently to MASM. See chapter 4 and chapter 7 for further details.

2.2.8 MASM compatibility package

See section 6.5.

Chapter 3: The NASM Language

3.1 Layout of a NASM Source Line

Like most assemblers, each NASM source line contains (unless it is a macro, a preprocessor directive or an assembler directive: see chapter 4 and chapter 7) some combination of the four fields

```
label:    instruction operands        ; comment
```

As usual, most of these fields are optional; the presence or absence of any combination of a label, an instruction and a comment is allowed. Of course, the operand field is either required or forbidden by the presence and nature of the instruction field.

NASM uses backslash (\) as the line continuation character; if a line ends with backslash, the next line is considered to be a part of the backslash-ended line.

NASM places no restrictions on white space within a line: labels may have white space before them, or instructions may have no space before them, or anything. The colon after a label is also optional. (Note that this means that if you intend to code `lodsrb` alone on a line, and type `lodab` by accident, then that's still a valid source line which does nothing but define a label. Running NASM with the command-line option `-w+orphan-labels` will cause it to warn you if you define a label alone on a line without a trailing colon.)

Valid characters in labels are letters, numbers, `_`, `$`, `#`, `@`, `~`, `.`, and `?`. The only characters which may be used as the *first* character of an identifier are letters, `.` (with special meaning: see section 3.9), `_` and `?`. An identifier may also be prefixed with a `$` to indicate that it is intended to be read as an identifier and not a reserved word; thus, if some other module you are linking with defines a symbol called `eax`, you can refer to `$eax` in NASM code to distinguish the symbol from the register. Maximum length of an identifier is 4095 characters.

The instruction field may contain any machine instruction: Pentium and P6 instructions, FPU instructions, MMX instructions and even undocumented instructions are all supported. The instruction may be prefixed by `LOCK`, `REP`, `REPE/REPZ`, `REPNE/REPNZ`, `XACQUIRE/XRELEASE` or `BND/NOBND`, in the usual way. Explicit address-size and operand-size prefixes `A16`, `A32`, `A64`, `O16` and `O32`, `O64` are provided – one example of their use is given in chapter 11. You can also use the name of a segment register as an instruction prefix: coding `es mov [bx],ax` is equivalent to coding `mov [es:bx],ax`. We recommend the latter syntax, since it is consistent with other syntactic features of the language, but for instructions such as `LODSB`, which has no operands and yet can require a segment override, there is no clean syntactic way to proceed apart from `es lodsb`.

An instruction is not required to use a prefix: prefixes such as `CS`, `A32`, `LOCK` or `REPE` can appear on a line by themselves, and NASM will just generate the prefix bytes.

In addition to actual machine instructions, NASM also supports a number of pseudo-instructions, described in section 3.2.

Instruction operands may take a number of forms: they can be registers, described simply by the register name (e.g. `ax`, `bp`, `ebx`, `cr0`: NASM does not use the `gas`-style syntax in which register names must be prefixed by a `%` sign), or they can be effective addresses (see section 3.3), constants (section 3.4) or expressions (section 3.5).

For x87 floating-point instructions, NASM accepts a wide range of syntaxes: you can use two-operand forms like MASM supports, or you can use NASM's native single-operand forms in most cases. For example, you can code:

```
fadd    st1                ; this sets st0 := st0 + st1
fadd    st0,st1            ; so does this
```

```

fadd    st1,st0        ; this sets st1 := st1 + st0
fadd    to st1         ; so does this

```

Almost any x87 floating-point instruction that references memory must use one of the prefixes DWORD, QWORD or TWORD to indicate what size of memory operand it refers to.

3.2 Pseudo-Instructions

Pseudo-instructions are things which, though not real x86 machine instructions, are used in the instruction field anyway because that's the most convenient place to put them. The current pseudo-instructions are DB, DW, DD, DQ, DT, DO, DY and DZ; their uninitialized counterparts RESB, RESW, RESD, RESQ, REST, RESO, RESY and RESZ; the INCBIN command, the EQU command, and the TIMES prefix.

3.2.1 DB and Friends: Declaring Initialized Data

DB, DW, DD, DQ, DT, DO, DY and DZ are used, much as in MASM, to declare initialized data in the output file. They can be invoked in a wide range of ways:

```

db      0x55           ; just the byte 0x55
db      0x55,0x56,0x57 ; three bytes in succession
db      'a',0x55       ; character constants are OK
db      'hello',13,10,'$' ; so are string constants
dw      0x1234         ; 0x34 0x12
dw      'a'           ; 0x61 0x00 (it's just a number)
dw      'ab'          ; 0x61 0x62 (character constant)
dw      'abc'         ; 0x61 0x62 0x63 0x00 (string)
dd      0x12345678     ; 0x78 0x56 0x34 0x12
dd      1.234567e20   ; floating-point constant
dq      0x123456789abcdef0 ; eight byte constant
dq      1.234567e20   ; double-precision float
dt      1.234567e20   ; extended-precision float

```

DT, DO, DY and DZ do not accept numeric constants as operands.

3.2.2 RESB and Friends: Declaring Uninitialized Data

RESB, RESW, RESD, RESQ, REST, RESO, RESY and RESZ are designed to be used in the BSS section of a module: they declare *uninitialized* storage space. Each takes a single operand, which is the number of bytes, words, doublewords or whatever to reserve. As stated in section 2.2.7, NASM does not support the MASM/TASM syntax of reserving uninitialized space by writing DW ? or similar things: this is what it does instead. The operand to a RESB-type pseudo-instruction is a *critical expression*: see section 3.8.

For example:

```

buffer:      resb    64           ; reserve 64 bytes
wordvar:     resw    1           ; reserve a word
realarray   resq    10          ; array of ten reals
ymmval:     resy    1           ; one YMM register
zmmvals:    resz    32          ; 32 ZMM registers

```

3.2.3 INCBIN: Including External Binary Files

INCBIN is borrowed from the old Amiga assembler DevPac: it includes a binary file verbatim into the output file. This can be handy for (for example) including graphics and sound data directly into a game executable file. It can be called in one of these three ways:

```

incbin "file.dat"           ; include the whole file
incbin "file.dat",1024     ; skip the first 1024 bytes

```

```
incbin "file.dat",1024,512    ; skip the first 1024, and
                             ; actually include at most 512
```

INCBIN is both a directive and a standard macro; the standard macro version searches for the file in the include file search path and adds the file to the dependency lists. This macro can be overridden if desired.

3.2.4 EQU: Defining Constants

EQU defines a symbol to a given constant value: when EQU is used, the source line must contain a label. The action of EQU is to define the given label name to the value of its (only) operand. This definition is absolute, and cannot change later. So, for example,

```
message      db      'hello, world'
msglen       equ     $-message
```

defines msglen to be the constant 12. msglen may not then be redefined later. This is not a preprocessor definition either: the value of msglen is evaluated *once*, using the value of \$ (see section 3.5 for an explanation of \$) at the point of definition, rather than being evaluated wherever it is referenced and using the value of \$ at the point of reference.

3.2.5 TIMES: Repeating Instructions or Data

The TIMES prefix causes the instruction to be assembled multiple times. This is partly present as NASM's equivalent of the DUP syntax supported by MASM-compatible assemblers, in that you can code

```
zerobuf:     times 64 db 0
```

or similar things; but TIMES is more versatile than that. The argument to TIMES is not just a numeric constant, but a numeric *expression*, so you can do things like

```
buffer: db    'hello, world'
         times 64-$+buffer db ' '
```

which will store exactly enough spaces to make the total length of buffer up to 64. Finally, TIMES can be applied to ordinary instructions, so you can code trivial unrolled loops in it:

```
times 100 movsb
```

Note that there is no effective difference between times 100 resb 1 and resb 100, except that the latter will be assembled about 100 times faster due to the internal structure of the assembler.

The operand to TIMES is a critical expression (section 3.8).

Note also that TIMES can't be applied to macros: the reason for this is that TIMES is processed after the macro phase, which allows the argument to TIMES to contain expressions such as 64-\$+buffer as above. To repeat more than one line of code, or a complex macro, use the preprocessor %rep directive.

3.3 Effective Addresses

An effective address is any operand to an instruction which references memory. Effective addresses, in NASM, have a very simple syntax: they consist of an expression evaluating to the desired address, enclosed in square brackets. For example:

```
wordvar dw    123
         mov   ax,[wordvar]
         mov   ax,[wordvar+1]
         mov   ax,[es:wordvar+bx]
```

Anything not conforming to this simple system is not a valid memory reference in NASM, for example es:wordvar[bx].

More complicated effective addresses, such as those involving more than one register, work in exactly the same way:

```
mov    eax, [ebx*2+ecx+offset]
mov    ax, [bp+di+8]
```

NASM is capable of doing algebra on these effective addresses, so that things which don't necessarily *look* legal are perfectly all right:

```
mov    eax, [ebx*5]           ; assembles as [ebx*4+ebx]
mov    eax, [label1*2-label2] ; ie [label1+(label1-label2)]
```

Some forms of effective address have more than one assembled form; in most such cases NASM will generate the smallest form it can. For example, there are distinct assembled forms for the 32-bit effective addresses `[eax*2+0]` and `[eax+eax]`, and NASM will generally generate the latter on the grounds that the former requires four bytes to store a zero offset.

NASM has a hinting mechanism which will cause `[eax+ebx]` and `[ebx+eax]` to generate different opcodes; this is occasionally useful because `[esi+ebp]` and `[ebp+esi]` have different default segment registers.

However, you can force NASM to generate an effective address in a particular form by the use of the keywords `BYTE`, `WORD`, `DWORD` and `NOSPLIT`. If you need `[eax+3]` to be assembled using a double-word offset field instead of the one byte NASM will normally generate, you can code `[dword eax+3]`. Similarly, you can force NASM to use a byte offset for a small value which it hasn't seen on the first pass (see section 3.8 for an example of such a code fragment) by using `[byte eax+offset]`. As special cases, `[byte eax]` will code `[eax+0]` with a byte offset of zero, and `[dword eax]` will code it with a double-word offset of zero. The normal form, `[eax]`, will be coded with no offset field.

The form described in the previous paragraph is also useful if you are trying to access data in a 32-bit segment from within 16 bit code. For more information on this see the section on mixed-size addressing (section 11.2). In particular, if you need to access data with a known offset that is larger than will fit in a 16-bit value, if you don't specify that it is a dword offset, nasm will cause the high word of the offset to be lost.

Similarly, NASM will split `[eax*2]` into `[eax+eax]` because that allows the offset field to be absent and space to be saved; in fact, it will also split `[eax*2+offset]` into `[eax+eax+offset]`. You can combat this behaviour by the use of the `NOSPLIT` keyword: `[nosplit eax*2]` will force `[eax*2+0]` to be generated literally. `[nosplit eax*1]` also has the same effect. In another way, a split EA form `[0, eax*2]` can be used, too. However, `NOSPLIT` in `[nosplit eax+eax]` will be ignored because user's intention here is considered as `[eax+eax]`.

In 64-bit mode, NASM will by default generate absolute addresses. The `REL` keyword makes it produce RIP-relative addresses. Since this is frequently the normally desired behaviour, see the `DEFAULT` directive (section 7.2). The keyword `ABS` overrides `REL`.

A new form of split effective address syntax is also supported. This is mainly intended for mib operands as used by MPX instructions, but can be used for any memory reference. The basic concept of this form is splitting base and index.

```
mov    eax, [ebx+8, ecx*4]    ; ebx=base, ecx=index, 4=scale, 8=disp
```

For mib operands, there are several ways of writing effective address depending on the tools. NASM supports all currently possible ways of mib syntax:

```
; bndstx
; next 5 lines are parsed same
; base=rax, index=rbx, scale=1, displacement=3
bndstx [rax+0x3, rbx], bnd0    ; NASM - split EA
```

```

bndstx [rbx*1+rax+0x3], bnd0    ; GAS - '*1' indicates an index reg
bndstx [rax+rbx+3], bnd0       ; GAS - without hints
bndstx [rax+0x3], bnd0, rbx    ; ICC-1
bndstx [rax+0x3], rbx, bnd0    ; ICC-2

```

When broadcasting decorator is used, the `opsz` keyword should match the size of each element.

```

VDIVPS zmm4, zmm5, dword [rbx]{1to16} ; single-precision float
VDIVPS zmm4, zmm5, zword [rbx]         ; packed 512 bit memory

```

3.4 Constants

NASM understands four different types of constant: numeric, character, string and floating-point.

3.4.1 Numeric Constants

A numeric constant is simply a number. NASM allows you to specify numbers in a variety of number bases, in a variety of ways: you can suffix `H` or `X`, `D` or `T`, `Q` or `O`, and `B` or `Y` for hexadecimal, decimal, octal and binary respectively, or you can prefix `0x`, for hexadecimal in the style of `C`, or you can prefix `$` for hexadecimal in the style of Borland Pascal or Motorola Assemblers. Note, though, that the `$` prefix does double duty as a prefix on identifiers (see section 3.1), so a hex number prefixed with a `$` sign must have a digit after the `$` rather than a letter. In addition, current versions of NASM accept the prefix `0h` for hexadecimal, `0d` or `0t` for decimal, `0o` or `0q` for octal, and `0b` or `0y` for binary. Please note that unlike `C`, a `0` prefix by itself does *not* imply an octal constant!

Numeric constants can have underscores (`_`) interspersed to break up long strings.

Some examples (all producing exactly the same code):

```

mov    ax,200           ; decimal
mov    ax,0200         ; still decimal
mov    ax,0200d        ; explicitly decimal
mov    ax,0d200        ; also decimal
mov    ax,0c8h         ; hex
mov    ax,$0c8         ; hex again: the 0 is required
mov    ax,0xc8         ; hex yet again
mov    ax,0hc8         ; still hex
mov    ax,310q         ; octal
mov    ax,310o         ; octal again
mov    ax,0o310        ; octal yet again
mov    ax,0q310        ; octal yet again
mov    ax,11001000b    ; binary
mov    ax,1100_1000b   ; same binary constant
mov    ax,1100_1000y   ; same binary constant once more
mov    ax,0b1100_1000 ; same binary constant yet again
mov    ax,0y1100_1000 ; same binary constant yet again

```

3.4.2 Character Strings

A character string consists of up to eight characters enclosed in either single quotes (`'...'`), double quotes (`"..."`) or backquotes (`'...'`>). Single or double quotes are equivalent to NASM (except of course that surrounding the constant with single quotes allows double quotes to appear within it and vice versa); the contents of those are represented verbatim. Strings enclosed in backquotes support C-style \-escapes for special characters.`

The following escape sequences are recognized by backquoted strings:

```

\'      single quote (')
\"      double quote (")

```

<code>\‘</code>	backquote (‘)
<code>\\</code>	backslash (\)
<code>\?</code>	question mark (?)
<code>\a</code>	BEL (ASCII 7)
<code>\b</code>	BS (ASCII 8)
<code>\t</code>	TAB (ASCII 9)
<code>\n</code>	LF (ASCII 10)
<code>\v</code>	VT (ASCII 11)
<code>\f</code>	FF (ASCII 12)
<code>\r</code>	CR (ASCII 13)
<code>\e</code>	ESC (ASCII 27)
<code>\377</code>	Up to 3 octal digits - literal byte
<code>\xFF</code>	Up to 2 hexadecimal digits - literal byte
<code>\u1234</code>	4 hexadecimal digits - Unicode character
<code>\U12345678</code>	8 hexadecimal digits - Unicode character

All other escape sequences are reserved. Note that `\0`, meaning a NUL character (ASCII 0), is a special case of the octal escape sequence.

Unicode characters specified with `\u` or `\U` are converted to UTF-8. For example, the following lines are all equivalent:

```
db ‘\u263a’           ; UTF-8 smiley face
db ‘\xe2\x98\xba’   ; UTF-8 smiley face
db 0E2h, 098h, 0BAh ; UTF-8 smiley face
```

3.4.3 Character Constants

A character constant consists of a string up to eight bytes long, used in an expression context. It is treated as if it was an integer.

A character constant with more than one byte will be arranged with little-endian order in mind: if you code

```
mov eax, ‘abcd’
```

then the constant generated is not `0x61626364`, but `0x64636261`, so that if you were then to store the value into memory, it would read `abcd` rather than `dcba`. This is also the sense of character constants understood by the Pentium’s `CPUID` instruction.

3.4.4 String Constants

String constants are character strings used in the context of some pseudo-instructions, namely the `DB` family and `INCBIN` (where it represents a filename.) They are also used in certain preprocessor directives.

A string constant looks like a character constant, only longer. It is treated as a concatenation of maximum-size character constants for the conditions. So the following are equivalent:

```
db ‘hello’           ; string constant
db ‘h’, ‘e’, ‘l’, ‘l’, ‘o’ ; equivalent character constants
```

And the following are also equivalent:

```
dd ‘ninechars’       ; doubleword string constant
dd ‘nine’, ‘char’, ‘s’ ; becomes three doublewords
db ‘ninechars’, 0, 0, 0 ; and really looks like this
```

Note that when used in a string-supporting context, quoted strings are treated as a string constants even if they are short enough to be a character constant, because otherwise `db ‘ab’` would have the

same effect as `db 'a'`, which would be silly. Similarly, three-character or four-character constants are treated as strings when they are operands to `DW`, and so forth.

3.4.5 Unicode Strings

The special operators `__?utf16?__`, `__?utf16le?__`, `__?utf16be?__`, `__?utf32?__`, `__?utf32le?__` and `__?utf32be?__` allows definition of Unicode strings. They take a string in UTF-8 format and converts it to UTF-16 or UTF-32, respectively. Unless the `be` forms are specified, the output is littleendian.

For example:

```
%define u(x) __?utf16?__(x)
%define w(x) __?utf32?__(x)

        dw u('C:\WINDOWS'), 0      ; Pathname in UTF-16
        dd w('A + B = \u206a'), 0  ; String in UTF-32
```

The UTF operators can be applied either to strings passed to the `DB` family instructions, or to character constants in an expression context.

3.4.6 Floating-Point Constants

Floating-point constants are acceptable only as arguments to `DB`, `DW`, `DD`, `DQ`, `DT`, and `DO`, or as arguments to the special operators `__?float8?__`, `__?float16?__`, `__?float32?__`, `__?float64?__`, `__?float80m?__`, `__?float80e?__`, `__?float128l?__`, and `__?float128h?__`.

Floating-point constants are expressed in the traditional form: digits, then a period, then optionally more digits, then optionally an `E` followed by an exponent. The period is mandatory, so that `NASM` can distinguish between `dd 1`, which declares an integer constant, and `dd 1.0` which declares a floating-point constant.

`NASM` also support C99-style hexadecimal floating-point: `0x`, hexadecimal digits, period, optionally more hexadecimal digits, then optionally a `P` followed by a *binary* (not hexadecimal) exponent in decimal notation. As an extension, `NASM` additionally supports the `0h` and `$` prefixes for hexadecimal, as well binary and octal floating-point, using the `0b` or `0y` and `0o` or `0q` prefixes, respectively.

Underscores to break up groups of digits are permitted in floating-point constants as well.

Some examples:

```
db    -0.2                ; "Quarter precision"
dw    -0.5                ; IEEE 754r/SSE5 half precision
dd    1.2                 ; an easy one
dd    1.222_222_222      ; underscores are permitted
dd    0x1p+2             ; 1.0x2^2 = 4.0
dq    0x1p+32            ; 1.0x2^32 = 4 294 967 296.0
dq    1.e10              ; 10 000 000 000.0
dq    1.e+10             ; synonymous with 1.e10
dq    1.e-10             ; 0.000 000 000 1
dt    3.141592653589793238462 ; pi
do    1.e+4000           ; IEEE 754r quad precision
```

The 8-bit "quarter-precision" floating-point format is sign:exponent:mantissa = 1:4:3 with an exponent bias of 7. This appears to be the most frequently used 8-bit floating-point format, although it is not covered by any formal standard. This is sometimes called a "minifloat."

The special operators are used to produce floating-point numbers in other contexts. They produce the binary representation of a specific floating-point number as an integer, and can use anywhere integer

constants are used in an expression. `__?float80m?__` and `__?float80e?__` produce the 64-bit mantissa and 16-bit exponent of an 80-bit floating-point number, and `__?float128l?__` and `__?float128h?__` produce the lower and upper 64-bit halves of a 128-bit floating-point number, respectively.

For example:

```
mov    rax,__?float64?__(3.141592653589793238462)
```

... would assign the binary representation of pi as a 64-bit floating point number into RAX. This is exactly equivalent to:

```
mov    rax,0x400921fb54442d18
```

NASM cannot do compile-time arithmetic on floating-point constants. This is because NASM is designed to be portable – although it always generates code to run on x86 processors, the assembler itself can run on any system with an ANSI C compiler. Therefore, the assembler cannot guarantee the presence of a floating-point unit capable of handling the Intel number formats, and so for NASM to be able to do floating arithmetic it would have to include its own complete set of floating-point routines, which would significantly increase the size of the assembler for very little benefit.

The special tokens `__?Infinity?__`, `__?QNaN?__` (or `__?NaN?__`) and `__?SNaN?__` can be used to generate infinities, quiet NaNs, and signalling NaNs, respectively. These are normally used as macros:

```
%define Inf __?Infinity?__
%define NaN __?QNaN?__
```

```
        dq    +1.5, -Inf, NaN            ; Double-precision constants
```

The `%use fp` standard macro package contains a set of convenience macros. See section 6.3.

3.4.7 Packed BCD Constants

x87-style packed BCD constants can be used in the same contexts as 80-bit floating-point numbers. They are suffixed with `p` or prefixed with `0p`, and can include up to 18 decimal digits.

As with other numeric constants, underscores can be used to separate digits.

For example:

```
dt 12_345_678_901_245_678p
dt -12_345_678_901_245_678p
dt +0p33
dt 33p
```

3.5 Expressions

Expressions in NASM are similar in syntax to those in C. Expressions are evaluated as 64-bit integers which are then adjusted to the appropriate size.

NASM supports two special tokens in expressions, allowing calculations to involve the current assembly position: the `$` and `$$` tokens. `$` evaluates to the assembly position at the beginning of the line containing the expression; so you can code an infinite loop using `JMP $`. `$$` evaluates to the beginning of the current section; so you can tell how far into the section you are by using `($-$)`.

The arithmetic operators provided by NASM are listed here, in increasing order of precedence.

3.5.1 |: Bitwise OR Operator

The `|` operator gives a bitwise OR, exactly as performed by the OR machine instruction. Bitwise OR is the lowest-priority arithmetic operator supported by NASM.

3.5.2 ^: Bitwise XOR Operator

^ provides the bitwise XOR operation.

3.5.3 &: Bitwise AND Operator

& provides the bitwise AND operation.

3.5.4 << and >>: Bit Shift Operators

<< gives a bit-shift to the left, just as it does in C. So `5<<3` evaluates to 5 times 8, or 40. >> gives a bit-shift to the right; in NASM, such a shift is *always* unsigned, so that the bits shifted in from the left-hand end are filled with zero rather than a sign-extension of the previous highest bit.

3.5.5 + and -: Addition and Subtraction Operators

The + and - operators do perfectly ordinary addition and subtraction.

3.5.6 *, /, //, % and %%: Multiplication and Division

* is the multiplication operator. / and // are both division operators: / is unsigned division and // is signed division. Similarly, % and %% provide unsigned and signed modulo operators respectively.

NASM, like ANSI C, provides no guarantees about the sensible operation of the signed modulo operator.

Since the % character is used extensively by the macro preprocessor, you should ensure that both the signed and unsigned modulo operators are followed by white space wherever they appear.

3.5.7 Unary Operators

The highest-priority operators in NASM's expression grammar are those which only apply to one argument. These are +, -, ~, !, SEG, and the integer functions operators.

- negates its operand, + does nothing (it's provided for symmetry with -), ~ computes the one's complement of its operand, ! is the logical negation operator.

SEG provides the segment address of its operand (explained in more detail in section 3.6).

A set of additional operators with leading and trailing double underscores are used to implement the integer functions of the `i func` macro package, see section 6.4.

3.6 SEG and WRT

When writing large 16-bit programs, which must be split into multiple segments, it is often necessary to be able to refer to the segment part of the address of a symbol. NASM supports the SEG operator to perform this function.

The SEG operator returns the *preferred* segment base of a symbol, defined as the segment base relative to which the offset of the symbol makes sense. So the code

```
mov    ax,seg symbol
mov    es,ax
mov    bx,symbol
```

will load ES:BX with a valid pointer to the symbol `symbol`.

Things can be more complex than this: since 16-bit segments and groups may overlap, you might occasionally want to refer to some symbol using a different segment base from the preferred one. NASM lets you do this, by the use of the WRT (With Reference To) keyword. So you can do things like

```
mov    ax,weird_seg      ; weird_seg is a segment base
mov    es,ax
mov    bx,symbol wrt weird_seg
```

to load ES:BX with a different, but functionally equivalent, pointer to the symbol `symbol`.

NASM supports far (inter-segment) calls and jumps by means of the syntax `call segment:offset`, where `segment` and `offset` both represent immediate values. So to call a far procedure, you could code either of

```
call    (seg procedure):procedure
call    weird_seg:(procedure wrt weird_seg)
```

(The parentheses are included for clarity, to show the intended parsing of the above instructions. They are not necessary in practice.)

NASM supports the syntax `call far procedure` as a synonym for the first of the above usages. JMP works identically to CALL in these examples.

To declare a far pointer to a data item in a data segment, you must code

```
dw      symbol, seg symbol
```

NASM supports no convenient synonym for this, though you can always invent one using the macro processor.

3.7 STRICT: Inhibiting Optimization

When assembling with the optimizer set to level 2 or higher (see section 2.1.24), NASM will use size specifiers (BYTE, WORD, DWORD, QWORD, TWORD, OWORD, YWORD or ZWORD), but will give them the smallest possible size. The keyword STRICT can be used to inhibit optimization and force a particular operand to be emitted in the specified size. For example, with the optimizer on, and in BITS 16 mode,

```
push dword 33
```

is encoded in three bytes 66 6A 21, whereas

```
push strict dword 33
```

is encoded in six bytes, with a full dword immediate operand 66 68 21 00 00 00.

With the optimizer off, the same code (six bytes) is generated whether the STRICT keyword was used or not.

3.8 Critical Expressions

Although NASM has an optional multi-pass optimizer, there are some expressions which must be resolvable on the first pass. These are called *Critical Expressions*.

The first pass is used to determine the size of all the assembled code and data, so that the second pass, when generating all the code, knows all the symbol addresses the code refers to. So one thing NASM can't handle is code whose size depends on the value of a symbol declared after the code in question. For example,

```
times (label-$) db 0
label: db      'Where am I?'
```

The argument to TIMES in this case could equally legally evaluate to anything at all; NASM will reject this example because it cannot tell the size of the TIMES line when it first sees it. It will just as firmly reject the slightly paradoxical code

```
times (label-$(+1)) db 0
label: db      'NOW where am I?'
```

in which *any* value for the TIMES argument is by definition wrong!

NASM rejects these examples by means of a concept called a *critical expression*, which is defined to be an expression whose value is required to be computable in the first pass, and which must therefore depend only on symbols defined before it. The argument to the TIMES prefix is a critical expression.

3.9 Local Labels

NASM gives special treatment to symbols beginning with a period. A label beginning with a single period is treated as a *local* label, which means that it is associated with the previous non-local label. So, for example:

```
label1 ; some code

.loop
    ; some more code
    jne .loop
    ret

label2 ; some code

.loop
    ; some more code
    jne .loop
    ret
```

In the above code fragment, each JNE instruction jumps to the line immediately before it, because the two definitions of `.loop` are kept separate by virtue of each being associated with the previous non-local label.

This form of local label handling is borrowed from the old Amiga assembler DevPac; however, NASM goes one step further, in allowing access to local labels from other parts of the code. This is achieved by means of *defining* a local label in terms of the previous non-local label: the first definition of `.loop` above is really defining a symbol called `label1.loop`, and the second defines a symbol called `label2.loop`. So, if you really needed to, you could write

```
label3 ; some more code
        ; and some more

        jmp label1.loop
```

Sometimes it is useful – in a macro, for instance – to be able to define a label which can be referenced from anywhere but which doesn't interfere with the normal local-label mechanism. Such a label can't be non-local because it would interfere with subsequent definitions of, and references to, local labels; and it can't be local because the macro that defined it wouldn't know the label's full name. NASM therefore introduces a third type of label, which is probably only useful in macro definitions: if a label begins with the special prefix `..@`, then it does nothing to the local label mechanism. So you could code

```
label1: ; a non-local label
.local: ; this is really label1.local
..@foo: ; this is a special symbol
label2: ; another non-local label
.local: ; this is really label2.local

        jmp ..@foo ; this will jump three lines up
```

NASM has the capacity to define other special symbols beginning with a double period: for example, `..start` is used to specify the entry point in the obj output format (see section 8.4.6),

`..imagebase` is used to find out the offset from a base address of the current image in the `win64` output format (see section 8.6.1). So just keep in mind that symbols beginning with a double period are special.

Chapter 4: The NASM Preprocessor

NASM contains a powerful macro processor, which supports conditional assembly, multi-level file inclusion, two forms of macro (single-line and multi-line), and a 'context stack' mechanism for extra macro power. Preprocessor directives all begin with a % sign.

The preprocessor collapses all lines which end with a backslash (\) character into a single line. Thus:

```
%define THIS_VERY_LONG_MACRO_NAME_IS_DEFINED_TO \  
    THIS_VALUE
```

will work like a single-line macro without the backslash-newline sequence.

4.1 Single-Line Macros

4.1.1 The Normal Way: %define

Single-line macros are defined using the %define preprocessor directive. The definitions work in a similar way to C; so you can do things like

```
%define ctrl    0x1F &  
%define param(a,b) ((a)+(a)*(b))  
  
    mov     byte [param(2,ebx)], ctrl 'D'
```

which will expand to

```
    mov     byte [(2)+(2)*(ebx)], 0x1F & 'D'
```

When the expansion of a single-line macro contains tokens which invoke another macro, the expansion is performed at invocation time, not at definition time. Thus the code

```
%define a(x)    1+b(x)  
%define b(x)    2*x  
  
    mov     ax,a(8)
```

will evaluate in the expected way to `mov ax,1+2*8`, even though the macro `b` wasn't defined at the time of definition of `a`.

Note that single-line macro argument list cannot be preceded by whitespace. Otherwise it will be treated as an expansion. For example:

```
%define foo (a,b)           ; no arguments, (a,b) is the expansion  
%define bar(a,b)           ; two arguments, empty expansion
```

Macros defined with %define are case sensitive: after %define foo bar, only foo will expand to bar: Foo or F00 will not. By using %ifndef instead of %define (the 'i' stands for 'insensitive') you can define all the case variants of a macro at once, so that %ifndef foo bar would cause foo, Foo, F00, f00 and so on all to expand to bar.

There is a mechanism which detects when a macro call has occurred as a result of a previous expansion of the same macro, to guard against circular references and infinite loops. If this happens, the preprocessor will only expand the first occurrence of the macro. Hence, if you code

```
%define a(x)    1+a(x)  
  
    mov     ax,a(3)
```

the macro `a(3)` will expand once, becoming `1+a(3)`, and will then expand no further. This behaviour can be useful: see section 10.1 for an example of its use.

You can overload single-line macros: if you write

```
%define foo(x) 1+x
%define foo(x,y) 1+x*y
```

the preprocessor will be able to handle both types of macro call, by counting the parameters you pass; so `foo(3)` will become `1+3` whereas `foo(ebx,2)` will become `1+ebx*2`. However, if you define

```
%define foo bar
```

then no other definition of `foo` will be accepted: a macro with no parameters prohibits the definition of the same name as a macro *with* parameters, and vice versa.

This doesn't prevent single-line macros being *redefined*: you can perfectly well define a macro with

```
%define foo bar
```

and then re-define it later in the same source file with

```
%define foo baz
```

Then everywhere the macro `foo` is invoked, it will be expanded according to the most recent definition. This is particularly useful when defining single-line macros with `%assign` (see section 4.1.7).

The following additional features were added in NASM 2.15:

It is possible to define an empty string instead of an argument name if the argument is never used. For example:

```
%define ereg(foo,) e %+ foo
mov eax,ereg(dx,cx)
```

A single pair of parentheses is a subcase of a single, unused argument:

```
%define myreg() eax
mov edx,myreg()
```

This is similar to the behavior of the C preprocessor.

- If declared with an `=`, NASM will evaluate the argument as an expression after expansion.
- If an argument declared with an `&`, a macro parameter will be turned into a quoted string after expansion.
- If declared with a `+`, it is a greedy or variadic parameter; it includes any subsequent commas and parameters.
- If declared with an `!`, NASM will not strip whitespace and braces (useful in conjunction with `&`).

For example:

```
%define xyzzy(=expr,&val) expr, str
%define plugh(x) xyzzy(x,x)
db plugh(3+5), '\0' ; Expands to: db 8, "3+5", '\0'
```

You can pre-define single-line macros using the `-d` option on the NASM command line: see section 2.1.20.

4.1.2 Resolving `%define`: `%xdefine`

To have a reference to an embedded single-line macro resolved at the time that the embedding macro is *defined*, as opposed to when the embedding macro is *expanded*, you need a different mechanism to

the one offered by `%define`. The solution is to use `%xdefine`, or its case-insensitive counterpart `%ixdefine`.

Suppose you have the following code:

```
%define isTrue 1
%define isFalse isTrue
%define isTrue 0

val1: db isFalse

%define isTrue 1

val2: db isFalse
```

In this case, `val1` is equal to 0, and `val2` is equal to 1. This is because, when a single-line macro is defined using `%define`, it is expanded only when it is called. As `isFalse` expands to `isTrue`, the expansion will be the current value of `isTrue`. The first time it is called that is 0, and the second time it is 1.

If you wanted `isFalse` to expand to the value assigned to the embedded macro `isTrue` at the time that `isFalse` was defined, you need to change the above code to use `%xdefine`.

```
%xdefine isTrue 1
%xdefine isFalse isTrue
%xdefine isTrue 0

val1: db isFalse

%xdefine isTrue 1

val2: db isFalse
```

Now, each time that `isFalse` is called, it expands to 1, as that is what the embedded macro `isTrue` expanded to at the time that `isFalse` was defined.

`%xdefine` and `%ixdefine` supports argument expansion exactly the same way that `%define` and `%idefine` does.

4.1.3 Macro Indirection: `%[...]`

The `%[...]` construct can be used to expand macros in contexts where macro expansion would otherwise not occur, including in the names other macros. For example, if you have a set of macros named `Foo16`, `Foo32` and `Foo64`, you could write:

```
mov ax, Foo%[__?BITS?__] ; The Foo value
```

to use the builtin macro `__?BITS?__` (see section 5.3) to automatically select between them. Similarly, the two statements:

```
%xdefine Bar Quux ; Expands due to %xdefine
%define Bar %[Quux] ; Expands due to %[...]
```

have, in fact, exactly the same effect.

`%[...]` concatenates to adjacent tokens in the same way that multi-line macro parameters do, see section 4.3.9 for details.

4.1.4 Concatenating Single Line Macro Tokens: %+

Individual tokens in single line macros can be concatenated, to produce longer tokens for later processing. This can be useful if there are several similar macros that perform similar functions.

Please note that a space is required after +, in order to disambiguate it from the syntax %+1 used in multiline macros.

As an example, consider the following:

```
%define BDASTART 400h                ; Start of BIOS data area
struc  tBIOSDA                        ; its structure
    .COM1addr      RESW  1
    .COM2addr      RESW  1
    ; ..and so on
endstruc
```

Now, if we need to access the elements of tBIOSDA in different places, we can end up with:

```
    mov    ax,BDASTART + tBIOSDA.COM1addr
    mov    bx,BDASTART + tBIOSDA.COM2addr
```

This will become pretty ugly (and tedious) if used in many places, and can be reduced in size significantly by using the following macro:

```
; Macro to access BIOS variables by their names (from tBDA):
```

```
%define BDA(x)  BDASTART + tBIOSDA. %+ x
```

Now the above code can be written as:

```
    mov    ax,BDA(COM1addr)
    mov    bx,BDA(COM2addr)
```

Using this feature, we can simplify references to a lot of macros (and, in turn, reduce typing errors).

4.1.5 The Macro Name Itself: %? and %??

The special symbols %? and %?? can be used to reference the macro name itself inside a macro expansion, this is supported for both single- and multi-line macros. %? refers to the macro name as *invoked*, whereas %?? refers to the macro name as *declared*. The two are always the same for case-sensitive macros, but for case-insensitive macros, they can differ.

For example:

```
%idefine Foo mov %?,%??
```

```
    foo
    FOO
```

will expand to:

```
    mov foo,foo
    mov FOO,foo
```

The sequence:

```
%idefine keyword $%?
```

can be used to make a keyword "disappear", for example in case a new instruction has been used as a label in older code. For example:

```
%idefine pause $%?                ; Hide the PAUSE instruction
```


4.1.6 undefining Single-Line Macros: %undef

Single-line macros can be removed with the %undef directive. For example, the following sequence:

```
%define foo bar
%undef foo
```

```
mov eax, foo
```

will expand to the instruction `mov eax, foo`, since after %undef the macro `foo` is no longer defined.

Macros that would otherwise be pre-defined can be undefined on the command-line using the '-u' option on the NASM command line: see section 2.1.21.

4.1.7 Preprocessor Variables: %assign

An alternative way to define single-line macros is by means of the %assign command (and its case-insensitive counterpart %iassign, which differs from %assign in exactly the same way that %ifdef differs from %define).

%assign is used to define single-line macros which take no parameters and have a numeric value. This value can be specified in the form of an expression, and it will be evaluated once, when the %assign directive is processed.

Like %define, macros defined using %assign can be re-defined later, so you can do things like

```
%assign i i+1
```

to increment the numeric value of a macro.

%assign is useful for controlling the termination of %rep preprocessor loops: see section 4.5 for an example of this. Another use for %assign is given in section 9.4 and section 10.1.

The expression passed to %assign is a critical expression (see section 3.8), and must also evaluate to a pure number (rather than a relocatable reference such as a code or data address, or anything involving a register).

4.1.8 Defining Strings: %defstr

%defstr, and its case-insensitive counterpart %ifdefstr, define or redefine a single-line macro without parameters but converts the entire right-hand side, after macro expansion, to a quoted string before definition.

For example:

```
%defstr test TEST
```

is equivalent to

```
%define test 'TEST'
```

This can be used, for example, with the %! construct (see section 4.11.2):

```
%defstr PATH %!PATH ; The operating system PATH variable
```

4.1.9 Defining Tokens: %deftok

%deftok, and its case-insensitive counterpart %ifdeftok, define or redefine a single-line macro without parameters but converts the second parameter, after string conversion, to a sequence of tokens.

For example:

```
%deftok test 'TEST'
```

is equivalent to

```
%define test TEST
```

4.1.10 Defining Aliases: `%defalias`

`%defalias`, and its case-insensitive counterpart `%idefalias`, define an alias to a macro, i.e. equivalent of a symbolic link.

When used with various macro defining and undefining directives, it affects the aliased macro. This functionality is intended for being able to rename macros while retaining the legacy names.

When an alias is defined, but the aliased macro is then undefined, the aliases can legitimately point to nonexistent macros.

The alias can be undefined using the `%undefalias` directive. *All* aliases can be undefined using the `%clear defalias` directive. This includes backwards compatibility aliases defined by NASM itself.

To disable aliases without undefining them, use the `%aliases off` directive.

To check whether an alias is defined, use `%ifdefalias`.

This

4.1.11 Conditional Comma Operator: `%,`

As of version 2.15, NASM has conditional comma operator `%,` that expands to a comma unless followed by a null expansion, which allows suppressing the comma before an empty argument. For example, all the expressions below are valid:

```
%define greedy(a,b,c+) a + 66 %, b * 3 %, c
```

```
db greedy(1,2)
db greedy(1,2,3)
db greedy(1,2,3,4)
db greedy(1,2,3,4,5)
```

4.2 String Manipulation in Macros

It's often useful to be able to handle strings in macros. NASM supports a few simple string handling macro operators from which more complex operations can be constructed.

All the string operators define or redefine a value (either a string or a numeric value) to a single-line macro. When producing a string value, it may change the style of quoting of the input string or strings, and possibly use `\`-escapes inside `'`-quoted strings.

4.2.1 Concatenating Strings: `%strcat`

The `%strcat` operator concatenates quoted strings and assign them to a single-line macro.

For example:

```
%strcat alpha "Alpha: ", '12" screen'
```

... would assign the value `'Alpha: 12" screen'` to `alpha`. Similarly:

```
%strcat beta '"foo"\', "'bar''
```

... would assign the value `'"foo"\\'bar''` to `beta`.

The use of commas to separate strings is permitted but optional.

4.2.2 String Length: `%strlen`

The `%strlen` operator assigns the length of a string to a macro. For example:

```
%strlen charcnt 'my string'
```

In this example, `charcnt` would receive the value 9, just as if an `%assign` had been used. In this example, `'my string'` was a literal string but it could also have been a single-line macro that expands to a string, as in the following example:

```
%define sometext 'my string'  
%strlen charcnt sometext
```

As in the first case, this would result in `charcnt` being assigned the value of 9.

4.2.3 Extracting Substrings: `%substr`

Individual letters or substrings in strings can be extracted using the `%substr` operator. An example of its use is probably more useful than the description:

```
%substr mychar 'xyzw' 1      ; equivalent to %define mychar 'x'  
%substr mychar 'xyzw' 2      ; equivalent to %define mychar 'y'  
%substr mychar 'xyzw' 3      ; equivalent to %define mychar 'z'  
%substr mychar 'xyzw' 2,2    ; equivalent to %define mychar 'yz'  
%substr mychar 'xyzw' 2,-1   ; equivalent to %define mychar 'yzw'  
%substr mychar 'xyzw' 2,-2   ; equivalent to %define mychar 'yz'
```

As with `%strlen` (see section 4.2.2), the first parameter is the single-line macro to be created and the second is the string. The third parameter specifies the first character to be selected, and the optional fourth parameter preceded by comma) is the length. Note that the first index is 1, not 0 and the last index is equal to the value that `%strlen` would assign given the same string. Index values out of range result in an empty string. A negative length means "until N-1 characters before the end of string", i.e. -1 means until end of string, -2 until one character before, etc.

4.3 Multi-Line Macros: `%macro`

Multi-line macros are much more like the type of macro seen in MASM and TASM: a multi-line macro definition in NASM looks something like this.

```
%macro prologue 1  
  
    push    ebp  
    mov     ebp,esp  
    sub     esp,%1  
  
%endmacro
```

This defines a C-like function `prologue` as a macro: so you would invoke the macro with a call such as:

```
myfunc: prologue 12
```

which would expand to the three lines of code

```
myfunc: push    ebp  
        mov     ebp,esp  
        sub     esp,12
```

The number 1 after the macro name in the `%macro` line defines the number of parameters the macro `prologue` expects to receive. The use of `%1` inside the macro definition refers to the first parameter to the macro call. With a macro taking more than one parameter, subsequent parameters would be referred to as `%2`, `%3` and so on.

Multi-line macros, like single-line macros, are case-sensitive, unless you define them using the alternative directive `%imacro`.

If you need to pass a comma as *part* of a parameter to a multi-line macro, you can do that by enclosing the entire parameter in braces. So you could code things like:

```
%macro silly 2
    %2: db    %1

%endmacro

    silly 'a', letter_a           ; letter_a: db 'a'
    silly 'ab', string_ab        ; string_ab: db 'ab'
    silly {13,10}, crlf          ; crlf:      db 13,10
```

The behavior with regards to empty arguments at the end of multi-line macros before NASM 2.15 was often very strange. For backwards compatibility, NASM attempts to recognize cases where the legacy behavior would give unexpected results, and issues a warning, but largely tries to match the legacy behavior. This can be disabled with the `%pragma` (see section 4.10.1):

```
%pragma preproc sane_empty_expansion
```

4.3.1 Overloading Multi-Line Macros

As with single-line macros, multi-line macros can be overloaded by defining the same macro name several times with different numbers of parameters. This time, no exception is made for macros with no parameters at all. So you could define

```
%macro prologue 0
    push    ebp
    mov     ebp,esp

%endmacro
```

to define an alternative form of the function prologue which allocates no local stack space.

Sometimes, however, you might want to ‘overload’ a machine instruction; for example, you might want to define

```
%macro push 2
    push    %1
    push    %2

%endmacro
```

so that you could code

```
    push    ebx           ; this line is not a macro call
    push    eax,ecx       ; but this one is
```

Ordinarily, NASM will give a warning for the first of the above two lines, since `push` is now defined to be a macro, and is being invoked with a number of parameters for which no definition has been given. The correct code will still be generated, but the assembler will give a warning. This warning can be disabled by the use of the `-w-macro-params` command-line option (see section 2.1.26).

4.3.2 Macro-Local Labels

NASM allows you to define labels within a multi-line macro definition in such a way as to make them local to the macro call: so calling the same macro multiple times will use a different label each time.

You do this by prefixing %% to the label name. So you can invent an instruction which executes a RET if the Z flag is set by doing this:

```
%macro retz 0

    jnz    %%skip
    ret
%%skip:

%endmacro
```

You can call this macro as many times as you want, and every time you call it NASM will make up a different 'real' name to substitute for the label %%skip. The names NASM invents are of the form .@2345.skip, where the number 2345 changes with every macro call. The .@ prefix prevents macro-local labels from interfering with the local label mechanism, as described in section 3.9. You should avoid defining your own labels in this form (the .@ prefix, then a number, then another period) in case they interfere with macro-local labels.

4.3.3 Greedy Macro Parameters

Occasionally it is useful to define a macro which lumps its entire command line into one parameter definition, possibly after extracting one or two smaller parameters from the front. An example might be a macro to write a text string to a file in MS-DOS, where you might want to be able to write

```
writefile [filehandle], "hello, world", 13, 10
```

NASM allows you to define the last parameter of a macro to be *greedy*, meaning that if you invoke the macro with more parameters than it expects, all the spare parameters get lumped into the last defined one along with the separating commas. So if you code:

```
%macro writefile 2+

    jmp    %%endstr
%%str:    db    %2
%%endstr:
    mov    dx, %%str
    mov    cx, %%endstr-%%str
    mov    bx, %1
    mov    ah, 0x40
    int    0x21

%endmacro
```

then the example call to `writefile` above will work as expected: the text before the first comma, `[filehandle]`, is used as the first macro parameter and expanded when `%1` is referred to, and all the subsequent text is lumped into `%2` and placed after the `db`.

The greedy nature of the macro is indicated to NASM by the use of the + sign after the parameter count on the `%macro` line.

If you define a greedy macro, you are effectively telling NASM how it should expand the macro given *any* number of parameters from the actual number specified up to infinity; in this case, for example, NASM now knows what to do when it sees a call to `writefile` with 2, 3, 4 or more parameters. NASM will take this into account when overloading macros, and will not allow you to define another form of `writefile` taking 4 parameters (for example).

Of course, the above macro could have been implemented as a non-greedy macro, in which case the call to it would have had to look like

```
writefile [filehandle], {"hello, world",13,10}
```

NASM provides both mechanisms for putting commas in macro parameters, and you choose which one you prefer for each macro definition.

See section 7.3.1 for a better way to write the above macro.

4.3.4 Macro Parameters Range

NASM allows you to expand parameters via special construction `%{x:y}` where `x` is the first parameter index and `y` is the last. Any index can be either negative or positive but must never be zero.

For example

```
%macro mpar 1-*
    db %{3:5}
%endmacro
```

```
mpar 1,2,3,4,5,6
```

expands to 3,4,5 range.

Even more, the parameters can be reversed so that

```
%macro mpar 1-*
    db %{5:3}
%endmacro
```

```
mpar 1,2,3,4,5,6
```

expands to 5,4,3 range.

But even this is not the last. The parameters can be addressed via negative indices so NASM will count them reversed. The ones who know Python may see the analogue here.

```
%macro mpar 1-*
    db %{-1:-3}
%endmacro
```

```
mpar 1,2,3,4,5,6
```

expands to 6,5,4 range.

Note that NASM uses comma to separate parameters being expanded.

By the way, here is a trick – you might use the index `%{-1:-1}` which gives you the last argument passed to a macro.

4.3.5 Default Macro Parameters

NASM also allows you to define a multi-line macro with a *range* of allowable parameter counts. If you do this, you can specify defaults for omitted parameters. So, for example:

```
%macro die 0-1 "Painful program death has occurred."

    writefile 2,%1
    mov     ax,0x4c01
    int     0x21

%endmacro
```

This macro (which makes use of the `writeln` macro defined in section 4.3.3) can be called with an explicit error message, which it will display on the error output stream before exiting, or it can be called with no parameters, in which case it will use the default error message supplied in the macro definition.

In general, you supply a minimum and maximum number of parameters for a macro of this type; the minimum number of parameters are then required in the macro call, and then you provide defaults for the optional ones. So if a macro definition began with the line

```
%macro foobar 1-3 eax,[ebx+2]
```

then it could be called with between one and three parameters, and `%1` would always be taken from the macro call. `%2`, if not specified by the macro call, would default to `eax`, and `%3` if not specified would default to `[ebx+2]`.

You can provide extra information to a macro by providing too many default parameters:

```
%macro quux 1 something
```

This will trigger a warning by default; see section 2.1.26 for more information. When `quux` is invoked, it receives not one but two parameters. `something` can be referred to as `%2`. The difference between passing `something` this way and writing `something` in the macro body is that with this way `something` is evaluated when the macro is defined, not when it is expanded.

You may omit parameter defaults from the macro definition, in which case the parameter default is taken to be blank. This can be useful for macros which can take a variable number of parameters, since the `%0` token (see section 4.3.6) allows you to determine how many parameters were really passed to the macro call.

This defaulting mechanism can be combined with the greedy-parameter mechanism; so the `die` macro above could be made more powerful, and more useful, by changing the first line of the definition to

```
%macro die 0-1+ "Painful program death has occurred.",13,10
```

The maximum parameter count can be infinite, denoted by `*`. In this case, of course, it is impossible to provide a *full* set of default parameters. Examples of this usage are shown in section 4.3.8.

4.3.6 `%0`: Macro Parameter Counter

The parameter reference `%0` will return a numeric constant giving the number of parameters received, that is, if `%0` is `n` then `%n` is the last parameter. `%0` is mostly useful for macros that can take a variable number of parameters. It can be used as an argument to `%rep` (see section 4.5) in order to iterate through all the parameters of a macro. Examples are given in section 4.3.8.

4.3.7 `%00`: Label Preceding Macro

`%00` will return the label preceding the macro invocation, if any. The label must be on the same line as the macro invocation, may be a local label (see section 3.9), and need not end in a colon.

4.3.8 `%rotate`: Rotating Macro Parameters

Unix shell programmers will be familiar with the `shift` shell command, which allows the arguments passed to a shell script (referenced as `$1`, `$2` and so on) to be moved left by one place, so that the argument previously referenced as `$2` becomes available as `$1`, and the argument previously referenced as `$1` is no longer available at all.

NASM provides a similar mechanism, in the form of `%rotate`. As its name suggests, it differs from the Unix `shift` in that no parameters are lost: parameters rotated off the left end of the argument list reappear on the right, and vice versa.

`%rotate` is invoked with a single numeric argument (which may be an expression). The macro parameters are rotated to the left by that many places. If the argument to `%rotate` is negative, the macro parameters are rotated to the right.

So a pair of macros to save and restore a set of registers might work as follows:

```
%macro  multipush 1-*
```

```
    %rep  %0
        push    %1
    %rotate 1
%endrep
```

```
%endmacro
```

This macro invokes the PUSH instruction on each of its arguments in turn, from left to right. It begins by pushing its first argument, `%1`, then invokes `%rotate` to move all the arguments one place to the left, so that the original second argument is now available as `%1`. Repeating this procedure as many times as there were arguments (achieved by supplying `%0` as the argument to `%rep`) causes each argument in turn to be pushed.

Note also the use of `*` as the maximum parameter count, indicating that there is no upper limit on the number of parameters you may supply to the `multipush` macro.

It would be convenient, when using this macro, to have a POP equivalent, which *didn't* require the arguments to be given in reverse order. Ideally, you would write the `multipush` macro call, then cut-and-paste the line to where the pop needed to be done, and change the name of the called macro to `multirop`, and the macro would take care of popping the registers in the opposite order from the one in which they were pushed.

This can be done by the following definition:

```
%macro  multirop 1-*
```

```
    %rep %0
    %rotate -1
        pop    %1
%endrep
```

```
%endmacro
```

This macro begins by rotating its arguments one place to the *right*, so that the original *last* argument appears as `%1`. This is then popped, and the arguments are rotated right again, so the second-to-last argument becomes `%1`. Thus the arguments are iterated through in reverse order.

4.3.9 Concatenating Macro Parameters

NASM can concatenate macro parameters and macro indirection constructs on to other text surrounding them. This allows you to declare a family of symbols, for example, in a macro definition. If, for example, you wanted to generate a table of key codes along with offsets into the table, you could code something like

```
%macro  keytab_entry 2
```

```
    keypos%1    equ    $-keytab
                db     %2
```

```
%endmacro
```



```
keytab:
    keytab_entry F1,128+1
    keytab_entry F2,128+2
    keytab_entry Return,13
```

which would expand to

```
keytab:
keyposF1      equ    $-keytab
              db     128+1
keyposF2      equ    $-keytab
              db     128+2
keyposReturn  equ    $-keytab
              db     13
```

You can just as easily concatenate text on to the other end of a macro parameter, by writing `%1foo`.

If you need to append a *digit* to a macro parameter, for example defining labels `foo1` and `foo2` when passed the parameter `foo`, you can't code `%11` because that would be taken as the eleventh macro parameter. Instead, you must code `%{1}1`, which will separate the first 1 (giving the number of the macro parameter) from the second (literal text to be concatenated to the parameter).

This concatenation can also be applied to other preprocessor in-line objects, such as macro-local labels (section 4.3.2) and context-local labels (section 4.7.2). In all cases, ambiguities in syntax can be resolved by enclosing everything after the `%` sign and before the literal text in braces: so `%{%foo}bar` concatenates the text `bar` to the end of the real name of the macro-local label `%%foo`. (This is unnecessary, since the form NASM uses for the real names of macro-local labels means that the two usages `%{%foo}bar` and `%%foobar` would both expand to the same thing anyway; nevertheless, the capability is there.)

The single-line macro indirection construct, `%[...]` (section 4.1.3), behaves the same way as macro parameters for the purpose of concatenation.

See also the `%+` operator, section 4.1.4.

4.3.10 Condition Codes as Macro Parameters

NASM can give special treatment to a macro parameter which contains a condition code. For a start, you can refer to the macro parameter `%1` by means of the alternative syntax `%+1`, which informs NASM that this macro parameter is supposed to contain a condition code, and will cause the preprocessor to report an error message if the macro is called with a parameter which is *not* a valid condition code.

Far more usefully, though, you can refer to the macro parameter by means of `%-1`, which NASM will expand as the *inverse* condition code. So the `retz` macro defined in section 4.3.2 can be replaced by a general conditional-return macro like this:

```
%macro    retc 1
    j%-1    %%skip
    ret
    %%skip:
%endmacro
```

This macro can now be invoked using calls like `retc ne`, which will cause the conditional-jump instruction in the macro expansion to come out as `JNE`, or `retc po` which will make the jump a `JPE`.

The `%+1` macro-parameter reference is quite happy to interpret the arguments `CXZ` and `ECXZ` as valid condition codes; however, `%-1` will report an error if passed either of these, because no inverse condition code exists.

4.3.11 Disabling Listing Expansion

When NASM is generating a listing file from your program, it will generally expand multi-line macros by means of writing the macro call and then listing each line of the expansion. This allows you to see which instructions in the macro expansion are generating what code; however, for some macros this clutters the listing up unnecessarily.

NASM therefore provides the `.nolist` qualifier, which you can include in a macro definition to inhibit the expansion of the macro in the listing file. The `.nolist` qualifier comes directly after the number of parameters, like this:

```
%macro foo 1.nolist
```

Or like this:

```
%macro bar 1-5+.nolist a,b,c,d,e,f,g,h
```

4.3.12 undefining Multi-Line Macros: `%unmacro`

Multi-line macros can be removed with the `%unmacro` directive. Unlike the `%undef` directive, however, `%unmacro` takes an argument specification, and will only remove exact matches with that argument specification.

For example:

```
%macro foo 1-3
    ; Do something
%endmacro
%unmacro foo 1-3
```

removes the previously defined macro `foo`, but

```
%macro bar 1-3
    ; Do something
%endmacro
%unmacro bar 1
```

does *not* remove the macro `bar`, since the argument specification does not match exactly.

4.4 Conditional Assembly

Similarly to the C preprocessor, NASM allows sections of a source file to be assembled only if certain conditions are met. The general syntax of this feature looks like this:

```
%if<condition>
    ; some code which only appears if <condition> is met
%elif<condition2>
    ; only appears if <condition> is not met but <condition2> is
%else
    ; this appears if neither <condition> nor <condition2> was met
%endif
```

The inverse forms `%ifn` and `%elifn` are also supported.

The `%else` clause is optional, as is the `%elif` clause. You can have more than one `%elif` clause as well.

There are a number of variants of the `%if` directive. Each has its corresponding `%elif`, `%ifn`, and `%elifn` directives; for example, the equivalents to the `%ifdef` directive are `%elifdef`, `%ifndef`, and `%elifndef`.

4.4.1 `%ifdef`: Testing Single-Line Macro Existence

Beginning a conditional-assembly block with the line `%ifdef MACRO` will assemble the subsequent code if, and only if, a single-line macro called `MACRO` is defined. If not, then the `%elif` and `%else` blocks (if any) will be processed instead.

For example, when debugging a program, you might want to write code such as

```
        ; perform some function
#ifdef DEBUG
        writefile 2,"Function performed successfully",13,10
#endif
        ; go and do something else
```

Then you could use the command-line option `-dDEBUG` to create a version of the program which produced debugging messages, and remove the option to generate the final release version of the program.

You can test for a macro *not* being defined by using `%ifndef` instead of `%ifdef`. You can also test for macro definitions in `%elif` blocks by using `%elifdef` and `%elifndef`.

4.4.2 `%ifmacro`: Testing Multi-Line Macro Existence

The `%ifmacro` directive operates in the same way as the `%ifdef` directive, except that it checks for the existence of a multi-line macro.

For example, you may be working with a large project and not have control over the macros in a library. You may want to create a macro with one name if it doesn't already exist, and another name if one with that name does exist.

The `%ifmacro` is considered true if defining a macro with the given name and number of arguments would cause a definitions conflict. For example:

```
%ifmacro MyMacro 1-3

        %error "MyMacro 1-3" causes a conflict with an existing macro.

%else

        %macro MyMacro 1-3

                ; insert code to define the macro

        %endmacro

#endif
```

This will create the macro "MyMacro 1-3" if no macro already exists which would conflict with it, and emits a warning if there would be a definition conflict.

You can test for the macro not existing by using the `%ifnmacro` instead of `%ifmacro`. Additional tests can be performed in `%elif` blocks by using `%elifmacro` and `%elifnmacro`.

4.4.3 `%ifctx`: Testing the Context Stack

The conditional-assembly construct `%ifctx` will cause the subsequent code to be assembled if and only if the top context on the preprocessor's context stack has the same name as one of the arguments. As with `%ifdef`, the inverse and `%elif` forms `%ifnctx`, `%elifctx` and `%elifnctx` are also supported.

For more details of the context stack, see section 4.7. For a sample use of `%i f c t x`, see section 4.7.6.

4.4.4 `%i f`: Testing Arbitrary Numeric Expressions

The conditional-assembly construct `%i f expr` will cause the subsequent code to be assembled if and only if the value of the numeric expression `expr` is non-zero. An example of the use of this feature is in deciding when to break out of a `%r e p` preprocessor loop: see section 4.5 for a detailed example.

The expression given to `%i f`, and its counterpart `%e l i f`, is a critical expression (see section 3.8).

`%i f` extends the normal NASM expression syntax, by providing a set of relational operators which are not normally available in expressions. The operators `=`, `<`, `>`, `<=`, `>=` and `<>` test equality, less-than, greater-than, less-or-equal, greater-or-equal and not-equal respectively. The C-like forms `==` and `!=` are supported as alternative forms of `=` and `<>`. In addition, low-priority logical operators `&&`, `^^` and `||` are provided, supplying logical AND, logical XOR and logical OR. These work like the C logical operators (although C has no logical XOR), in that they always return either 0 or 1, and treat any non-zero input as 1 (so that `^^`, for example, returns 1 if exactly one of its inputs is zero, and 0 otherwise). The relational operators also return 1 for true and 0 for false.

Like other `%i f` constructs, `%i f` has a counterpart `%e l i f`, and negative forms `%i f n` and `%e l i f n`.

4.4.5 `%i f i d n` and `%i f i d n i`: Testing Exact Text Identity

The construct `%i f i d n text1, text2` will cause the subsequent code to be assembled if and only if `text1` and `text2`, after expanding single-line macros, are identical pieces of text. Differences in white space are not counted.

`%i f i d n i` is similar to `%i f i d n`, but is case-insensitive.

For example, the following macro pushes a register or number on the stack, and allows you to treat IP as a real register:

```
%macro pushparam 1
    %i f i d n i %1, ip
        call    %%label
    %%label:
    %else
        push    %1
    %e n d i f
%e n d m a c r o
```

Like other `%i f` constructs, `%i f i d n` has a counterpart `%e l i f i d n`, and negative forms `%i f n i d n` and `%e l i f n i d n`. Similarly, `%i f i d n i` has counterparts `%e l i f i d n i`, `%i f n i d n i` and `%e l i f n i d n i`.

4.4.6 `%i f i d`, `%i f n u m`, `%i f s t r`: Testing Token Types

Some macros will want to perform different tasks depending on whether they are passed a number, a string, or an identifier. For example, a string output macro might want to be able to cope with being passed either a string constant or a pointer to an existing string.

The conditional assembly construct `%i f i d`, taking one parameter (which may be blank), assembles the subsequent code if and only if the first token in the parameter exists and is an identifier. `%i f n u m` works similarly, but tests for the token being a numeric constant; `%i f s t r` tests for it being a string.

For example, the `w r i t e f i l e` macro defined in section 4.3.3 can be extended to take advantage of `%i f s t r` in the following fashion:

```
%macro writefile 2-3+
```

```

%ifstr %2
    jmp    %%endstr
%if %0 = 3
    %%str: db    %2,%3
%else
    %%str: db    %2
%endif
    %%endstr: mov    dx,%%str
    mov    cx,%%endstr-%%str
%else
    mov    dx,%2
    mov    cx,%3
%endif
    mov    bx,%1
    mov    ah,0x40
    int    0x21

```

`%endmacro`

Then the `writefile` macro can cope with being called in either of the following two ways:

```

writefile [file], strpointer, length
writefile [file], "hello", 13, 10

```

In the first, `strpointer` is used as the address of an already-declared string, and `length` is used as its length; in the second, a string is given to the macro, which therefore declares it itself and works out the address and length for itself.

Note the use of `%if` inside the `%ifstr`: this is to detect whether the macro was passed two arguments (so the string would be a single string constant, and `db %2` would be adequate) or more (in which case, all but the first two would be lumped together into `%3`, and `db %2,%3` would be required).

The usual `%elif...`, `%ifn...`, and `%elifn...` versions exist for each of `%ifid`, `%ifnum` and `%ifstr`.

4.4.7 `%iftoken`: Test for a Single Token

Some macros will want to do different things depending on if it is passed a single token (e.g. paste it to something else using `%+`) versus a multi-token sequence.

The conditional assembly construct `%iftoken` assembles the subsequent code if and only if the expanded parameters consist of exactly one token, possibly surrounded by whitespace.

For example:

```
%iftoken 1
```

will assemble the subsequent code, but

```
%iftoken -1
```

will not, since `-1` contains two tokens: the unary minus operator `-`, and the number `1`.

The usual `%eliftoken`, `%ifntoken`, and `%elifntoken` variants are also provided.

4.4.8 `%ifempty`: Test for Empty Expansion

The conditional assembly construct `%ifempty` assembles the subsequent code if and only if the expanded parameters do not contain any tokens at all, whitespace excepted.

The usual `%elifempty`, `%ifnempty`, and `%elifnempty` variants are also provided.

4.4.9 %ifenv: Test If Environment Variable Exists

The conditional assembly construct %ifenv assembles the subsequent code if and only if the environment variable referenced by the %!*variable* directive exists.

The usual %elifenv, %ifnenv, and %elifnenv variants are also provided.

Just as for %!*variable* the argument should be written as a string if it contains characters that would not be legal in an identifier. See section 4.11.2.

4.5 Preprocessor Loops: %rep

NASM's TIMES prefix, though useful, cannot be used to invoke a multi-line macro multiple times, because it is processed by NASM after macros have already been expanded. Therefore NASM provides another form of loop, this time at the preprocessor level: %rep.

The directives %rep and %endrep (%rep takes a numeric argument, which can be an expression; %endrep takes no arguments) can be used to enclose a chunk of code, which is then replicated as many times as specified by the preprocessor:

```
%assign i 0
%rep 64
    inc    word [table+2*i]
%assign i i+1
%endrep
```

This will generate a sequence of 64 INC instructions, incrementing every word of memory from [table] to [table+126].

For more complex termination conditions, or to break out of a repeat loop part way along, you can use the %exitrep directive to terminate the loop, like this:

```
fibonacci:
%assign i 0
%assign j 1
%rep 100
%if j > 65535
    %exitrep
%endif
    dw j
%assign k j+i
%assign i j
%assign j k
%endrep
```

```
fib_number equ ($-fibonacci)/2
```

This produces a list of all the Fibonacci numbers that will fit in 16 bits. Note that a maximum repeat count must still be given to %rep. This is to prevent the possibility of NASM getting into an infinite loop in the preprocessor, which (on multitasking or multi-user systems) would typically cause all the system memory to be gradually used up and other applications to start crashing.

Note a maximum repeat count is limited by 62 bit number, though it is hardly possible that you ever need anything bigger.

4.6 Source Files and Dependencies

These commands allow you to split your sources into multiple files.

4.6.1 %include: Including Other Files

Using, once again, a very similar syntax to the C preprocessor, NASM's preprocessor lets you include other source files into your code. This is done by the use of the %include directive:

```
%include "macros.mac"
```

will include the contents of the file macros.mac into the source file containing the %include directive.

Include files are searched for in the current directory (the directory you're in when you run NASM, as opposed to the location of the NASM executable or the location of the source file), plus any directories specified on the NASM command line using the -i option.

The standard C idiom for preventing a file being included more than once is just as applicable in NASM: if the file macros.mac has the form

```
%ifndef MACROS_MAC
    %define MACROS_MAC
        ; now define some macros
%endif
```

then including the file more than once will not cause errors, because the second time the file is included nothing will happen because the macro MACROS_MAC will already be defined.

You can force a file to be included even if there is no %include directive that explicitly includes it, by using the -p option on the NASM command line (see section 2.1.19).

4.6.2 %pathsearch: Search the Include Path

The %pathsearch directive takes a single-line macro name and a filename, and declare or redefines the specified single-line macro to be the include-path-resolved version of the filename, if the file exists (otherwise, it is passed unchanged.)

For example,

```
%pathsearch MyFoo "foo.bin"
```

... with -Ibins/ in the include path may end up defining the macro MyFoo to be "bins/foo.bin".

4.6.3 %depend: Add Dependent Files

The %depend directive takes a filename and adds it to the list of files to be emitted as dependency generation when the -M options and its relatives (see section 2.1.5) are used. It produces no output.

This is generally used in conjunction with %pathsearch. For example, a simplified version of the standard macro wrapper for the INCBIN directive looks like:

```
%imacro incbin 1-2+ 0
%pathsearch dep %1
%depend dep
    incbin dep,%2
%endmacro
```

This first resolves the location of the file into the macro dep, then adds it to the dependency lists, and finally issues the assembler-level INCBIN directive.

4.6.4 %use: Include Standard Macro Package

The %use directive is similar to %include, but rather than including the contents of a file, it includes a named standard macro package. The standard macro packages are part of NASM, and are described in chapter 6.

Unlike the `%include` directive, package names for the `%use` directive do not require quotes, but quotes are permitted. In NASM 2.04 and 2.05 the unquoted form would be macro-expanded; this is no longer true. Thus, the following lines are equivalent:

```
%use altreg
%use 'altreg'
```

Standard macro packages are protected from multiple inclusion. When a standard macro package is used, a testable single-line macro of the form `__?USE_package?__` is also defined, see section 5.7.

4.7 The Context Stack

Having labels that are local to a macro definition is sometimes not quite powerful enough: sometimes you want to be able to share labels between several macro calls. An example might be a REPEAT ... UNTIL loop, in which the expansion of the REPEAT macro would need to be able to refer to a label which the UNTIL macro had defined. However, for such a macro you would also want to be able to nest these loops.

NASM provides this level of power by means of a *context stack*. The preprocessor maintains a stack of *contexts*, each of which is characterized by a name. You add a new context to the stack using the `%push` directive, and remove one using `%pop`. You can define labels that are local to a particular context on the stack.

4.7.1 `%push` and `%pop`: Creating and Removing Contexts

The `%push` directive is used to create a new context and place it on the top of the context stack. `%push` takes an optional argument, which is the name of the context. For example:

```
%push    foobar
```

This pushes a new context called `foobar` on the stack. You can have several contexts on the stack with the same name: they can still be distinguished. If no name is given, the context is unnamed (this is normally used when both the `%push` and the `%pop` are inside a single macro definition.)

The directive `%pop`, taking one optional argument, removes the top context from the context stack and destroys it, along with any labels associated with it. If an argument is given, it must match the name of the current context, otherwise it will issue an error.

4.7.2 Context-Local Labels

Just as the usage `%%foo` defines a label which is local to the particular macro call in which it is used, the usage `%%$foo` is used to define a label which is local to the context on the top of the context stack. So the REPEAT and UNTIL example given above could be implemented by means of:

```
%macro repeat 0
    %push    repeat
    %%$begin:

%endmacro

%macro until 1
    j%-1    %%$begin
    %pop

%endmacro
```

and invoked by means of, for example,


```

mov     cx,string
repeat
add     cx,3
scasb
until  e

```

which would scan every fourth byte of a string in search of the byte in AL.

If you need to define, or access, labels local to the context *below* the top one on the stack, you can use `%%$foo`, or `%%$%$foo` for the context below that, and so on.

4.7.3 Context-Local Single-Line Macros

NASM also allows you to define single-line macros which are local to a particular context, in just the same way:

```
%define %%$localmac 3
```

will define the single-line macro `%%$localmac` to be local to the top context on the stack. Of course, after a subsequent `%push`, it can then still be accessed by the name `%%$%$localmac`.

4.7.4 Context Fall-Through Lookup (*deprecated*)

Context fall-through lookup (automatic searching of outer contexts) is a feature that was added in NASM version 0.98.03. Unfortunately, this feature is unintuitive and can result in buggy code that would have otherwise been prevented by NASM's error reporting. As a result, this feature has been *deprecated*. NASM version 2.09 will issue a warning when usage of this *deprecated* feature is detected. Starting with NASM version 2.10, usage of this *deprecated* feature will simply result in an *expression syntax error*.

An example usage of this *deprecated* feature follows:

```

%macro ctxthru 0
%push ctx1
    %assign %%$external 1
    %push ctx2
        %assign %%$internal 1
        mov eax, %%$external
        mov eax, %%$internal
    %pop
%pop
%endmacro

```

As demonstrated, `%%$external` is being defined in the `ctx1` context and referenced within the `ctx2` context. With context fall-through lookup, referencing an undefined context-local macro like this implicitly searches through all outer contexts until a match is made or isn't found in any context. As a result, `%%$external` referenced within the `ctx2` context would implicitly use `%%$external` as defined in `ctx1`. Most people would expect NASM to issue an error in this situation because `%%$external` was never defined within `ctx2` and also isn't qualified with the proper context depth, `%%$%$external`.

Here is a revision of the above example with proper context depth:

```

%macro ctxthru 0
%push ctx1
    %assign %%$external 1
    %push ctx2
        %assign %%$internal 1
        mov eax, %%$%$external
        mov eax, %%$internal
    %pop

```

```
%pop
%endmacro
```

As demonstrated, `external` is still being defined in the `ctx1` context and referenced within the `ctx2` context. However, the reference to `external` within `ctx2` has been fully qualified with the proper context depth, `external`, and thus is no longer ambiguous, unintuitive or erroneous.

4.7.5 `repl`: Renaming a Context

If you need to change the name of the top context on the stack (in order, for example, to have it respond differently to `ifctx`), you can execute a `pop` followed by a `push`; but this will have the side effect of destroying all context-local labels and macros associated with the context that was just popped.

NASM provides the directive `repl`, which *replaces* a context with a different name, without touching the associated macros and labels. So you could replace the destructive code

```
%pop
%push    newname
```

with the non-destructive version `repl newname`.

4.7.6 Example Use of the Context Stack: Block IFs

This example makes use of almost all the context-stack features, including the conditional-assembly construct `ifctx`, to implement a block IF statement as a set of macros.

```
%macro if 1
    %push if
    jmp -1 %$ifnot
%endmacro

%macro else 0
    %ifctx if
        %repl else
        jmp %$ifend
        %$ifnot:
    %else
        %error "expected 'if' before 'else'"
    %endif
%endmacro

%macro endif 0
    %ifctx if
        %$ifnot:
        %pop
    %elifctx else
        %$ifend:
        %pop
    %else
        %error "expected 'if' or 'else' before 'endif'"
    %endif
%endmacro
```

```
%endmacro
```

This code is more robust than the REPEAT and UNTIL macros given in section 4.7.2, because it uses conditional assembly to check that the macros are issued in the right order (for example, not calling `endif` before `if`) and issues a `%error` if they're not.

In addition, the `endif` macro has to be able to cope with the two distinct cases of either directly following an `if`, or following an `else`. It achieves this, again, by using conditional assembly to do different things depending on whether the context on top of the stack is `if` or `else`.

The `else` macro has to preserve the context on the stack, in order to have the `%$ifnot` referred to by the `if` macro be the same as the one defined by the `endif` macro, but has to change the context's name so that `endif` will know there was an intervening `else`. It does this by the use of `%repl`.

A sample usage of these macros might look like:

```
    cmp     ax,bx

    if ae
        cmp     bx,cx

        if ae
            mov     ax,cx
        else
            mov     ax,bx
        endif
    else
        cmp     ax,cx

        if ae
            mov     ax,cx
        endif
    endif
```

The block-IF macros handle nesting quite happily, by means of pushing another context, describing the inner `if`, on top of the one describing the outer `if`; thus `else` and `endif` always refer to the last unmatched `if` or `else`.

4.8 Stack Relative Preprocessor Directives

The following preprocessor directives provide a way to use labels to refer to local variables allocated on the stack.

- `%arg` (see section 4.8.1)
- `%stacksize` (see section 4.8.2)
- `%local` (see section 4.8.3)

4.8.1 `%arg` Directive

The `%arg` directive is used to simplify the handling of parameters passed on the stack. Stack based parameter passing is used by many high level languages, including C, C++ and Pascal.

While NASM has macros which attempt to duplicate this functionality (see section 9.4.5), the syntax is not particularly convenient to use and is not TASM compatible. Here is an example which shows the use of `%arg` without any external macros:

```
some_function:
```

```
    %push    mycontext        ; save the current context
    %stacksize large          ; tell NASM to use bp
    %arg     i:word, j_ptr:word

    mov     ax,[i]
    mov     bx,[j_ptr]
    add     ax,[bx]
    ret

    %pop                                ; restore original context
```

This is similar to the procedure defined in section 9.4.5 and adds the value in `i` to the value pointed to by `j_ptr` and returns the sum in the `ax` register. See section 4.7.1 for an explanation of `push` and `pop` and the use of context stacks.

4.8.2 %stacksize Directive

The `%stacksize` directive is used in conjunction with the `%arg` (see section 4.8.1) and the `%local` (see section 4.8.3) directives. It tells NASM the default size to use for subsequent `%arg` and `%local` directives. The `%stacksize` directive takes one required argument which is one of `flat`, `flat64`, `large` or `small`.

```
%stacksize flat
```

This form causes NASM to use stack-based parameter addressing relative to `ebp` and it assumes that a near form of `call` was used to get to this label (i.e. that `ip` is on the stack).

```
%stacksize flat64
```

This form causes NASM to use stack-based parameter addressing relative to `rbp` and it assumes that a near form of `call` was used to get to this label (i.e. that `rip` is on the stack).

```
%stacksize large
```

This form uses `bp` to do stack-based parameter addressing and assumes that a far form of `call` was used to get to this address (i.e. that `ip` and `cs` are on the stack).

```
%stacksize small
```

This form also uses `bp` to address stack parameters, but it is different from `large` because it also assumes that the old value of `bp` is pushed onto the stack (i.e. it expects an `ENTER` instruction). In other words, it expects that `bp`, `ip` and `cs` are on the top of the stack, underneath any local space which may have been allocated by `ENTER`. This form is probably most useful when used in combination with the `%local` directive (see section 4.8.3).

4.8.3 %local Directive

The `%local` directive is used to simplify the use of local temporary stack variables allocated in a stack frame. Automatic local variables in C are an example of this kind of variable. The `%local` directive is most useful when used with the `%stacksize` (see section 4.8.2) and is also compatible with the `%arg` directive (see section 4.8.1). It allows simplified reference to variables on the stack which have been allocated typically by using the `ENTER` instruction. An example of its use is the following:

```
silly_swap:
```

```
    %push mycontext        ; save the current context
    %stacksize small      ; tell NASM to use bp
    %assign %$localsize 0 ; see text for explanation
```

```

%local old_ax:word, old_dx:word

    enter    %$localsize,0    ; see text for explanation
    mov     [old_ax],ax      ; swap ax & bx
    mov     [old_dx],dx      ; and swap dx & cx
    mov     ax,bx
    mov     dx,cx
    mov     bx,[old_ax]
    mov     cx,[old_dx]
    leave   ; restore old bp
    ret     ;

%pop          ; restore original context

```

The `%$localsize` variable is used internally by the `%local` directive and *must* be defined within the current context before the `%local` directive may be used. Failure to do so will result in one expression syntax error for each `%local` variable declared. It then may be used in the construction of an appropriately sized ENTER instruction as shown in the example.

4.9 Reporting User-Defined Errors: `%error`, `%warning`, `%fatal`

The preprocessor directive `%error` will cause NASM to report an error if it occurs in assembled code. So if other users are going to try to assemble your source files, you can ensure that they define the right macros by means of code like this:

```

%ifdef F1
    ; do some setup
%elifdef F2
    ; do some different setup
%else
    %error "Neither F1 nor F2 was defined."
%endif

```

Then any user who fails to understand the way your code is supposed to be assembled will be quickly warned of their mistake, rather than having to wait until the program crashes on being run and then not knowing what went wrong.

Similarly, `%warning` issues a warning, but allows assembly to continue:

```

%ifdef F1
    ; do some setup
%elifdef F2
    ; do some different setup
%else
    %warning "Neither F1 nor F2 was defined, assuming F1."
    %define F1
%endif

```

`%error` and `%warning` are issued only on the final assembly pass. This makes them safe to use in conjunction with tests that depend on symbol values.

`%fatal` terminates assembly immediately, regardless of pass. This is useful when there is no point in continuing the assembly further, and doing so is likely just going to cause a spew of confusing error messages.

It is optional for the message string after `%error`, `%warning` or `%fatal` to be quoted. If it is *not*, then single-line macros are expanded in it, which can be used to display more information to the user. For example:

```

%if foo > 64
    %assign foo_over foo-64
    %error foo is foo_over bytes too large
%endif

```

4.10 %pragma: Setting Options

The %pragma directive controls a number of options in NASM. Pragas are intended to remain backwards compatible, and therefore an unknown %pragma directive is not an error.

The various pragmas are documented with the options they affect.

The general structure of a NASM pragma is:

```
%pragma namespace directive [arguments...]
```

Currently defined namespaces are:

- `ignore`: this %pragma is unconditionally ignored.
- `preproc`: preprocessor, see section 4.10.1.
- `limit`: resource limits, see section 2.1.31.
- `asm`: the parser and assembler proper. Currently no such pragmas are defined.
- `list`: listing options, see section 2.1.4.
- `file`: general file handling options. Currently no such pragmas are defined.
- `input`: input file handling options. Currently no such pragmas are defined.
- `output`: output format options.
- `debug`: debug format options.

In addition, the name of any output or debug format, and sometimes groups thereof, also constitute %pragma namespaces. The namespaces `output` and `debug` simply refer to *any* output or debug format, respectively.

For example, to prepend an underscore to global symbols regardless of the output format (see section 7.10):

```
%pragma output gprefix _
```

... whereas to prepend an underscore to global symbols only when the output is either `win32` or `win64`:

```
%pragma win gprefix _
```

4.10.1 Preprocessor Pragas

The only preprocessor %pragma defined in NASM 2.15 is:

- `%pragma preproc sane_empty_expansion`: disables legacy compatibility handling of braceless empty arguments to multi-line macros. See section 4.3 and section 2.1.26.

4.11 Other Preprocessor Directives

4.11.1 %line Directive

The %line directive is used to notify NASM that the input line corresponds to a specific line number in another file. Typically this other file would be an original source file, with the current NASM input being the output of a pre-processor. The %line directive allows NASM to output messages which indicate the line number of the original source file, instead of the file that is being read by NASM.

This preprocessor directive is not generally used directly by programmers, but may be of interest to preprocessor authors. The usage of the `%line` preprocessor directive is as follows:

```
%line nnn[+mmm] [filename]
```

In this directive, `nnn` identifies the line of the original source file which this line corresponds to. `mmm` is an optional parameter which specifies a line increment value; each line of the input file read in is considered to correspond to `mmm` lines of the original source file. Finally, `filename` is an optional parameter which specifies the file name of the original source file. It may be a quoted string.

After reading a `%line` preprocessor directive, NASM will report all file name and line numbers relative to the values specified therein.

If the command line option `--no-line` is given, all `%line` directives are ignored. This may be useful for debugging preprocessed code. See section 2.1.33.

Starting in NASM 2.15, `%line` directives are processed before any other processing takes place.

4.11.2 `%!variable`: Read an Environment Variable.

The `%!variable` directive makes it possible to read the value of an environment variable at assembly time. This could, for example, be used to store the contents of an environment variable into a string, which could be used at some other point in your code.

For example, suppose that you have an environment variable `FOO`, and you want the contents of `FOO` to be embedded in your program as a quoted string. You could do that as follows:

```
%defstr FOO          %!FOO
```

See section 4.1.8 for notes on the `%defstr` directive.

If the name of the environment variable contains non-identifier characters, you can use string quotes to surround the name of the variable, for example:

```
%defstr C_colon     %!'C:'
```

4.11.3 `%clear`: Clear All Macro Definitions

The directive `%clear` clears all definitions of a certain type, *including the ones defined by NASM itself*. This can be useful when preprocessing non-NASM code, or to drop backwards compatibility aliases.

The syntax is:

```
%clear [global|context] type...
```

... where `context` indicates that this applies to context-local macros only; the default is `global`.

`type` can be one or more of:

- `define` single-line macros
- `defalias` single-line macro aliases (useful to remove backwards compatibility aliases)
- `alldefine` same as `define defalias`
- `macro` multi-line macros
- `all` same as `alldefine macro` (default)

In NASM 2.14 and earlier, only the single syntax `%clear` was supported, which is equivalent to `%clear global all`.

Chapter 5: Standard Macros

NASM defines a set of standard macros, which are already defined when it starts to process any source file. If you really need a program to be assembled with no pre-defined macros, you can use the `%clear` directive to empty the preprocessor of everything but context-local preprocessor variables and single-line macros, see section 4.11.3.

Most user-level assembler directives (see chapter 7) are implemented as macros which invoke primitive directives; these are described in chapter 7. The rest of the standard macro set is described here.

For compability with NASM versions before NASM 2.15, most standard macros of the form `__?foo?__` have aliases of form `__foo__` (see section 4.1.10). These can be removed with the directive `%clear defalias`.

5.1 NASM Version Macros

The single-line macros `__?NASM_MAJOR?__`, `__?NASM_MINOR?__`, `__?NASM_SUBMINOR?__` and `__?_NASM_PATCHLEVEL?__` expand to the major, minor, subminor and patch level parts of the version number of NASM being used. So, under NASM 0.98.32p1 for example, `__?NASM_MAJOR?__` would be defined to be 0, `__?NASM_MINOR?__` would be defined as 98, `__?NASM_SUBMINOR?__` would be defined to 32, and `__?_NASM_PATCHLEVEL?__` would be defined as 1.

Additionally, the macro `__?NASM_SNAPSHOT?__` is defined for automatically generated snapshot releases *only*.

5.1.1 `__?NASM_VERSION_ID?__`: NASM Version ID

The single-line macro `__?NASM_VERSION_ID?__` expands to a dword integer representing the full version number of the version of nasm being used. The value is the equivalent to `__?NASM_MAJOR?__`, `__?NASM_MINOR?__`, `__?NASM_SUBMINOR?__` and `__?_NASM_PATCHLEVEL?__` concatenated to produce a single doubleword. Hence, for 0.98.32p1, the returned number would be equivalent to:

```
dd    0x00622001
```

or

```
db    1,32,98,0
```

Note that the above lines are generate exactly the same code, the second line is used just to give an indication of the order that the separate values will be present in memory.

5.1.2 `__?NASM_VER?__`: NASM Version string

The single-line macro `__?NASM_VER?__` expands to a string which defines the version number of nasm being used. So, under NASM 0.98.32 for example,

```
db    __?NASM_VER?__
```

would expand to

```
db    "0.98.32"
```

5.2 `__?FILE?__` and `__?LINE?__`: File Name and Line Number

Like the C preprocessor, NASM allows the user to find out the file name and line number containing the current instruction. The macro `__?FILE?__` expands to a string constant giving the name of the current input file (which may change through the course of assembly if `%include` directives are used), and `__?LINE?__` expands to a numeric constant giving the current line number in the input file.

These macros could be used, for example, to communicate debugging information to a macro, since invoking `__?LINE?__` inside a macro definition (either single-line or multi-line) will return the line number of the macro *call*, rather than *definition*. So to determine where in a piece of code a crash is occurring, for example, one could write a routine `stillhere`, which is passed a line number in EAX and outputs something like `line 155: still here`. You could then write a macro:

```
%macro notdeadyet 0

    push    eax
    mov     eax, __?LINE?__
    call   stillhere
    pop     eax

%endmacro
```

and then pepper your code with calls to `notdeadyet` until you find the crash point.

5.3 `__?BITS?__`: Current Code Generation Mode

The `__?BITS?__` standard macro is updated every time that the BITS mode is set using the `BITS XX` or `[BITS XX]` directive, where `XX` is a valid mode number of 16, 32 or 64. `__?BITS?__` receives the specified mode number and makes it globally available. This can be very useful for those who utilize mode-dependent macros.

5.4 `__?OUTPUT_FORMAT?__`: Current Output Format

The `__?OUTPUT_FORMAT?__` standard macro holds the current output format name, as given by the `-f` option or NASM's default. Type `nasm -h` for a list.

```
%ifidn __?OUTPUT_FORMAT?__, win32
    %define NEWLINE 13, 10
%elifidn __?OUTPUT_FORMAT?__, elf32
    %define NEWLINE 10
%endif
```

5.5 `__?DEBUG_FORMAT?__`: Current Debug Format

If debugging information generation is enabled, The `__?DEBUG_FORMAT?__` standard macro holds the current debug format name as specified by the `-F` or `-g` option or the output format default. Type `nasm -f output y` for a list.

`__?DEBUG_FORMAT?__` is not defined if debugging is not enabled, or if the debug format specified is `null`.

5.6 Assembly Date and Time Macros

NASM provides a variety of macros that represent the timestamp of the assembly session.

- The `__?DATE?__` and `__?TIME?__` macros give the assembly date and time as strings, in ISO 8601 format ("`YYYY-MM-DD`" and "`HH:MM:SS`", respectively.)
- The `__?DATE_NUM?__` and `__?TIME_NUM?__` macros give the assembly date and time in numeric form; in the format `YYYYMMDD` and `HHMMSS` respectively.
- The `__?UTC_DATE?__` and `__?UTC_TIME?__` macros give the assembly date and time in universal time (UTC) as strings, in ISO 8601 format ("`YYYY-MM-DD`" and "`HH:MM:SS`", respectively.) If the host platform doesn't provide UTC time, these macros are undefined.

- The `__?UTC_DATE_NUM?__` and `__?UTC_TIME_NUM?__` macros give the assembly date and time universal time (UTC) in numeric form; in the format YYYYMMDD and HHMMSS respectively. If the host platform doesn't provide UTC time, these macros are undefined.
- The `__?POSIX_TIME?__` macro is defined as a number containing the number of seconds since the POSIX epoch, 1 January 1970 00:00:00 UTC; excluding any leap seconds. This is computed using UTC time if available on the host platform, otherwise it is computed using the local time as if it was UTC.

All instances of time and date macros in the same assembly session produce consistent output. For example, in an assembly session started at 42 seconds after midnight on January 1, 2010 in Moscow (timezone UTC+3) these macros would have the following values, assuming, of course, a properly configured environment with a correct clock:

```

__?DATE?__           "2010-01-01"
__?TIME?__           "00:00:42"
__?DATE_NUM?__       20100101
__?TIME_NUM?__       000042
__?UTC_DATE?__       "2009-12-31"
__?UTC_TIME?__       "21:00:42"
__?UTC_DATE_NUM?__   20091231
__?UTC_TIME_NUM?__   210042
__?POSIX_TIME?__     1262293242

```

5.7 `__?USE_package?__`: Package Include Test

When a standard macro package (see chapter 6) is included with the `%use` directive (see section 4.6.4), a single-line macro of the form `__USE_package__` is automatically defined. This allows testing if a particular package is invoked or not.

For example, if the `altreg` package is included (see section 6.1), then the macro `__?USE_ALTREG?__` is defined.

5.8 `__?PASS?__`: Assembly Pass

The macro `__?PASS?__` is defined to be 1 on preparatory passes, and 2 on the final pass. In preprocess-only mode, it is set to 3, and when running only to generate dependencies (due to the `-M` or `-MG` option, see section 2.1.5) it is set to 0.

Avoid using this macro if at all possible. It is tremendously easy to generate very strange errors by misusing it, and the semantics may change in future versions of NASM.

5.9 Structure Data Types

5.9.1 STRUC and ENDSTRUC: Declaring Structure Data Types

The core of NASM contains no intrinsic means of defining data structures; instead, the preprocessor is sufficiently powerful that data structures can be implemented as a set of macros. The macros `STRUC` and `ENDSTRUC` are used to define a structure data type.

`STRUC` takes one or two parameters. The first parameter is the name of the data type. The second, optional parameter is the base offset of the structure. The name of the data type is defined as a symbol with the value of the base offset, and the name of the data type with the suffix `_size` appended to it is defined as an `EQU` giving the size of the structure. Once `STRUC` has been issued, you are defining the structure, and should define fields using the `RESB` family of pseudo-instructions, and then invoke `ENDSTRUC` to finish the definition.

For example, to define a structure called `mytype` containing a longword, a word, a byte and a string of bytes, you might code

```

struc    mytype

    mt_long:    resd    1
    mt_word:    resw    1
    mt_byte:    resb    1
    mt_str:     resb    32

```

```
endstruc
```

The above code defines six symbols: `mt_long` as 0 (the offset from the beginning of a `mytype` structure to the longword field), `mt_word` as 4, `mt_byte` as 6, `mt_str` as 7, `mytype_size` as 39, and `mytype` itself as zero.

The reason why the structure type name is defined at zero by default is a side effect of allowing structures to work with the local label mechanism: if your structure members tend to have the same names in more than one structure, you can define the above structure like this:

```

struc mytype

    .long:      resd    1
    .word:      resw    1
    .byte:      resb    1
    .str:       resb    32

```

```
endstruc
```

This defines the offsets to the structure fields as `mytype.long`, `mytype.word`, `mytype.byte` and `mytype.str`.

NASM, since it has no *intrinsic* structure support, does not support any form of period notation to refer to the elements of a structure once you have one (except the above local-label notation), so code such as `mov ax, [mystruc.mt_word]` is not valid. `mt_word` is a constant just like any other constant, so the correct syntax is `mov ax, [mystruc+mt_word]` or `mov ax, [mystruc+mytype.word]`.

Sometimes you only have the address of the structure displaced by an offset. For example, consider this standard stack frame setup:

```

push ebp
mov  ebp, esp
sub  esp, 40

```

In this case, you could access an element by subtracting the offset:

```
mov [ebp - 40 + mytype.word], ax
```

However, if you do not want to repeat this offset, you can use `-40` as a base offset:

```
struc mytype, -40
```

And access an element this way:

```
mov [ebp + mytype.word], ax
```

5.9.2 ISTRUC, AT and IEND: Declaring Instances of Structures

Having defined a structure type, the next thing you typically want to do is to declare instances of that structure in your data segment. NASM provides an easy way to do this in the `ISTRUC` mechanism. To declare a structure of type `mytype` in a program, you code something like this:

```

mystruc:
    istruc mytype

```

```

    at mt_long, dd    123456
    at mt_word, dw    1024
    at mt_byte, db    'x'
    at mt_str,  db    'hello, world', 13, 10, 0

```

```

iend

```

The function of the AT macro is to make use of the TIMES prefix to advance the assembly position to the correct point for the specified structure field, and then to declare the specified data. Therefore the structure fields must be declared in the same order as they were specified in the structure definition.

If the data to go in a structure field requires more than one source line to specify, the remaining source lines can easily come after the AT line. For example:

```

    at mt_str,  db    123,134,145,156,167,178,189
                    db    190,100,0

```

Depending on personal taste, you can also omit the code part of the AT line completely, and start the structure field on the next line:

```

    at mt_str
        db    'hello, world'
        db    13,10,0

```

5.10 Alignment Control

5.10.1 ALIGN and ALIGNB: Code and Data Alignment

The ALIGN and ALIGNB macros provides a convenient way to align code or data on a word, longword, paragraph or other boundary. (Some assemblers call this directive EVEN.) The syntax of the ALIGN and ALIGNB macros is

```

align  4                ; align on 4-byte boundary
align  16               ; align on 16-byte boundary
align  8,db 0           ; pad with 0s rather than NOPs
align  4,resb 1         ; align to 4 in the BSS
alignb 4                ; equivalent to previous line

```

Both macros require their first argument to be a power of two; they both compute the number of additional bytes required to bring the length of the current section up to a multiple of that power of two, and then apply the TIMES prefix to their second argument to perform the alignment.

If the second argument is not specified, the default for ALIGN is NOP, and the default for ALIGNB is RESB 1. So if the second argument is specified, the two macros are equivalent. Normally, you can just use ALIGN in code and data sections and ALIGNB in BSS sections, and never need the second argument except for special purposes.

ALIGN and ALIGNB, being simple macros, perform no error checking: they cannot warn you if their first argument fails to be a power of two, or if their second argument generates more than one byte of code. In each of these cases they will silently do the wrong thing.

ALIGNB (or ALIGN with a second argument of RESB 1) can be used within structure definitions:

```

struc mytype2
    mt_byte:
        resb 1
        alignb 2
    mt_word:

```

```

        resw 1
        alignb 4
mt_long:
        resd 1
mt_str:
        resb 32

```

endstruc

This will ensure that the structure members are sensibly aligned relative to the base of the structure.

A final caveat: ALIGN and ALIGNB work relative to the beginning of the *section*, not the beginning of the address space in the final executable. Aligning to a 16-byte boundary when the section you're in is only guaranteed to be aligned to a 4-byte boundary, for example, is a waste of effort. Again, NASM does not check that the section's alignment characteristics are sensible for the use of ALIGN or ALIGNB.

Both ALIGN and ALIGNB do call SECTALIGN macro implicitly. See section 5.10.2 for details.

See also the `smartalign` standard macro package, section 6.2.

5.10.2 SECTALIGN: Section Alignment

The SECTALIGN macros provides a way to modify alignment attribute of output file section. Unlike the `align=` attribute (which is allowed at section definition only) the SECTALIGN macro may be used at any time.

For example the directive

```
SECTALIGN 16
```

sets the section alignment requirements to 16 bytes. Once increased it can not be decreased, the magnitude may grow only.

Note that ALIGN (see section 5.10.1) calls the SECTALIGN macro implicitly so the active section alignment requirements may be updated. This is by default behaviour, if for some reason you want the ALIGN do not call SECTALIGN at all use the directive

```
SECTALIGN OFF
```

It is still possible to turn in on again by

```
SECTALIGN ON
```

Note that SECTALIGN <ON|OFF> affects only the ALIGN/ALIGNB directives, not an explicit SECTALIGN directive.

Chapter 6: Standard Macro Packages

The `%use` directive (see section 4.6.4) includes one of the standard macro packages included with the NASM distribution and compiled into the NASM binary. It operates like the `%include` directive (see section 4.6.1), but the included contents is provided by NASM itself.

The names of standard macro packages are case insensitive and can be quoted or not.

As of version 2.15, NASM has `%ifusable` and `%ifusing` directives to help the user understand whether an individual package available in this version of NASM (`%ifusable`) or a particular package already loaded (`%ifusing`).

6.1 `altreg`: Alternate Register Names

The `altreg` standard macro package provides alternate register names. It provides numeric register names for all registers (not just R8–R15), the Intel-defined aliases R8L–R15L for the low bytes of register (as opposed to the NASM/AMD standard names R8B–R15B), and the names R0H–R3H (by analogy with R0L–R3L) for AH, CH, DH, and BH.

Example use:

```
%use altreg
```

```
proc:
    mov r0l,r3h                ; mov al,bh
    ret
```

See also section 12.1.

6.2 `smartalign`: Smart ALIGN Macro

The `smartalign` standard macro package provides for an ALIGN macro which is more powerful than the default (and backwards-compatible) one (see section 5.10.1). When the `smartalign` package is enabled, when ALIGN is used without a second argument, NASM will generate a sequence of instructions more efficient than a series of NOP. Furthermore, if the padding exceeds a specific threshold, then NASM will generate a jump over the entire padding sequence.

The specific instructions generated can be controlled with the new ALIGNMODE macro. This macro takes two parameters: one mode, and an optional jump threshold override. If (for any reason) you need to turn off the jump completely just set jump threshold value to -1 (or set it to `nojump`). The following modes are possible:

- `generic`: Works on all x86 CPUs and should have reasonable performance. The default jump threshold is 8. This is the default.
- `nop`: Pad out with NOP instructions. The only difference compared to the standard ALIGN macro is that NASM can still jump over a large padding area. The default jump threshold is 16.
- `k7`: Optimize for the AMD K7 (Athlon/Althon XP). These instructions should still work on all x86 CPUs. The default jump threshold is 16.
- `k8`: Optimize for the AMD K8 (Opteron/Althon 64). These instructions should still work on all x86 CPUs. The default jump threshold is 16.
- `p6`: Optimize for Intel CPUs. This uses the long NOP instructions first introduced in Pentium Pro. This is incompatible with all CPUs of family 5 or lower, as well as some VIA CPUs and several virtualization solutions. The default jump threshold is 16.

The macro `__?ALIGNMODE?__` is defined to contain the current alignment mode. A number of other macros beginning with `__?ALIGN_` are used internally by this macro package.

6.3 fp: Floating-point macros

This packages contains the following floating-point convenience macros:

```
%define Inf          __?Infinity?__
%define NaN          __?QNaN?__
%define QNaN         __?QNaN?__
%define SNaN        __?SNaN?__

%define float8(x)    __?float8?__(x)
%define float16(x)   __?float16?__(x)
%define float32(x)   __?float32?__(x)
%define float64(x)   __?float64?__(x)
%define float80m(x)  __?float80m?__(x)
%define float80e(x)  __?float80e?__(x)
%define float128l(x) __?float128l?__(x)
%define float128h(x) __?float128h?__(x)
```

6.4 i func: Integer functions

This package contains a set of macros which implement integer functions. These are actually implemented as special operators, but are most conveniently accessed via this macro package.

The macros provided are:

6.4.1 Integer logarithms

These functions calculate the integer logarithm base 2 of their argument, considered as an unsigned integer. The only differences between the functions is their respective behavior if the argument provided is not a power of two.

The function `i log2e()` (alias `i log2()`) generates an error if the argument is not a power of two.

The function `i log2f()` rounds the argument down to the nearest power of two; if the argument is zero it returns zero.

The function `i log2c()` rounds the argument up to the nearest power of two.

The functions `i log2fw()` (alias `i log2w()`) and `i log2cw()` generate a warning if the argument is not a power of two, but otherwise behaves like `i log2f()` and `i log2c()`, respectively.

6.5 masm: MASM compatibility

Since version 2.15, NASM has a MASM compatibility package with minimal functionality, as intended to be used primarily with machine-generated code. It does not include any "programmer-friendly" shortcuts, nor does it in any way support ASSUME, symbol typing, or MASM-style structures.

Currently, the MASM compatibility package emulates only the PTR keyword and recognize syntax `displacement[index]` for memory operations.

To enable the package, use the directive:

```
%use masm
```


Chapter 7: Assembler Directives

NASM, though it attempts to avoid the bureaucracy of assemblers like MASM and TASM, is nevertheless forced to support a *few* directives. These are described in this chapter.

NASM's directives come in two types: *user-level* directives and *primitive* directives. Typically, each directive has a user-level form and a primitive form. In almost all cases, we recommend that users use the user-level forms of the directives, which are implemented as macros which call the primitive forms.

Primitive directives are enclosed in square brackets; user-level directives are not.

In addition to the universal directives described in this chapter, each object file format can optionally supply extra directives in order to control particular features of that file format. These *format-specific* directives are documented along with the formats that implement them, in chapter 8.

7.1 BITS: Specifying Target Processor Mode

The BITS directive specifies whether NASM should generate code designed to run on a processor operating in 16-bit mode, 32-bit mode or 64-bit mode. The syntax is `BITS XX`, where `XX` is 16, 32 or 64.

In most cases, you should not need to use BITS explicitly. The `aout`, `coff`, `elf*`, `macho`, `win32` and `win64` object formats, which are designed for use in 32-bit or 64-bit operating systems, all cause NASM to select 32-bit or 64-bit mode, respectively, by default. The `obj` object format allows you to specify each segment you define as either `USE16` or `USE32`, and NASM will set its operating mode accordingly, so the use of the BITS directive is once again unnecessary.

The most likely reason for using the BITS directive is to write 32-bit or 64-bit code in a flat binary file; this is because the `bin` output format defaults to 16-bit mode in anticipation of it being used most frequently to write DOS `.COM` programs, DOS `.SYS` device drivers and boot loader software.

The BITS directive can also be used to generate code for a different mode than the standard one for the output format.

You do *not* need to specify `BITS 32` merely in order to use 32-bit instructions in a 16-bit DOS program; if you do, the assembler will generate incorrect code because it will be writing code targeted at a 32-bit platform, to be run on a 16-bit one.

When NASM is in `BITS 16` mode, instructions which use 32-bit data are prefixed with an `0x66` byte, and those referring to 32-bit addresses have an `0x67` prefix. In `BITS 32` mode, the reverse is true: 32-bit instructions require no prefixes, whereas instructions using 16-bit data need an `0x66` and those working on 16-bit addresses need an `0x67`.

When NASM is in `BITS 64` mode, most instructions operate the same as they do for `BITS 32` mode. However, there are 8 more general and SSE registers, and 16-bit addressing is no longer supported.

The default address size is 64 bits; 32-bit addressing can be selected with the `0x67` prefix. The default operand size is still 32 bits, however, and the `0x66` prefix selects 16-bit operand size. The REX prefix is used both to select 64-bit operand size, and to access the new registers. NASM automatically inserts REX prefixes when necessary.

When the REX prefix is used, the processor does not know how to address the AH, BH, CH or DH (high 8-bit legacy) registers. Instead, it is possible to access the the low 8-bits of the SP, BP SI and DI registers as SPL, BPL, SIL and DIL, respectively; but only when the REX prefix is used.

The BITS directive has an exactly equivalent primitive form, `[BITS 16]`, `[BITS 32]` and `[BITS 64]`. The user-level form is a macro which has no function other than to call the primitive form.

Note that the space is necessary, e.g. BITS32 will *not* work!

7.1.1 USE16 & USE32: Aliases for BITS

The 'USE16' and 'USE32' directives can be used in place of 'BITS 16' and 'BITS 32', for compatibility with other assemblers.

7.2 DEFAULT: Change the assembler defaults

The DEFAULT directive changes the assembler defaults. Normally, NASM defaults to a mode where the programmer is expected to explicitly specify most features directly. However, this is occasionally obnoxious, as the explicit form is pretty much the only one one wishes to use.

Currently, DEFAULT can set REL & ABS and BND & NOBND.

7.2.1 REL & ABS: RIP-relative addressing

This sets whether registerless instructions in 64-bit mode are RIP-relative or not. By default, they are absolute unless overridden with the REL specifier (see section 3.3). However, if DEFAULT REL is specified, REL is default, unless overridden with the ABS specifier, *except when used with an FS or GS segment override*.

The special handling of FS and GS overrides are due to the fact that these registers are generally used as thread pointers or other special functions in 64-bit mode, and generating RIP-relative addresses would be extremely confusing.

DEFAULT REL is disabled with DEFAULT ABS.

7.2.2 BND & NOBND: BND prefix

If DEFAULT BND is set, all bnd-prefix available instructions following this directive are prefixed with bnd. To override it, NOBND prefix can be used.

```
DEFAULT BND
    call foo                ; BND will be prefixed
    nobnd call foo         ; BND will NOT be prefixed
```

DEFAULT NOBND can disable DEFAULT BND and then BND prefix will be added only when explicitly specified in code.

DEFAULT BND is expected to be the normal configuration for writing MPX-enabled code.

7.3 SECTION or SEGMENT: Changing and Defining Sections

The SECTION directive (SEGMENT is an exactly equivalent synonym) changes which section of the output file the code you write will be assembled into. In some object file formats, the number and names of sections are fixed; in others, the user may make up as many as they wish. Hence SECTION may sometimes give an error message, or may define a new section, if you try to switch to a section that does not (yet) exist.

The Unix object formats, and the bin object format (but see section 8.1.3), all support the standardized section names .text, .data and .bss for the code, data and uninitialized-data sections. The obj format, by contrast, does not recognize these section names as being special, and indeed will strip off the leading period of any section name that has one.

7.3.1 The __?SECT?__ Macro

The SECTION directive is unusual in that its user-level form functions differently from its primitive form. The primitive form, [SECTION xyz], simply switches the current target section to the one given. The user-level form, SECTION xyz, however, first defines the single-line macro __?SECT?__

to be the primitive [SECTION] directive which it is about to issue, and then issues it. So the user-level directive

```
SECTION .text
```

expands to the two lines

```
%define __?SECT?__ [SECTION .text]
[SECTION .text]
```

Users may find it useful to make use of this in their own macros. For example, the `writeln` macro defined in section 4.3.3 can be usefully rewritten in the following more sophisticated form:

```
%macro writeln 2+
    [section .data]

    %%str:      db      %2
    %%endstr:

    __?SECT?__

    mov     dx,%%str
    mov     cx,%%endstr-%%str
    mov     bx,%1
    mov     ah,0x40
    int     0x21

%endmacro
```

This form of the macro, once passed a string to output, first switches temporarily to the data section of the file, using the primitive form of the SECTION directive so as not to modify __?SECT?__. It then declares its string in the data section, and then invokes __?SECT?__ to switch back to *whichever* section the user was previously working in. It thus avoids the need, in the previous version of the macro, to include a JMP instruction to jump over the data, and also does not fail if, in a complicated OBJ format module, the user could potentially be assembling the code in any of several separate code sections.

7.4 ABSOLUTE: Defining Absolute Labels

The ABSOLUTE directive can be thought of as an alternative form of SECTION: it causes the subsequent code to be directed at no physical section, but at the hypothetical section starting at the given absolute address. The only instructions you can use in this mode are the RESB family.

ABSOLUTE is used as follows:

```
absolute 0x1A

    kbuf_chr    resw    1
    kbuf_free   resw    1
    kbuf        resw   16
```

This example describes a section of the PC BIOS data area, at segment address 0x40: the above code defines `kbuf_chr` to be 0x1A, `kbuf_free` to be 0x1C, and `kbuf` to be 0x1E.

The user-level form of ABSOLUTE, like that of SECTION, redefines the __?SECT?__ macro when it is invoked.

STRUC and ENDSTRUC are defined as macros which use ABSOLUTE (and also __?SECT?__).

ABSOLUTE doesn't have to take an absolute constant as an argument: it can take an expression (actually, a critical expression: see section 3.8) and it can be a value in a segment. For example, a TSR can re-use its setup code as run-time BSS like this:

```
org      100h                ; it's a .COM program

jmp      setup                ; setup code comes last

; the resident part of the TSR goes here
setup:
; now write the code that installs the TSR here

absolute setup

runtimevar1    resw    1
runtimevar2    resd    20

tsr_end:
```

This defines some variables 'on top of' the setup code, so that after the setup has finished running, the space it took up can be re-used as data storage for the running TSR. The symbol 'tsr_end' can be used to calculate the total size of the part of the TSR that needs to be made resident.

7.5 EXTERN: Importing Symbols from Other Modules

EXTERN is similar to the MASM directive EXTRN and the C keyword extern: it is used to declare a symbol which is not defined anywhere in the module being assembled, but is assumed to be defined in some other module and needs to be referred to by this one. Not every object-file format can support external variables: the bin format cannot.

The EXTERN directive takes as many arguments as you like. Each argument is the name of a symbol:

```
extern _printf
extern _sscanf,_fscanf
```

Some object-file formats provide extra features to the EXTERN directive. In all cases, the extra features are used by suffixing a colon to the symbol name followed by object-format specific text. For example, the obj format allows you to declare that the default segment base of an external should be the group dgroup by means of the directive

```
extern _variable:wrt dgroup
```

The primitive form of EXTERN differs from the user-level form only in that it can take only one argument at a time: the support for multiple arguments is implemented at the preprocessor level.

You can declare the same variable as EXTERN more than once: NASM will quietly ignore the second and later redeclarations.

If a variable is declared both GLOBAL and EXTERN, or if it is declared as EXTERN and then defined, it will be treated as GLOBAL. If a variable is declared both as COMMON and EXTERN, it will be treated as COMMON.

7.6 REQUIRED: Importing Symbols from Other Modules

The REQUIRED keyword is similar to EXTERN one. The difference is that the EXTERN keyword as of version 2.15 does not generate unknown symbols, as this behavior is highly undesirable when using common header files, because it might cause the linker to pull in a bunch of unnecessary modules, depending on how smart the linker is.

If the old behavior is required, use REQUIRED keyword instead.

7.7 GLOBAL: Exporting Symbols to Other Modules

GLOBAL is the other end of EXTERN: if one module declares a symbol as EXTERN and refers to it, then in order to prevent linker errors, some other module must actually *define* the symbol and declare it as GLOBAL. Some assemblers use the name PUBLIC for this purpose.

GLOBAL uses the same syntax as EXTERN, except that it must refer to symbols which *are* defined in the same module as the GLOBAL directive. For example:

```
global _main
_main:
    ; some code
```

GLOBAL, like EXTERN, allows object formats to define private extensions by means of a colon. The ELF object format, for example, lets you specify whether global data items are functions or data:

```
global hashlookup:function, hashtable:data
```

Like EXTERN, the primitive form of GLOBAL differs from the user-level form only in that it can take only one argument at a time.

7.8 COMMON: Defining Common Data Areas

The COMMON directive is used to declare *common variables*. A common variable is much like a global variable declared in the uninitialized data section, so that

```
common intvar 4
```

is similar in function to

```
global intvar
section .bss
```

```
intvar resd 1
```

The difference is that if more than one module defines the same common variable, then at link time those variables will be *merged*, and references to `intvar` in all modules will point at the same piece of memory.

Like GLOBAL and EXTERN, COMMON supports object-format specific extensions. For example, the `obj` format allows common variables to be NEAR or FAR, and the ELF format allows you to specify the alignment requirements of a common variable:

```
common commvar 4:near ; works in OBJ
common intarray 100:4 ; works in ELF: 4 byte aligned
```

Once again, like EXTERN and GLOBAL, the primitive form of COMMON differs from the user-level form only in that it can take only one argument at a time.

7.9 STATIC: Local Symbols within Modules

Opposite to EXTERN and GLOBAL, STATIC is local symbol, but should be named according to the global mangling rules (named by analogy with the C keyword `static` as applied to functions or global variables).

```
static foo
foo:
    ; codes
```

Unlike GLOBAL, STATIC does not allow object formats to accept private extensions mentioned in section 7.7.

7.10 (G|L)PREFIX, (G|L)POSTFIX: Mangling Symbols

PREFIX, GPREFIX, LPREFIX, POSTFIX, GPOSTFIX, and LPOSTFIX directives can prepend or append a string to a certain type of symbols, normally to fit specific ABI conventions

- PREFIX|GPREFIX: Prepend the argument to all EXTERN COMMON, STATIC, and GLOBAL symbols.
- LPREFIX: Prepend the argument to all other symbols such as local labels and backend defined symbols.
- POSTFIX|GPOSTFIX: Append the argument to all EXTERN COMMON, STATIC, and GLOBAL symbols.
- LPOSTFIX: Append the argument to all other symbols such as local labels and backend defined symbols.

These a macros implemented as pragmas, and using %pragma syntax can be restricted to specific backends (see section 4.10):

```
%pragma macho lprefix L_
```

Command line options are also available. See also section 2.1.28.

One example which supports many ABIs:

```
; The most common conventions
%pragma output gprefix _
%pragma output lprefix L_
; ELF uses a different convention
%pragma elf gprefix ; empty
%pragma elf lprefix .L
```

Some toolchains is aware of a particular prefix for its own optimization options, such as code elimination. For instance, Mach-O backend has a linker that uses a simplistic naming scheme to chunk up sections into a meta section. When the subsections_via_symbols directive (section 8.8.4) is declared, each symbol is the start of a separate block. The meta section is, then, defined to include sections before the one that starts with a 'L'. LPREFIX is useful here to mark all local symbols with the 'L' prefix to be excluded to the meta section. It converts local symbols compatible with the particular toolchain. Note that local symbols declared with STATIC (section 7.9) are excluded from the symbol mangling and also not marked as global.

7.11 CPU: Defining CPU Dependencies

The CPU directive restricts assembly to those instructions which are available on the specified CPU.

Options are:

- CPU 8086 Assemble only 8086 instruction set
- CPU 186 Assemble instructions up to the 80186 instruction set
- CPU 286 Assemble instructions up to the 286 instruction set
- CPU 386 Assemble instructions up to the 386 instruction set
- CPU 486 486 instruction set
- CPU 586 Pentium instruction set
- CPU PENTIUM Same as 586
- CPU 686 P6 instruction set
- CPU PPRO Same as 686

- CPU P2 Same as 686
- CPU P3 Pentium III (Katmai) instruction sets
- CPU KATMAI Same as P3
- CPU P4 Pentium 4 (Willamette) instruction set
- CPU WILLAMETTE Same as P4
- CPU PRESCOTT Prescott instruction set
- CPU X64 x86-64 (x64/AMD64/Intel 64) instruction set
- CPU IA64 IA64 CPU (in x86 mode) instruction set

All options are case insensitive. All instructions will be selected only if they apply to the selected CPU or lower. By default, all instructions are available.

7.12 FLOAT: Handling of floating-point constants

By default, floating-point constants are rounded to nearest, and IEEE denormals are supported. The following options can be set to alter this behaviour:

- `FLOAT DAZ` Flush denormals to zero
- `FLOAT NODAZ` Do not flush denormals to zero (default)
- `FLOAT NEAR` Round to nearest (default)
- `FLOAT UP` Round up (toward +Infinity)
- `FLOAT DOWN` Round down (toward -Infinity)
- `FLOAT ZERO` Round toward zero
- `FLOAT DEFAULT` Restore default settings

The standard macros `__?FLOAT_DAZ?__`, `__?FLOAT_ROUND?__`, and `__?FLOAT?__` contain the current state, as long as the programmer has avoided the use of the bracketed primitive form, (`[FLOAT]`).

`__?FLOAT?__` contains the full set of floating-point settings; this value can be saved away and invoked later to restore the setting.

7.13 [WARNING]: Enable or disable warnings

The `[WARNING]` directive can be used to enable or disable classes of warnings in the same way as the `-w` option, see section 2.1.26 for more details about warning classes.

- `[warning +warning-class]` enables warnings for *warning-class*.
- `[warning -warning-class]` disables warnings for *warning-class*.
- `[warning *warning-class]` restores *warning-class* to the original value, either the default value or as specified on the command line.
- `[warning push]` saves the current warning state on a stack.
- `[warning pop]` restores the current warning state from the stack.

The `[WARNING]` directive also accepts the `all`, `error` and `error=warning-class` specifiers.

No "user form" (without the brackets) currently exists.

Chapter 8: Output Formats

NASM is a portable assembler, designed to be able to compile on any ANSI C-supporting platform and produce output to run on a variety of Intel x86 operating systems. For this reason, it has a large number of available output formats, selected using the `-f` option on the NASM command line. Each of these formats, along with its extensions to the base NASM syntax, is detailed in this chapter.

As stated in section 2.1.1, NASM chooses a default name for your output file based on the input file name and the chosen output format. This will be generated by removing the extension (`.asm`, `.s`, or whatever you like to use) from the input file name, and substituting an extension defined by the output format. The extensions are given with each format below.

8.1 `bin`: Flat-Form Binary Output

The `bin` format does not produce object files: it generates nothing in the output file except the code you wrote. Such 'pure binary' files are used by MS-DOS: `.COM` executables and `.SYS` device drivers are pure binary files. Pure binary output is also useful for operating system and boot loader development.

The `bin` format supports multiple section names. For details of how NASM handles sections in the `bin` format, see section 8.1.3.

Using the `bin` format puts NASM by default into 16-bit mode (see section 7.1). In order to use `bin` to write 32-bit or 64-bit code, such as an OS kernel, you need to explicitly issue the `BITS 32` or `BITS 64` directive.

`bin` has no default output file name extension: instead, it leaves your file name as it is once the original extension has been removed. Thus, the default is for NASM to assemble `binprog.asm` into a binary file called `binprog`.

8.1.1 `ORG`: Binary File Program Origin

The `bin` format provides an additional directive to the list given in chapter 7: `ORG`. The function of the `ORG` directive is to specify the origin address which NASM will assume the program begins at when it is loaded into memory.

For example, the following code will generate the longword `0x00000104`:

```
org      0x100
dd      label
label:
```

Unlike the `ORG` directive provided by MASM-compatible assemblers, which allows you to jump around in the object file and overwrite code you have already generated, NASM's `ORG` does exactly what the directive says: *origin*. Its sole function is to specify one offset which is added to all internal address references within the section; it does not permit any of the trickery that MASM's version does. See section 13.1.3 for further comments.

8.1.2 `bin` Extensions to the `SECTION` Directive

The `bin` output format extends the `SECTION` (or `SEGMENT`) directive to allow you to specify the alignment requirements of segments. This is done by appending the `ALIGN` qualifier to the end of the section-definition line. For example,

```
section .data align=16
```

switches to the section `.data` and also specifies that it must be aligned on a 16-byte boundary.

The parameter to `ALIGN` specifies how many low bits of the section start address must be forced to zero. The alignment value given may be any power of two.

8.1.3 Multisection Support for the bin Format

The `bin` format allows the use of multiple sections, of arbitrary names, besides the "known" `.text`, `.data`, and `.bss` names.

- Sections may be designated `progbits` or `nobits`. Default is `progbits` (except `.bss`, which defaults to `nobits`, of course).
- Sections can be aligned at a specified boundary following the previous section with `align=`, or at an arbitrary byte-granular position with `start=`.
- Sections can be given a virtual start address, which will be used for the calculation of all memory references within that section with `vstart=`.
- Sections can be ordered using `follows=<section>` or `vfollows=<section>` as an alternative to specifying an explicit start address.
- Arguments to `org`, `start`, `vstart`, and `align=` are critical expressions. See section 3.8. E.g. `align=(1 << ALIGN_SHIFT) - ALIGN_SHIFT` must be defined before it is used here.
- Any code which comes before an explicit `SECTION` directive is directed by default into the `.text` section.
- If an `ORG` statement is not given, `ORG 0` is used by default.
- The `.bss` section will be placed after the last `progbits` section, unless `start=`, `vstart=`, `follows=`, or `vfollows=` has been specified.
- All sections are aligned on `dword` boundaries, unless a different alignment has been specified.
- Sections may not overlap.
- NASM creates the `section.<secname>.start` for each section, which may be used in your code.

8.1.4 Map Files

Map files can be generated in `-f bin` format by means of the `[map]` option. Map types of all (default), `brief`, `sections`, `segments`, or `symbols` may be specified. Output may be directed to `stdout` (default), `stderr`, or a specified file. E.g. `[map symbols myfile.map]`. No "user form" exists, the square brackets must be used.

8.2 ith: Intel Hex Output

The `ith` file format produces Intel hex-format files. Just as the `bin` format, this is a flat memory image format with no support for relocation or linking. It is usually used with ROM programmers and similar utilities.

All extensions supported by the `bin` file format is also supported by the `ith` file format.

`ith` provides a default output file-name extension of `.ith`.

8.3 srec: Motorola S-Records Output

The `srec` file format produces Motorola S-records files. Just as the `bin` format, this is a flat memory image format with no support for relocation or linking. It is usually used with ROM programmers and similar utilities.

All extensions supported by the `bin` file format is also supported by the `srec` file format.

`srec` provides a default output file-name extension of `.srec`.

8.4 obj: Microsoft OMF Object Files

The obj file format (NASM calls it obj rather than omf for historical reasons) is the one produced by MASM and TASM, which is typically fed to 16-bit DOS linkers to produce .EXE files. It is also the format used by OS/2.

obj provides a default output file-name extension of .obj.

obj is not exclusively a 16-bit format, though: NASM has full support for the 32-bit extensions to the format. In particular, 32-bit obj format files are used by Borland's Win32 compilers, instead of using Microsoft's newer win32 object file format.

The obj format does not define any special segment names: you can call your segments anything you like. Typical names for segments in obj format files are CODE, DATA and BSS.

If your source file contains code before specifying an explicit SEGMENT directive, then NASM will invent its own segment called __NASMDEFSEG for you.

When you define a segment in an obj file, NASM defines the segment name as a symbol as well, so that you can access the segment address of the segment. So, for example:

```
segment data

dvar:  dw      1234

segment code

function:
    mov     ax,data           ; get segment address of data
    mov     ds,ax            ; and move it into DS
    inc     word [dvar]      ; now this reference will work
    ret
```

The obj format also enables the use of the SEG and WRT operators, so that you can write code which does things like

```
extern  foo

    mov     ax,seg foo       ; get preferred segment of foo
    mov     ds,ax
    mov     ax,data         ; a different segment
    mov     es,ax
    mov     ax,[ds:foo]     ; this accesses 'foo'
    mov     [es:foo wrt data],bx ; so does this
```

8.4.1 obj Extensions to the SEGMENT Directive

The obj output format extends the SEGMENT (or SECTION) directive to allow you to specify various properties of the segment you are defining. This is done by appending extra qualifiers to the end of the segment-definition line. For example,

```
segment code private align=16
```

defines the segment code, but also declares it to be a private segment, and requires that the portion of it described in this code module must be aligned on a 16-byte boundary.

The available qualifiers are:

- PRIVATE, PUBLIC, COMMON and STACK specify the combination characteristics of the segment. PRIVATE segments do not get combined with any others by the linker; PUBLIC and STACK

segments get concatenated together at link time; and COMMON segments all get overlaid on top of each other rather than stuck end-to-end.

- ALIGN is used, as shown above, to specify how many low bits of the segment start address must be forced to zero. The alignment value given may be any power of two from 1 to 4096; in reality, the only values supported are 1, 2, 4, 16, 256 and 4096, so if 8 is specified it will be rounded up to 16, and 32, 64 and 128 will all be rounded up to 256, and so on. Note that alignment to 4096-byte boundaries is a PharLap extension to the format and may not be supported by all linkers.
- CLASS can be used to specify the segment class; this feature indicates to the linker that segments of the same class should be placed near each other in the output file. The class name can be any word, e.g. CLASS=CODE.
- OVERLAY, like CLASS, is specified with an arbitrary word as an argument, and provides overlay information to an overlay-capable linker.
- Segments can be declared as USE16 or USE32, which has the effect of recording the choice in the object file and also ensuring that NASM's default assembly mode when assembling in that segment is 16-bit or 32-bit respectively.
- When writing OS/2 object files, you should declare 32-bit segments as FLAT, which causes the default segment base for anything in the segment to be the special group FLAT, and also defines the group if it is not already defined.
- The obj file format also allows segments to be declared as having a pre-defined absolute segment address, although no linkers are currently known to make sensible use of this feature; nevertheless, NASM allows you to declare a segment such as SEGMENT SCREEN ABSOLUTE=0xB800 if you need to. The ABSOLUTE and ALIGN keywords are mutually exclusive.

NASM's default segment attributes are PUBLIC, ALIGN=1, no class, no overlay, and USE16.

8.4.2 GROUP: Defining Groups of Segments

The obj format also allows segments to be grouped, so that a single segment register can be used to refer to all the segments in a group. NASM therefore supplies the GROUP directive, whereby you can code

```
segment data
    ; some data

segment bss
    ; some uninitialized data
```

```
group dgroup data bss
```

which will define a group called dgroup to contain the segments data and bss. Like SEGMENT, GROUP causes the group name to be defined as a symbol, so that you can refer to a variable var in the data segment as var wrt data or as var wrt dgroup, depending on which segment value is currently in your segment register.

If you just refer to var, however, and var is declared in a segment which is part of a group, then NASM will default to giving you the offset of var from the beginning of the *group*, not the *segment*. Therefore SEG var, also, will return the group base rather than the segment base.

NASM will allow a segment to be part of more than one group, but will generate a warning if you do this. Variables declared in a segment which is part of more than one group will default to being relative to the first group that was defined to contain the segment.

A group does not have to contain any segments; you can still make WRT references to a group which does not contain the variable you are referring to. OS/2, for example, defines the special group FLAT with no segments in it.

8.4.3 UPPERCASE: Disabling Case Sensitivity in Output

Although NASM itself is case sensitive, some OMF linkers are not; therefore it can be useful for NASM to output single-case object files. The UPPERCASE format-specific directive causes all segment, group and symbol names that are written to the object file to be forced to upper case just before being written. Within a source file, NASM is still case-sensitive; but the object file can be written entirely in upper case if desired.

UPPERCASE is used alone on a line; it requires no parameters.

8.4.4 IMPORT: Importing DLL Symbols

The IMPORT format-specific directive defines a symbol to be imported from a DLL, for use if you are writing a DLL's import library in NASM. You still need to declare the symbol as EXTERN as well as using the IMPORT directive.

The IMPORT directive takes two required parameters, separated by white space, which are (respectively) the name of the symbol you wish to import and the name of the library you wish to import it from. For example:

```
import WSASStartup wsock32.dll
```

A third optional parameter gives the name by which the symbol is known in the library you are importing it from, in case this is not the same as the name you wish the symbol to be known by to your code once you have imported it. For example:

```
import asyncsel wsock32.dll WSAAsyncSelect
```

8.4.5 EXPORT: Exporting DLL Symbols

The EXPORT format-specific directive defines a global symbol to be exported as a DLL symbol, for use if you are writing a DLL in NASM. You still need to declare the symbol as GLOBAL as well as using the EXPORT directive.

EXPORT takes one required parameter, which is the name of the symbol you wish to export, as it was defined in your source file. An optional second parameter (separated by white space from the first) gives the *external* name of the symbol: the name by which you wish the symbol to be known to programs using the DLL. If this name is the same as the internal name, you may leave the second parameter off.

Further parameters can be given to define attributes of the exported symbol. These parameters, like the second, are separated by white space. If further parameters are given, the external name must also be specified, even if it is the same as the internal name. The available attributes are:

- `resident` indicates that the exported name is to be kept resident by the system loader. This is an optimisation for frequently used symbols imported by name.
- `nodata` indicates that the exported symbol is a function which does not make use of any initialized data.
- `parm=NNN`, where NNN is an integer, sets the number of parameter words for the case in which the symbol is a call gate between 32-bit and 16-bit segments.
- An attribute which is just a number indicates that the symbol should be exported with an identifying number (ordinal), and gives the desired number.

For example:

```

export myfunc
export myfunc TheRealMoreFormalLookingFunctionName
export myfunc myfunc 1234 ; export by ordinal
export myfunc myfunc resident parm=23 nodata

```

8.4.6 `..start`: Defining the Program Entry Point

OMF linkers require exactly one of the object files being linked to define the program entry point, where execution will begin when the program is run. If the object file that defines the entry point is assembled using NASM, you specify the entry point by declaring the special symbol `..start` at the point where you wish execution to begin.

8.4.7 `obj` Extensions to the `EXTERN` Directive

If you declare an external symbol with the directive

```
extern foo
```

then references such as `mov ax,foo` will give you the offset of `foo` from its preferred segment base (as specified in whichever module `foo` is actually defined in). So to access the contents of `foo` you will usually need to do something like

```

mov    ax,seg foo      ; get preferred segment base
mov    es,ax           ; move it into ES
mov    ax,[es:foo]     ; and use offset 'foo' from it

```

This is a little unwieldy, particularly if you know that an external is going to be accessible from a given segment or group, say `dgroup`. So if `DS` already contained `dgroup`, you could simply code

```
mov    ax,[foo wrt dgroup]
```

However, having to type this every time you want to access `foo` can be a pain; so NASM allows you to declare `foo` in the alternative form

```
extern foo:wrt dgroup
```

This form causes NASM to pretend that the preferred segment base of `foo` is in fact `dgroup`; so the expression `seg foo` will now return `dgroup`, and the expression `foo` is equivalent to `foo wrt dgroup`.

This default-WRT mechanism can be used to make externals appear to be relative to any group or segment in your program. It can also be applied to common variables: see section 8.4.8.

8.4.8 `obj` Extensions to the `COMMON` Directive

The `obj` format allows common variables to be either near or far; NASM allows you to specify which your variables should be by the use of the syntax

```

common nearvar 2:near ; 'nearvar' is a near common
common farvar 10:far  ; and 'farvar' is far

```

Far common variables may be greater in size than 64Kb, and so the OMF specification says that they are declared as a number of *elements* of a given size. So a 10-byte far common variable could be declared as ten one-byte elements, five two-byte elements, two five-byte elements or one ten-byte element.

Some OMF linkers require the element size, as well as the variable size, to match when resolving common variables declared in more than one module. Therefore NASM must allow you to specify the element size on your far common variables. This is done by the following syntax:

```

common c_5by2 10:far 5 ; two five-byte elements
common c_2by5 10:far 2 ; five two-byte elements

```

If no element size is specified, the default is 1. Also, the FAR keyword is not required when an element size is specified, since only far commons may have element sizes at all. So the above declarations could equivalently be

```
common c_5by2 10:5           ; two five-byte elements
common c_2by5 10:2           ; five two-byte elements
```

In addition to these extensions, the COMMON directive in obj also supports default-WRT specification like EXTERN does (explained in section 8.4.7). So you can also declare things like

```
common foo      10:wrt dgroup
common bar      16:far 2:wrt data
common baz      24:wrt data:6
```

8.4.9 Embedded File Dependency Information

Since NASM 2.13.02, obj files contain embedded dependency file information. To suppress the generation of dependencies, use

```
%pragma obj nodepend
```

8.5 win32: Microsoft Win32 Object Files

The win32 output format generates Microsoft Win32 object files, suitable for passing to Microsoft linkers such as Visual C++. Note that Borland Win32 compilers do not use this format, but use obj instead (see section 8.4).

win32 provides a default output file-name extension of .obj.

Note that although Microsoft say that Win32 object files follow the COFF (Common Object File Format) standard, the object files produced by Microsoft Win32 compilers are not compatible with COFF linkers such as DJGPP's, and vice versa. This is due to a difference of opinion over the precise semantics of PC-relative relocations. To produce COFF files suitable for DJGPP, use NASM's coff output format; conversely, the coff format does not produce object files that Win32 linkers can generate correct output from.

8.5.1 win32 Extensions to the SECTION Directive

Like the obj format, win32 allows you to specify additional information on the SECTION directive line, to control the type and properties of sections you declare. Section types and properties are generated automatically by NASM for the standard section names .text, .data and .bss, but may still be overridden by these qualifiers.

The available qualifiers are:

- `code`, or equivalently `text`, defines the section to be a code section. This marks the section as readable and executable, but not writable, and also indicates to the linker that the type of the section is code.
- `data` and `bss` define the section to be a data section, analogously to code. Data sections are marked as readable and writable, but not executable. `data` declares an initialized data section, whereas `bss` declares an uninitialized data section.
- `rdata` declares an initialized data section that is readable but not writable. Microsoft compilers use this section to place constants in it.
- `info` defines the section to be an informational section, which is not included in the executable file by the linker, but may (for example) pass information to the linker. For example, declaring an `info`-type section called `.directive` causes the linker to interpret the contents of the section as command-line options.

- `align=`, used with a trailing number as in `obj`, gives the alignment requirements of the section. The maximum you may specify is 64: the Win32 object file format contains no means to request a greater section alignment than this. If alignment is not explicitly specified, the defaults are 16-byte alignment for code sections, 8-byte alignment for rdata sections and 4-byte alignment for data (and BSS) sections. Informational sections get a default alignment of 1 byte (no alignment), though the value does not matter.

The defaults assumed by NASM if you do not specify the above qualifiers are:

```
section .text    code    align=16
section .data    data    align=4
section .rdata   rdata   align=8
section .bss     bss     align=4
```

Any other section name is treated by default like `.text`.

8.5.2 win32: Safe Structured Exception Handling

Among other improvements in Windows XP SP2 and Windows Server 2003 Microsoft has introduced concept of "safe structured exception handling." General idea is to collect handlers' entry points in designated read-only table and have alleged entry point verified against this table prior exception control is passed to the handler. In order for an executable module to be equipped with such "safe exception handler table," all object modules on linker command line has to comply with certain criteria. If one single module among them does not, then the table in question is omitted and above mentioned run-time checks will not be performed for application in question. Table omission is by default silent and therefore can be easily overlooked. One can instruct linker to refuse to produce binary without such table by passing `/safeseh` command line option.

Without regard to this run-time check merits it's natural to expect NASM to be capable of generating modules suitable for `/safeseh` linking. From developer's viewpoint the problem is two-fold:

- how to adapt modules not deploying exception handlers of their own;
- how to adapt/develop modules utilizing custom exception handling;

Former can be easily achieved with any NASM version by adding following line to source code:

```
$@feat.00 equ 1
```

As of version 2.03 NASM adds this absolute symbol automatically. If it's not already present to be precise. I.e. if for whatever reason developer would choose to assign another value in source file, it would still be perfectly possible.

Registering custom exception handler on the other hand requires certain "magic." As of version 2.03 additional directive is implemented, `safeseh`, which instructs the assembler to produce appropriately formatted input data for above mentioned "safe exception handler table." Its typical use would be:

```
section .text
extern _MessageBoxA@16
%if    __?NASM_VERSION_ID?__ >= 0x02030000
safeseh handler          ; register handler as "safe handler"
%endif
handler:
    push    DWORD 1 ; MB_OKCANCEL
    push    DWORD caption
    push    DWORD text
    push    DWORD 0
    call    _MessageBoxA@16
    sub     eax,1    ; incidentally suits as return value
```



```

                                ; for exception handler
                                ret
global _main
_main:
    push    DWORD handler
    push    DWORD [fs:0]
    mov     DWORD [fs:0],esp ; engage exception handler
    xor     eax,eax
    mov     eax,DWORD[eax]   ; cause exception
    pop     DWORD [fs:0]     ; disengage exception handler
    add     esp,4
    ret
text: db 'OK to rethrow, CANCEL to generate core dump',0
caption:db 'SEGV',0

section .drectve info
    db     '/defaultlib:user32.lib /defaultlib:msvcrt.lib '

```

As you might imagine, it's perfectly possible to produce .exe binary with "safe exception handler table" and yet engage unregistered exception handler. Indeed, handler is engaged by simply manipulating [fs:0] location at run-time, something linker has no power over, run-time that is. It should be explicitly mentioned that such failure to register handler's entry point with safeseh directive has undesired side effect at run-time. If exception is raised and unregistered handler is to be executed, the application is abruptly terminated without any notification whatsoever. One can argue that system could at least have logged some kind "non-safe exception handler in x.exe at address n" message in event log, but no, literally no notification is provided and user is left with no clue on what caused application failure.

Finally, all mentions of linker in this paragraph refer to Microsoft linker version 7.x and later. Presence of @feat.00 symbol and input data for "safe exception handler table" causes no backward incompatibilities and "safeseh" modules generated by NASM 2.03 and later can still be linked by earlier versions or non-Microsoft linkers.

8.5.3 Debugging formats for Windows

The win32 and win64 formats support the Microsoft CodeView debugging format. Currently CodeView version 8 format is supported (cv8), but newer versions of the CodeView debugger should be able to handle this format as well.

8.6 win64: Microsoft Win64 Object Files

The win64 output format generates Microsoft Win64 object files, which is nearly 100% identical to the win32 object format (section 8.5) with the exception that it is meant to target 64-bit code and the x86-64 platform altogether. This object file is used exactly the same as the win32 object format (section 8.5), in NASM, with regard to this exception.

8.6.1 win64: Writing Position-Independent Code

While REL takes good care of RIP-relative addressing, there is one aspect that is easy to overlook for a Win64 programmer: indirect references. Consider a switch dispatch table:

```

    jmp     qword [dsptch+rax*8]
    ...
dsptch: dq   case0
        dq   case1
    ...

```

Even a novice Win64 assembler programmer will soon realize that the code is not 64-bit savvy. Most notably linker will refuse to link it with

'ADDR32' relocation to '.text' invalid without /LARGEADDRESSAWARE:NO

So [s]he will have to split jmp instruction as following:

```
lea    rbx,[rel dsptch]
jmp    qword [rbx+rax*8]
```

What happens behind the scene is that effective address in lea is encoded relative to instruction pointer, or in perfectly position-independent manner. But this is only part of the problem! Trouble is that in .dll context caseN relocations will make their way to the final module and might have to be adjusted at .dll load time. To be specific when it can't be loaded at preferred address. And when this occurs, pages with such relocations will be rendered private to current process, which kind of undermines the idea of sharing .dll. But no worry, it's trivial to fix:

```
lea    rbx,[rel dsptch]
add    rbx,[rbx+rax*8]
jmp    rbx
...
dsptch: dq    case0-dsptch
        dq    case1-dsptch
        ...
```

NASM version 2.03 and later provides another alternative, wrt ..imagebase operator, which returns offset from base address of the current image, be it .exe or .dll module, therefore the name. For those acquainted with PE-COFF format base address denotes start of IMAGE_DOS_HEADER structure. Here is how to implement switch with these image-relative references:

```
lea    rbx,[rel dsptch]
mov    eax,[rbx+rax*4]
sub    rbx,dsptch wrt ..imagebase
add    rbx,rax
jmp    rbx
...
dsptch: dd    case0 wrt ..imagebase
        dd    case1 wrt ..imagebase
```

One can argue that the operator is redundant. Indeed, snippet before last works just fine with any NASM version and is not even Windows specific... The real reason for implementing wrt ..imagebase will become apparent in next paragraph.

It should be noted that wrt ..imagebase is defined as 32-bit operand only:

```
dd    label wrt ..imagebase        ; ok
dq    label wrt ..imagebase        ; bad
mov    eax,label wrt ..imagebase    ; ok
mov    rax,label wrt ..imagebase    ; bad
```

8.6.2 win64: Structured Exception Handling

Structured exception handling in Win64 is completely different matter from Win32. Upon exception program counter value is noted, and linker-generated table comprising start and end addresses of all the functions [in given executable module] is traversed and compared to the saved program counter. Thus so called UNWIND_INFO structure is identified. If it's not found, then offending subroutine is assumed to be "leaf" and just mentioned lookup procedure is attempted for its caller. In Win64 leaf function is such function that does not call any other function *nor* modifies any Win64 non-volatile

registers, including stack pointer. The latter ensures that it's possible to identify leaf function's caller by simply pulling the value from the top of the stack.

While majority of subroutines written in assembler are not calling any other function, requirement for non-volatile registers' immutability leaves developer with not more than 7 registers and no stack frame, which is not necessarily what [s]he counted with. Customarily one would meet the requirement by saving non-volatile registers on stack and restoring them upon return, so what can go wrong? If [and only if] an exception is raised at run-time and no UNWIND_INFO structure is associated with such "leaf" function, the stack unwind procedure will expect to find caller's return address on the top of stack immediately followed by its frame. Given that developer pushed caller's non-volatile registers on stack, would the value on top point at some code segment or even addressable space? Well, developer can attempt copying caller's return address to the top of stack and this would actually work in some very specific circumstances. But unless developer can guarantee that these circumstances are always met, it's more appropriate to assume worst case scenario, i.e. stack unwind procedure going berserk. Relevant question is what happens then? Application is abruptly terminated without any notification whatsoever. Just like in Win32 case, one can argue that system could at least have logged "unwind procedure went berserk in x.exe at address n" in event log, but no, no trace of failure is left.

Now, when we understand significance of the UNWIND_INFO structure, let's discuss what's in it and/or how it's processed. First of all it is checked for presence of reference to custom language-specific exception handler. If there is one, then it's invoked. Depending on the return value, execution flow is resumed (exception is said to be "handled"), or rest of UNWIND_INFO structure is processed as following. Beside optional reference to custom handler, it carries information about current callee's stack frame and where non-volatile registers are saved. Information is detailed enough to be able to reconstruct contents of caller's non-volatile registers upon call to current callee. And so caller's context is reconstructed, and then unwind procedure is repeated, i.e. another UNWIND_INFO structure is associated, this time, with caller's instruction pointer, which is then checked for presence of reference to language-specific handler, etc. The procedure is recursively repeated till exception is handled. As last resort system "handles" it by generating memory core dump and terminating the application.

As for the moment of this writing NASM unfortunately does not facilitate generation of above mentioned detailed information about stack frame layout. But as of version 2.03 it implements building blocks for generating structures involved in stack unwinding. As simplest example, here is how to deploy custom exception handler for leaf function:

```
default rel
section .text
extern MessageBoxA
handler:
    sub     rsp,40
    mov     rcx,0
    lea     rdx,[text]
    lea     r8,[caption]
    mov     r9,1      ; MB_OKCANCEL
    call    MessageBoxA
    sub     eax,1     ; incidentally suits as return value
                    ; for exception handler
    add     rsp,40
    ret
global main
main:
    xor     rax,rax
    mov     rax,QWORD[rax] ; cause exception
    ret
main_end:
text: db     'OK to rethrow, CANCEL to generate core dump',0
```

```

caption:db      'SEGV',0

section .pdata  rdata align=4
               dd      main wrt  ..imagebase
               dd      main_end wrt ..imagebase
               dd      xmain wrt  ..imagebase
section .xdata  rdata align=8
xmain:  db      9,0,0,0
               dd      handler wrt ..imagebase
section .drectve info
               db      '/defaultlib:user32.lib /defaultlib:msvcrt.lib '

```

What you see in `.pdata` section is element of the "table comprising start and end addresses of function" along with reference to associated `UNWIND_INFO` structure. And what you see in `.xdata` section is `UNWIND_INFO` structure describing function with no frame, but with designated exception handler. References are *required* to be image-relative (which is the real reason for implementing `wrt ..imagebase` operator). It should be noted that `rdata align=n`, as well as `wrt ..imagebase`, are optional in these two segments' contexts, i.e. can be omitted. Latter means that *all* 32-bit references, not only above listed required ones, placed into these two segments turn out image-relative. Why is it important to understand? Developer is allowed to append handler-specific data to `UNWIND_INFO` structure, and if [s]he adds a 32-bit reference, then [s]he will have to remember to adjust its value to obtain the real pointer.

As already mentioned, in Win64 terms leaf function is one that does not call any other function *nor* modifies any non-volatile register, including stack pointer. But it's not uncommon that assembler programmer plans to utilize every single register and sometimes even have variable stack frame. Is there anything one can do with bare building blocks? I.e. besides manually composing fully-fledged `UNWIND_INFO` structure, which would surely be considered error-prone? Yes, there is. Recall that exception handler is called first, before stack layout is analyzed. As it turned out, it's perfectly possible to manipulate current callee's context in custom handler in manner that permits further stack unwinding. General idea is that handler would not actually "handle" the exception, but instead restore callee's context, as it was at its entry point and thus mimic leaf function. In other words, handler would simply undertake part of unwinding procedure. Consider following example:

```

function:
    mov     rax, rsp           ; copy rsp to volatile register
    push   r15                ; save non-volatile registers
    push   rbx
    push   rbp
    mov    r11, rsp           ; prepare variable stack frame
    sub   r11, rcx
    and   r11, -64
    mov   QWORD[r11], rax    ; check for exceptions
    mov   rsp, r11           ; allocate stack frame
    mov   QWORD[rsp], rax    ; save original rsp value
magic_point:
    ...
    mov   r11, QWORD[rsp]    ; pull original rsp value
    mov   rbp, QWORD[r11-24]
    mov   rbx, QWORD[r11-16]
    mov   r15, QWORD[r11-8]
    mov   rsp, r11          ; destroy frame
    ret

```

The keyword is that up to `magic_point` original `rsp` value remains in chosen volatile register and no non-volatile register, except for `rsp`, is modified. While past `magic_point` `rsp` remains constant till

the very end of the function. In this case custom language-specific exception handler would look like this:

```
EXCEPTION_DISPOSITION handler (EXCEPTION_RECORD *rec,ULONG64 frame,
                               CONTEXT *context,DISPATCHER_CONTEXT *disp)
{
    ULONG64 *rsp;
    if (context->Rip<(ULONG64)magic_point)
        rsp = (ULONG64 *)context->Rax;
    else
    {
        rsp = ((ULONG64 **)context->Rsp)[0];
        context->Rbp = rsp[-3];
        context->Rbx = rsp[-2];
        context->R15 = rsp[-1];
    }
    context->Rsp = (ULONG64)rsp;

    memcpy (disp->ContextRecord,context,sizeof(CONTEXT));
    RtlVirtualUnwind(UNW_FLAG_NHANDLER,disp->ImageBase,
                    dips->ControlPc,disp->FunctionEntry,disp->ContextRecord,
                    &disp->HandlerData,&disp->EstablisherFrame,NULL);
    return ExceptionContinueSearch;
}
```

As custom handler mimics leaf function, corresponding UNWIND_INFO structure does not have to contain any information about stack frame and its layout.

8.7 coff: Common Object File Format

The `coff` output type produces COFF object files suitable for linking with the DJGPP linker.

`coff` provides a default output file-name extension of `.o`.

The `coff` format supports the same extensions to the `SECTION` directive as `win32` does, except that the `align` qualifier and the `info` section type are not supported.

8.8 macho32 and macho64: Mach Object File Format

The `macho32` and `macho64` output formats produce Mach-O object files suitable for linking with the MacOS X linker. `macho` is a synonym for `macho32`.

`macho` provides a default output file-name extension of `.o`.

8.8.1 macho extensions to the SECTION Directive

The `macho` output format specifies section names in the format "`segment,section`". No spaces are allowed around the comma. The following flags can also be specified:

- `data` – this section contains initialized data items
- `code` – this section contains code exclusively
- `mixed` – this section contains both code and data
- `bss` – this section is uninitialized and filled with zero
- `zerofill` – same as `bss`
- `no_dead_strip` – inhibit dead code stripping for this section
- `live_support` – set the live support flag for this section
- `strip_static_syms` – strip static symbols for this section

- `debug` – this section contains debugging information
- `align=alignment` – specify section alignment

The default is `data`, unless the section name is `__text` or `__bss` in which case the default is `text` or `bss`, respectively.

For compatibility with other Unix platforms, the following standard names are also supported:

```
.text    = __TEXT,__text  text
.rodata  = __DATA,__const data
.data    = __DATA,__data  data
.bss     = __DATA,__bss   bss
```

If the `.rodata` section contains no relocations, it is instead put into the `__TEXT,__const` section unless this section has already been specified explicitly. However, it is probably better to specify `__TEXT,__const` and `__DATA,__const` explicitly as appropriate.

8.8.2 Thread Local Storage in Mach-O: macho special symbols and WRT

Mach-O defines the following special symbols that can be used on the right-hand side of the WRT operator:

- `..tlvp` is used to specify access to thread-local storage.
- `..gotpcrel` is used to specify references to the Global Offset Table. The GOT is supported in the macho64 format only.

8.8.3 macho specific directive subsections_via_symbols

The directive `subsections_via_symbols` sets the `MH_SUBSECTIONS_VIA_SYMBOLS` flag in the Mach-O header, that effectively separates a block (or a subsection) based on a symbol. It is often used for eliminating dead codes by a linker.

This directive takes no arguments.

This is a macro implemented as a `%pragma`. It can also be specified in its `%pragma` form, in which case it will not affect non-Mach-O builds of the same source code:

```
%pragma macho subsections_via_symbols
```

8.8.4 macho specific directive no_dead_strip

The directive `no_dead_strip` sets the Mach-O `SH_NO_DEAD_STRIP` section flag on the section containing a specific symbol. This directive takes a list of symbols as its arguments.

This is a macro implemented as a `%pragma`. It can also be specified in its `%pragma` form, in which case it will not affect non-Mach-O builds of the same source code:

```
%pragma macho no_dead_strip symbol...
```

8.8.5 macho specific extensions to the GLOBAL Directive: private_extern

The directive extension to `GLOBAL` marks the symbol with limited global scope. For example, you can specify the global symbol with this extension:

```
global foo:private_extern
foo:
    ; codes
```

Using with static linker will clear the `private_extern` attribute. But linker option like `-keep_private_externs` can avoid it.

8.9 elf32, elf64, elfx32: Executable and Linkable Format Object Files

The elf32, elf64 and elfx32 output formats generate ELF32 and ELF64 (Executable and Linkable Format) object files, as used by Linux as well as Unix System V, including Solaris x86, UnixWare and SCO Unix. ELF provides a default output file-name extension of .o. elf is a synonym for elf32.

The elfx32 format is used for the x32 ABI, which is a 32-bit ABI with the CPU in 64-bit mode.

8.9.1 ELF specific directive osabi

The ELF header specifies the application binary interface for the target operating system (OSABI). This field can be set by using the osabi directive with the numeric value (0-255) of the target system. If this directive is not used, the default value will be "UNIX System V ABI" (0) which will work on most systems which support ELF.

8.9.2 ELF extensions to the SECTION Directive

Like the obj format, elf allows you to specify additional information on the SECTION directive line, to control the type and properties of sections you declare. Section types and properties are generated automatically by NASM for the standard section names, but may still be overridden by these qualifiers.

The available qualifiers are:

- `alloc` defines the section to be one which is loaded into memory when the program is run. `noalloc` defines it to be one which is not, such as an informational or comment section.
- `exec` defines the section to be one which should have execute permission when the program is run. `noexec` defines it as one which should not.
- `write` defines the section to be one which should be writable when the program is run. `nowrite` defines it as one which should not.
- `progbits` defines the section to be one with explicit contents stored in the object file: an ordinary code or data section, for example.
- `nobits` defines the section to be one with no explicit contents given, such as a BSS section.
- `note` indicates that this section contains ELF notes. The content of ELF notes are specified using normal assembly instructions; it is up to the programmer to ensure these are valid ELF notes.
- `preinit_array` indicates that this section contains function addresses to be called before any other initialization has happened.
- `init_array` indicates that this section contains function addresses to be called during initialization.
- `fini_array` indicates that this section contains function pointers to be called during termination.
- `align=`, used with a trailing number as in obj, gives the alignment requirements of the section.
- `byte`, `word`, `dword`, `qword`, `tword`, `oword`, `yword`, or `zword` with an optional *multiplier specify the fundamental data item size for a section which contains either fixed-sized data structures or strings; it also sets a default alignment. This is generally used with the `strings` and `merge` attributes (see below.) For example `byte*4` defines a unit size of 4 bytes, with a default alignment of 1; `dword` also defines a unit size of 4 bytes, but with a default alignment of 4. The `align=` attribute, if specified, overrides this default alignment.
- `pointer` is equivalent to `dword` for elf32 or elfx32, and `qword` for elf64.
- `strings` indicate that this section contains exclusively null-terminated strings. By default these are assumed to be byte strings, but a size specifier can be used to override that.

- `merge` indicates that duplicate data elements in this section should be merged with data elements from other object files. Data elements can be either fixed-sized objects or null-terminated strings (with the `strings` attribute.) A size specifier is required unless `strings` is specified, in which case the size defaults to byte.
- `tls` defines the section to be one which contains thread local variables.

The defaults assumed by NASM if you do not specify the above qualifiers are:

section <code>.text</code>	<code>progbits</code>	<code>alloc</code>	<code>exec</code>	<code>nowrite</code>	<code>align=16</code>	
section <code>.rodata</code>	<code>progbits</code>	<code>alloc</code>	<code>noexec</code>	<code>nowrite</code>	<code>align=4</code>	
section <code>.lrodata</code>	<code>progbits</code>	<code>alloc</code>	<code>noexec</code>	<code>nowrite</code>	<code>align=4</code>	
section <code>.data</code>	<code>progbits</code>	<code>alloc</code>	<code>noexec</code>	<code>write</code>	<code>align=4</code>	
section <code>.ldata</code>	<code>progbits</code>	<code>alloc</code>	<code>noexec</code>	<code>write</code>	<code>align=4</code>	
section <code>.bss</code>	<code>nobits</code>	<code>alloc</code>	<code>noexec</code>	<code>write</code>	<code>align=4</code>	
section <code>.lbss</code>	<code>nobits</code>	<code>alloc</code>	<code>noexec</code>	<code>write</code>	<code>align=4</code>	
section <code>.tdata</code>	<code>progbits</code>	<code>alloc</code>	<code>noexec</code>	<code>write</code>	<code>align=4</code>	<code>tls</code>
section <code>.tbss</code>	<code>nobits</code>	<code>alloc</code>	<code>noexec</code>	<code>write</code>	<code>align=4</code>	<code>tls</code>
section <code>.comment</code>	<code>progbits</code>	<code>noalloc</code>	<code>noexec</code>	<code>nowrite</code>	<code>align=1</code>	
section <code>.preinit_array</code>	<code>preinit_array</code>	<code>alloc</code>	<code>noexec</code>	<code>nowrite</code>	<code>pointer</code>	
section <code>.init_array</code>	<code>init_array</code>	<code>alloc</code>	<code>noexec</code>	<code>nowrite</code>	<code>pointer</code>	
section <code>.fini_array</code>	<code>fini_array</code>	<code>alloc</code>	<code>noexec</code>	<code>nowrite</code>	<code>pointer</code>	
section <code>.note</code>	<code>note</code>	<code>noalloc</code>	<code>noexec</code>	<code>nowrite</code>	<code>align=4</code>	
section <code>other</code>	<code>progbits</code>	<code>alloc</code>	<code>noexec</code>	<code>nowrite</code>	<code>align=1</code>	

(Any section name other than those in the above table is treated by default like `other` in the above table. Please note that section names are case sensitive.)

8.9.3 Position-Independent Code: ELF Special Symbols and WRT

Since ELF does not support segment-base references, the `WRT` operator is not used for its normal purpose; therefore NASM's `elf` output format makes use of `WRT` for a different purpose, namely the PIC-specific relocation types.

`elf` defines five special symbols which you can use as the right-hand side of the `WRT` operator to obtain PIC relocation types. They are `..gotpc`, `..gotoff`, `..got`, `..plt` and `..sym`. Their functions are summarized here:

- Referring to the symbol marking the global offset table base using `wrt ..gotpc` will end up giving the distance from the beginning of the current section to the global offset table. (`_GLOBAL_OFFSET_TABLE_` is the standard symbol name used to refer to the GOT.) So you would then need to add `$$` to the result to get the real address of the GOT.
- Referring to a location in one of your own sections using `wrt ..gotoff` will give the distance from the beginning of the GOT to the specified location, so that adding on the address of the GOT would give the real address of the location you wanted.
- Referring to an external or global symbol using `wrt ..got` causes the linker to build an entry *in* the GOT containing the address of the symbol, and the reference gives the distance from the beginning of the GOT to the entry; so you can add on the address of the GOT, load from the resulting address, and end up with the address of the symbol.
- Referring to a procedure name using `wrt ..plt` causes the linker to build a procedure linkage table entry for the symbol, and the reference gives the address of the PLT entry. You can only use this in contexts which would generate a PC-relative relocation normally (i.e. as the destination for `CALL` or `JMP`), since ELF contains no relocation type to refer to PLT entries absolutely.

- Referring to a symbol name using `wrt ..sym` causes NASM to write an ordinary relocation, but instead of making the relocation relative to the start of the section and then adding on the offset to the symbol, it will write a relocation record aimed directly at the symbol in question. The distinction is a necessary one due to a peculiarity of the dynamic linker.

A fuller explanation of how to use these relocation types to write shared libraries entirely in NASM is given in section 10.2.

8.9.4 Thread Local Storage in ELF: `elf` Special Symbols and `WRT`

- In ELF32 mode, referring to an external or global symbol using `wrt ..tlsie` causes the linker to build an entry *in* the GOT containing the offset of the symbol within the TLS block, so you can access the value of the symbol with code such as:

```
mov  eax,[tid wrt ..tlsie]
mov  [gs:eax],ebx
```

- In ELF64 or ELF32 mode, referring to an external or global symbol using `wrt ..gottpoff` causes the linker to build an entry *in* the GOT containing the offset of the symbol within the TLS block, so you can access the value of the symbol with code such as:

```
mov  rax,[rel tid wrt ..gottpoff]
mov  rcx,[fs:rax]
```

8.9.5 `elf` Extensions to the `GLOBAL` Directive

ELF object files can contain more information about a global symbol than just its address: they can contain the size of the symbol and its type as well. These are not merely debugger conveniences, but are actually necessary when the program being written is a shared library. NASM therefore supports some extensions to the `GLOBAL` directive, allowing you to specify these features.

You can specify whether a global variable is a function or a data object by suffixing the name with a colon and the word `function` or `data`. (`object` is a synonym for `data`.) For example:

```
global  hashlookup:function, hashtable:data
```

exports the global symbol `hashlookup` as a function and `hashtable` as a data object.

Optionally, you can control the ELF visibility of the symbol. Just add one of the visibility keywords: `default`, `internal`, `hidden`, or `protected`. The default is `default` of course. For example, to make `hashlookup` `hidden`:

```
global  hashlookup:function hidden
```

Since version 2.15, it is possible to specify symbols binding. The keywords are: `weak` to generate weak symbol or `strong`. The default is `strong`.

You can also specify the size of the data associated with the symbol, as a numeric expression (which may involve labels, and even forward references) after the type specifier. Like this:

```
global  hashtable:data (hashtable.end - hashtable)
```

```
hashtable:
    db this,that,theother ; some data here
.end:
```

This makes NASM automatically calculate the length of the table and place that information into the ELF symbol table.

Declaring the type and size of global symbols is necessary when writing shared library code. For more information, see section 10.2.4.

8.9.6 `elf` Extensions to the `EXTERN` Directive

Since version 2.15 it is possible to specify keyword `weak` to generate weak external reference. Example:

```
extern weak_ref:weak
```

8.9.7 `elf` Extensions to the `COMMON` Directive

ELF also allows you to specify alignment requirements on common variables. This is done by putting a number (which must be a power of two) after the name and size of the common variable, separated (as usual) by a colon. For example, an array of doublewords would benefit from 4-byte alignment:

```
common dwordarray 128:4
```

This declares the total size of the array to be 128 bytes, and requires that it be aligned on a 4-byte boundary.

8.9.8 16-bit code and ELF

Older versions of the ELF32 specification did not provide relocations for 8- and 16-bit values. It is now part of the formal specification, and any new enough linker should support them.

ELF has currently no support for segmented programming.

8.9.9 Debug formats and ELF

ELF provides debug information in STABS and DWARF formats. Line number information is generated for all executable sections, but please note that only the `.text` section is executable by default.

8.10 `aout`: Linux `a.out` Object Files

The `aout` format generates `a.out` object files, in the form used by early Linux systems (current Linux systems use ELF, see section 8.9.) These differ from other `a.out` object files in that the magic number in the first four bytes of the file is different; also, some implementations of `a.out`, for example NetBSD's, support position-independent code, which Linux's implementation does not.

`a.out` provides a default output file-name extension of `.o`.

`a.out` is a very simple object format. It supports no special directives, no special symbols, no use of `SEG` or `WRT`, and no extensions to any standard directives. It supports only the three standard section names `.text`, `.data` and `.bss`.

8.11 `aoutb`: NetBSD/FreeBSD/OpenBSD `a.out` Object Files

The `aoutb` format generates `a.out` object files, in the form used by the various free BSD Unix clones, NetBSD, FreeBSD and OpenBSD. For simple object files, this object format is exactly the same as `aout` except for the magic number in the first four bytes of the file. However, the `aoutb` format supports position-independent code in the same way as the `elf` format, so you can use it to write BSD shared libraries.

`aoutb` provides a default output file-name extension of `.o`.

`aoutb` supports no special directives, no special symbols, and only the three standard section names `.text`, `.data` and `.bss`. However, it also supports the same use of `WRT` as `elf` does, to provide position-independent code relocation types. See section 8.9.3 for full documentation of this feature.

`aoutb` also supports the same extensions to the `GLOBAL` directive as `elf` does: see section 8.9.5 for documentation of this.

8.12 as86: Minix/Linux as86 Object Files

The Minix/Linux 16-bit assembler `as86` has its own non-standard object file format. Although its companion linker `ld86` produces something close to ordinary `a.out` binaries as output, the object file format used to communicate between `as86` and `ld86` is not itself `a.out`.

NASM supports this format, just in case it is useful, as `as86`. `as86` provides a default output file-name extension of `.o`.

`as86` is a very simple object format (from the NASM user's point of view). It supports no special directives, no use of `SEG` or `WRT`, and no extensions to any standard directives. It supports only the three standard section names `.text`, `.data` and `.bss`. The only special symbol supported is `..start`.

8.13 rdf: Relocatable Dynamic Object File Format

The `rdf` output format produces RDOFF object files. RDOFF (Relocatable Dynamic Object File Format) is a home-grown object-file format, designed alongside NASM itself and reflecting in its file format the internal structure of the assembler.

RDOFF is not used by any well-known operating systems. Those writing their own systems, however, may well wish to use RDOFF as their object format, on the grounds that it is designed primarily for simplicity and contains very little file-header bureaucracy.

The Unix NASM archive, and the DOS archive which includes sources, both contain an `rdoff` subdirectory holding a set of RDOFF utilities: an RDF linker, an RDF static-library manager, an RDF file dump utility, and a program which will load and execute an RDF executable under Linux.

`rdf` supports only the standard section names `.text`, `.data` and `.bss`.

8.13.1 Requiring a Library: The LIBRARY Directive

RDOFF contains a mechanism for an object file to demand a given library to be linked to the module, either at load time or run time. This is done by the `LIBRARY` directive, which takes one argument which is the name of the module:

```
library mylib.rdl
```

8.13.2 Specifying a Module Name: The MODULE Directive

Special RDOFF header record is used to store the name of the module. It can be used, for example, by run-time loader to perform dynamic linking. `MODULE` directive takes one argument which is the name of current module:

```
module mymodname
```

Note that when you statically link modules and tell linker to strip the symbols from output file, all module names will be stripped too. To avoid it, you should start module names with `$`, like:

```
module $kernel.core
```

8.13.3 rdf Extensions to the GLOBAL Directive

RDOFF global symbols can contain additional information needed by the static linker. You can mark a global symbol as exported, thus telling the linker do not strip it from target executable or library file. Like in ELF, you can also specify whether an exported symbol is a procedure (function) or data object.

Suffixing the name with a colon and the word `export` you make the symbol exported:

```
global sys_open:export
```

To specify that exported symbol is a procedure (function), you add the word `proc` or `function` after declaration:

```
global sys_open:export proc
```

Similarly, to specify exported data object, add the word `data` or `object` to the directive:

```
global kernel_ticks:export data
```

8.13.4 `rdf` Extensions to the `EXTERN` Directive

By default the `EXTERN` directive in `RDOFF` declares a "pure external" symbol (i.e. the static linker will complain if such a symbol is not resolved). To declare an "imported" symbol, which must be resolved later during a dynamic linking phase, `RDOFF` offers an additional `import` modifier. As in `GLOBAL`, you can also specify whether an imported symbol is a procedure (function) or data object. For example:

```
library $libc
extern _open:import
extern _printf:import proc
extern _errno:import data
```

Here the directive `LIBRARY` is also included, which gives the dynamic linker a hint as to where to find requested symbols.

8.14 `dbg`: Debugging Format

The `dbg` format does not output an object file as such; instead, it outputs a text file which contains a complete list of all the transactions between the main body of `NASM` and the output-format back end module. It is primarily intended to aid people who want to write their own output drivers, so that they can get a clearer idea of the various requests the main program makes of the output driver, and in what order they happen.

For simple files, one can easily use the `dbg` format like this:

```
nasm -f dbg filename.asm
```

which will generate a diagnostic file called `filename.dbg`. However, this will not work well on files which were designed for a different object format, because each object format defines its own macros (usually user-level forms of directives), and those macros will not be defined in the `dbg` format. Therefore it can be useful to run `NASM` twice, in order to do the preprocessing with the native object format selected:

```
nasm -e -f rdf -o rdfprog.i rdfprog.asm
nasm -a -f dbg rdfprog.i
```

This preprocesses `rdfprog.asm` into `rdfprog.i`, keeping the `rdf` object format selected in order to make sure `RDF` special directives are converted into primitive form correctly. Then the preprocessed source is fed through the `dbg` format to generate the final diagnostic output.

This workaround will still typically not work for programs intended for `obj` format, because the `obj` `SEGMENT` and `GROUP` directives have side effects of defining the segment and group names as symbols; `dbg` will not do this, so the program will not assemble. You will have to work around that by defining the symbols yourself (using `EXTERN`, for example) if you really need to get a `dbg` trace of an `obj`-specific source file.

`dbg` accepts any section name and any directives at all, and logs them all to its output file.

`dbg` accepts and logs any `%pragma`, but the specific `%pragma`:

```
%pragma dbg maxdump <size>
```

where `<size>` is either a number or `unlimited`, can be used to control the maximum size for dumping the full contents of a `rawdata` output object.

Chapter 9: Writing 16-bit Code (DOS, Windows 3/3.1)

This chapter attempts to cover some of the common issues encountered when writing 16-bit code to run under MS-DOS or Windows 3.x. It covers how to link programs to produce .EXE or .COM files, how to write .SYS device drivers, and how to interface assembly language code with 16-bit C compilers and with Borland Pascal.

9.1 Producing .EXE Files

Any large program written under DOS needs to be built as a .EXE file: only .EXE files have the necessary internal structure required to span more than one 64K segment. Windows programs, also, have to be built as .EXE files, since Windows does not support the .COM format.

In general, you generate .EXE files by using the obj output format to produce one or more .OBJ files, and then linking them together using a linker. However, NASM also supports the direct generation of simple DOS .EXE files using the bin output format (by using DB and DW to construct the .EXE file header), and a macro package is supplied to do this. Thanks to Yann Guidon for contributing the code for this.

NASM may also support .EXE natively as another output format in future releases.

9.1.1 Using the obj Format To Generate .EXE Files

This section describes the usual method of generating .EXE files by linking .OBJ files together.

Most 16-bit programming language packages come with a suitable linker; if you have none of these, there is a free linker called VAL, available in LZH archive format from x2ftp.oulu.fi. An LZH archiver can be found at ftp.simtel.net. There is another 'free' linker (though this one doesn't come with sources) called FREELINK, available from www.pcorner.com. A third, `djlink`, written by DJ Delorie, is available at www.delorie.com. A fourth linker, ALINK, written by Anthony A.J. Williams, is available at alink.sourceforge.net.

When linking several .OBJ files into a .EXE file, you should ensure that exactly one of them has a start point defined (using the `..start` special symbol defined by the obj format: see section 8.4.6). If no module defines a start point, the linker will not know what value to give the entry-point field in the output file header; if more than one defines a start point, the linker will not know *which* value to use.

An example of a NASM source file which can be assembled to a .OBJ file and linked on its own to a .EXE is given here. It demonstrates the basic principles of defining a stack, initialising the segment registers, and declaring a start point. This file is also provided in the `test` subdirectory of the NASM archives, under the name `objexe.asm`.

```
segment code

..start:
    mov     ax,data
    mov     ds,ax
    mov     ax,stack
    mov     ss,ax
    mov     sp,stacktop
```

This initial piece of code sets up DS to point to the data segment, and initializes SS and SP to point to the top of the provided stack. Notice that interrupts are implicitly disabled for one instruction after a move into SS, precisely for this situation, so that there's no chance of an interrupt occurring between the loads of SS and SP and not having a stack to execute on.

Note also that the special symbol `..start` is defined at the beginning of this code, which means that will be the entry point into the resulting executable file.

```
mov    dx,hello
mov    ah,9
int    0x21
```

The above is the main program: load DS:DX with a pointer to the greeting message (`hello` is implicitly relative to the segment data, which was loaded into DS in the setup code, so the full pointer is valid), and call the DOS print-string function.

```
mov    ax,0x4c00
int    0x21
```

This terminates the program using another DOS system call.

```
segment data
```

```
hello: db    'hello, world', 13, 10, '$'
```

The data segment contains the string we want to display.

```
segment stack stack
        resb 64
```

```
stacktop:
```

The above code declares a stack segment containing 64 bytes of uninitialized stack space, and points `stacktop` at the top of it. The directive `segment stack stack` defines a segment *called* `stack`, and also of *type* `STACK`. The latter is not necessary to the correct running of the program, but linkers are likely to issue warnings or errors if your program has no segment of type `STACK`.

The above file, when assembled into a `.OBJ` file, will link on its own to a valid `.EXE` file, which when run will print 'hello, world' and then exit.

9.1.2 Using the `bin` Format To Generate `.EXE` Files

The `.EXE` file format is simple enough that it's possible to build a `.EXE` file by writing a pure-binary program and sticking a 32-byte header on the front. This header is simple enough that it can be generated using `DB` and `DW` commands by `NASM` itself, so that you can use the `bin` output format to directly generate `.EXE` files.

Included in the `NASM` archives, in the `misc` subdirectory, is a file `exebin.mac` of macros. It defines three macros: `EXE_begin`, `EXE_stack` and `EXE_end`.

To produce a `.EXE` file using this method, you should start by using `%include` to load the `exebin.mac` macro package into your source file. You should then issue the `EXE_begin` macro call (which takes no arguments) to generate the file header data. Then write code as normal for the `bin` format – you can use all three standard sections `.text`, `.data` and `.bss`. At the end of the file you should call the `EXE_end` macro (again, no arguments), which defines some symbols to mark section sizes, and these symbols are referred to in the header code generated by `EXE_begin`.

In this model, the code you end up writing starts at `0x100`, just like a `.COM` file – in fact, if you strip off the 32-byte header from the resulting `.EXE` file, you will have a valid `.COM` program. All the segment bases are the same, so you are limited to a 64K program, again just like a `.COM` file. Note that an `ORG` directive is issued by the `EXE_begin` macro, so you should not explicitly issue one of your own.

You can't directly refer to your segment base value, unfortunately, since this would require a relocation in the header, and things would get a lot more complicated. So you should get your segment base by copying it out of `CS` instead.

On entry to your .EXE file, SS:SP are already set up to point to the top of a 2Kb stack. You can adjust the default stack size of 2Kb by calling the EXE_stack macro. For example, to change the stack size of your program to 64 bytes, you would call EXE_stack 64.

A sample program which generates a .EXE file in this way is given in the test subdirectory of the NASM archive, as binexe.asm.

9.2 Producing .COM Files

While large DOS programs must be written as .EXE files, small ones are often better written as .COM files. .COM files are pure binary, and therefore most easily produced using the bin output format.

9.2.1 Using the bin Format To Generate .COM Files

.COM files expect to be loaded at offset 100h into their segment (though the segment may change). Execution then begins at 100h, i.e. right at the start of the program. So to write a .COM program, you would create a source file looking like

```
org 100h

section .text

start:
    ; put your code here

section .data

    ; put data items here

section .bss

    ; put uninitialized data here
```

The bin format puts the .text section first in the file, so you can declare data or BSS items before beginning to write code if you want to and the code will still end up at the front of the file where it belongs.

The BSS (uninitialized data) section does not take up space in the .COM file itself: instead, addresses of BSS items are resolved to point at space beyond the end of the file, on the grounds that this will be free memory when the program is run. Therefore you should not rely on your BSS being initialized to all zeros when you run.

To assemble the above program, you should use a command line like

```
nasm myprog.asm -fbin -o myprog.com
```

The bin format would produce a file called myprog if no explicit output file name were specified, so you have to override it and give the desired file name.

9.2.2 Using the obj Format To Generate .COM Files

If you are writing a .COM program as more than one module, you may wish to assemble several .OBJ files and link them together into a .COM program. You can do this, provided you have a linker capable of outputting .COM files directly (TLINK does this), or alternatively a converter program such as EXE2BIN to transform the .EXE file output from the linker into a .COM file.

If you do this, you need to take care of several things:

- The first object file containing code should start its code segment with a line like RESB 100h. This is to ensure that the code begins at offset 100h relative to the beginning of the code segment, so

that the linker or converter program does not have to adjust address references within the file when generating the .COM file. Other assemblers use an ORG directive for this purpose, but ORG in NASM is a format-specific directive to the bin output format, and does not mean the same thing as it does in MASM-compatible assemblers.

- You don't need to define a stack segment.
- All your segments should be in the same group, so that every time your code or data references a symbol offset, all offsets are relative to the same segment base. This is because, when a .COM file is loaded, all the segment registers contain the same value.

9.3 Producing .SYS Files

MS-DOS device drivers – .SYS files – are pure binary files, similar to .COM files, except that they start at origin zero rather than 100h. Therefore, if you are writing a device driver using the bin format, you do not need the ORG directive, since the default origin for bin is zero. Similarly, if you are using obj, you do not need the RESB 100h at the start of your code segment.

.SYS files start with a header structure, containing pointers to the various routines inside the driver which do the work. This structure should be defined at the start of the code segment, even though it is not actually code.

For more information on the format of .SYS files, and the data which has to go in the header structure, a list of books is given in the Frequently Asked Questions list for the newsgroup comp.os.msdos.programmer.

9.4 Interfacing to 16-bit C Programs

This section covers the basics of writing assembly routines that call, or are called from, C programs. To do this, you would typically write an assembly module as a .OBJ file, and link it with your C modules to produce a mixed-language program.

9.4.1 External Symbol Names

C compilers have the convention that the names of all global symbols (functions or data) they define are formed by prefixing an underscore to the name as it appears in the C program. So, for example, the function a C programmer thinks of as printf appears to an assembly language programmer as _printf. This means that in your assembly programs, you can define symbols without a leading underscore, and not have to worry about name clashes with C symbols.

If you find the underscores inconvenient, you can define macros to replace the GLOBAL and EXTERN directives as follows:

```
%macro  cglobal 1
    global  _%1
    %define  %1  _%1
%endmacro

%macro  cextern 1
    extern  _%1
    %define  %1  _%1
%endmacro
```

(These forms of the macros only take one argument at a time; a %rep construct could solve this.)

If you then declare an external like this:


```
cextern printf
```

then the macro will expand it as

```
extern _printf  
%define printf _printf
```

Thereafter, you can reference `printf` as if it was a symbol, and the preprocessor will put the leading underscore on where necessary.

The `cglobal` macro works similarly. You must use `cglobal` before defining the symbol in question, but you would have had to do that anyway if you used `GLOBAL`.

Also see section 2.1.28.

9.4.2 Memory Models

NASM contains no mechanism to support the various C memory models directly; you have to keep track yourself of which one you are writing for. This means you have to keep track of the following things:

- In models using a single code segment (tiny, small and compact), functions are near. This means that function pointers, when stored in data segments or pushed on the stack as function arguments, are 16 bits long and contain only an offset field (the CS register never changes its value, and always gives the segment part of the full function address), and that functions are called using ordinary near CALL instructions and return using RETN (which, in NASM, is synonymous with RET anyway). This means both that you should write your own routines to return with RETN, and that you should call external C routines with near CALL instructions.
- In models using more than one code segment (medium, large and huge), functions are far. This means that function pointers are 32 bits long (consisting of a 16-bit offset followed by a 16-bit segment), and that functions are called using CALL FAR (or CALL seg:offset) and return using RETF. Again, you should therefore write your own routines to return with RETF and use CALL FAR to call external routines.
- In models using a single data segment (tiny, small and medium), data pointers are 16 bits long, containing only an offset field (the DS register doesn't change its value, and always gives the segment part of the full data item address).
- In models using more than one data segment (compact, large and huge), data pointers are 32 bits long, consisting of a 16-bit offset followed by a 16-bit segment. You should still be careful not to modify DS in your routines without restoring it afterwards, but ES is free for you to use to access the contents of 32-bit data pointers you are passed.
- The huge memory model allows single data items to exceed 64K in size. In all other memory models, you can access the whole of a data item just by doing arithmetic on the offset field of the pointer you are given, whether a segment field is present or not; in huge model, you have to be more careful of your pointer arithmetic.
- In most memory models, there is a *default* data segment, whose segment address is kept in DS throughout the program. This data segment is typically the same segment as the stack, kept in SS, so that functions' local variables (which are stored on the stack) and global data items can both be accessed easily without changing DS. Particularly large data items are typically stored in other segments. However, some memory models (though not the standard ones, usually) allow the assumption that SS and DS hold the same value to be removed. Be careful about functions' local variables in this latter case.

In models with a single code segment, the segment is called `_TEXT`, so your code segment must also go by this name in order to be linked into the same place as the main code segment. In models with a single data segment, or with a default data segment, it is called `_DATA`.

9.4.3 Function Definitions and Function Calls

The C calling convention in 16-bit programs is as follows. In the following description, the words *caller* and *callee* are used to denote the function doing the calling and the function which gets called.

- The caller pushes the function's parameters on the stack, one after another, in reverse order (right to left, so that the first argument specified to the function is pushed last).
- The caller then executes a CALL instruction to pass control to the callee. This CALL is either near or far depending on the memory model.
- The callee receives control, and typically (although this is not actually necessary, in functions which do not need to access their parameters) starts by saving the value of SP in BP so as to be able to use BP as a base pointer to find its parameters on the stack. However, the caller was probably doing this too, so part of the calling convention states that BP must be preserved by any C function. Hence the callee, if it is going to set up BP as a *frame pointer*, must push the previous value first.
- The callee may then access its parameters relative to BP. The word at [BP] holds the previous value of BP as it was pushed; the next word, at [BP+2], holds the offset part of the return address, pushed implicitly by CALL. In a small-model (near) function, the parameters start after that, at [BP+4]; in a large-model (far) function, the segment part of the return address lives at [BP+4], and the parameters begin at [BP+6]. The leftmost parameter of the function, since it was pushed last, is accessible at this offset from BP; the others follow, at successively greater offsets. Thus, in a function such as printf which takes a variable number of parameters, the pushing of the parameters in reverse order means that the function knows where to find its first parameter, which tells it the number and type of the remaining ones.
- The callee may also wish to decrease SP further, so as to allocate space on the stack for local variables, which will then be accessible at negative offsets from BP.
- The callee, if it wishes to return a value to the caller, should leave the value in AL, AX or DX:AX depending on the size of the value. Floating-point results are sometimes (depending on the compiler) returned in ST0.
- Once the callee has finished processing, it restores SP from BP if it had allocated local stack space, then pops the previous value of BP, and returns via RETN or RETF depending on memory model.
- When the caller regains control from the callee, the function parameters are still on the stack, so it typically adds an immediate constant to SP to remove them (instead of executing a number of slow POP instructions). Thus, if a function is accidentally called with the wrong number of parameters due to a prototype mismatch, the stack will still be returned to a sensible state since the caller, which *knows* how many parameters it pushed, does the removing.

It is instructive to compare this calling convention with that for Pascal programs (described in section 9.5.1). Pascal has a simpler convention, since no functions have variable numbers of parameters. Therefore the callee knows how many parameters it should have been passed, and is able to deallocate them from the stack itself by passing an immediate argument to the RET or RETF instruction, so the caller does not have to do it. Also, the parameters are pushed in left-to-right order, not right-to-left, which means that a compiler can give better guarantees about sequence points without performance suffering.

Thus, you would define a function in C style in the following way. The following example is for small model:

```
global _myfunc

_myfunc:
    push    bp
    mov     bp, sp
```

```

sub    sp,0x40          ; 64 bytes of local stack space
mov    bx,[bp+4]        ; first parameter to function

; some more code

mov    sp,bp            ; undo "sub sp,0x40" above
pop    bp
ret

```

For a large-model function, you would replace RET by RETF, and look for the first parameter at [BP+6] instead of [BP+4]. Of course, if one of the parameters is a pointer, then the offsets of *subsequent* parameters will change depending on the memory model as well: far pointers take up four bytes on the stack when passed as a parameter, whereas near pointers take up two.

At the other end of the process, to call a C function from your assembly code, you would do something like this:

```

extern _printf

; and then, further down...

push   word [myint]      ; one of my integer variables
push   word mystring     ; pointer into my data segment
call   _printf
add    sp,byte 4         ; 'byte' saves space

; then those data items...

segment _DATA

myint   dw    1234
mystring db   'This number -> %d <- should be 1234',10,0

```

This piece of code is the small-model assembly equivalent of the C code

```

int myint = 1234;
printf("This number -> %d <- should be 1234\n", myint);

```

In large model, the function-call code might look more like this. In this example, it is assumed that DS already holds the segment base of the segment `_DATA`. If not, you would have to initialize it first.

```

push   word [myint]
push   word seg mystring ; Now push the segment, and...
push   word mystring     ; ... offset of "mystring"
call   far _printf
add    sp,byte 6

```

The integer value still takes up one word on the stack, since large model does not affect the size of the `int` data type. The first argument (pushed last) to `printf`, however, is a data pointer, and therefore has to contain a segment and offset part. The segment should be stored second in memory, and therefore must be pushed first. (Of course, `PUSH DS` would have been a shorter instruction than `PUSH WORD SEG mystring`, if DS was set up as the above example assumed.) Then the actual call becomes a far call, since functions expect far calls in large model; and SP has to be increased by 6 rather than 4 afterwards to make up for the extra word of parameters.

9.4.4 Accessing Data Items

To get at the contents of C variables, or to declare variables which C can access, you need only declare the names as GLOBAL or EXTERN. (Again, the names require leading underscores, as stated in section 9.4.1.) Thus, a C variable declared as `int i` can be accessed from assembler as

```
extern _i

        mov ax,[_i]
```

And to declare your own integer variable which C programs can access as `extern int j`, you do this (making sure you are assembling in the `_DATA` segment, if necessary):

```
global _j

_j      dw      0
```

To access a C array, you need to know the size of the components of the array. For example, `int` variables are two bytes long, so if a C program declares an array as `int a[10]`, you can access `a[3]` by coding `mov ax,[_a+6]`. (The byte offset 6 is obtained by multiplying the desired array index, 3, by the size of the array element, 2.) The sizes of the C base types in 16-bit compilers are: 1 for `char`, 2 for `short` and `int`, 4 for `long` and `float`, and 8 for `double`.

To access a C data structure, you need to know the offset from the base of the structure to the field you are interested in. You can either do this by converting the C structure definition into a NASM structure definition (using `STRUC`), or by calculating the one offset and using just that.

To do either of these, you should read your C compiler's manual to find out how it organizes data structures. NASM gives no special alignment to structure members in its own `STRUC` macro, so you have to specify alignment yourself if the C compiler generates it. Typically, you might find that a structure like

```
struct {
    char c;
    int i;
} foo;
```

might be four bytes long rather than three, since the `int` field would be aligned to a two-byte boundary. However, this sort of feature tends to be a configurable option in the C compiler, either using command-line options or `#pragma` lines, so you have to find out how your own compiler does it.

9.4.5 `c16.mac`: Helper Macros for the 16-bit C Interface

Included in the NASM archives, in the `misc` directory, is a file `c16.mac` of macros. It defines three macros: `proc`, `arg` and `endproc`. These are intended to be used for C-style procedure definitions, and they automate a lot of the work involved in keeping track of the calling convention.

(An alternative, TASM compatible form of `arg` is also now built into NASM's preprocessor. See section 4.8 for details.)

An example of an assembly function using the macro set is given here:

```
proc    _nearproc

%$i    arg
%$j    arg
        mov     ax,[bp + %$i]
        mov     bx,[bp + %$j]
        add     ax,[bx]
```

endproc

This defines `_nearproc` to be a procedure taking two arguments, the first (`i`) an integer and the second (`j`) a pointer to an integer. It returns `i + *j`.

Note that the `arg` macro has an EQU as the first line of its expansion, and since the label before the macro call gets prepended to the first line of the expanded macro, the EQU works, defining `$$i` to be an offset from BP. A context-local variable is used, local to the context pushed by the `proc` macro and popped by the `endproc` macro, so that the same argument name can be used in later procedures. Of course, you don't *have* to do that.

The macro set produces code for near functions (tiny, small and compact-model code) by default. You can have it generate far functions (medium, large and huge-model code) by means of coding `%define FARCODE`. This changes the kind of return instruction generated by `endproc`, and also changes the starting point for the argument offsets. The macro set contains no intrinsic dependency on whether data pointers are far or not.

`arg` can take an optional parameter, giving the size of the argument. If no size is given, 2 is assumed, since it is likely that many function parameters will be of type `int`.

The large-model equivalent of the above function would look like this:

```
%define FARCODE

proc    _farproc

$$i    arg
$$j    arg      4
        mov     ax,[bp + $$i]
        mov     bx,[bp + $$j]
        mov     es,[bp + $$j + 2]
        add     ax,[bx]
```

endproc

This makes use of the argument to the `arg` macro to define a parameter of size 4, because `j` is now a far pointer. When we load from `j`, we must load a segment and an offset.

9.5 Interfacing to Borland Pascal Programs

Interfacing to Borland Pascal programs is similar in concept to interfacing to 16-bit C programs. The differences are:

- The leading underscore required for interfacing to C programs is not required for Pascal.
- The memory model is always large: functions are far, data pointers are far, and no data item can be more than 64K long. (Actually, some functions are near, but only those functions that are local to a Pascal unit and never called from outside it. All assembly functions that Pascal calls, and all Pascal functions that assembly routines are able to call, are far.) However, all static data declared in a Pascal program goes into the default data segment, which is the one whose segment address will be in DS when control is passed to your assembly code. The only things that do not live in the default data segment are local variables (they live in the stack segment) and dynamically allocated variables. All data *pointers*, however, are far.
- The function calling convention is different – described below.
- Some data types, such as strings, are stored differently.

- There are restrictions on the segment names you are allowed to use – Borland Pascal will ignore code or data declared in a segment it doesn't like the name of. The restrictions are described below.

9.5.1 The Pascal Calling Convention

The 16-bit Pascal calling convention is as follows. In the following description, the words *caller* and *callee* are used to denote the function doing the calling and the function which gets called.

- The caller pushes the function's parameters on the stack, one after another, in normal order (left to right, so that the first argument specified to the function is pushed first).
- The caller then executes a far CALL instruction to pass control to the callee.
- The callee receives control, and typically (although this is not actually necessary, in functions which do not need to access their parameters) starts by saving the value of SP in BP so as to be able to use BP as a base pointer to find its parameters on the stack. However, the caller was probably doing this too, so part of the calling convention states that BP must be preserved by any function. Hence the callee, if it is going to set up BP as a frame pointer, must push the previous value first.
- The callee may then access its parameters relative to BP. The word at [BP] holds the previous value of BP as it was pushed. The next word, at [BP+2], holds the offset part of the return address, and the next one at [BP+4] the segment part. The parameters begin at [BP+6]. The rightmost parameter of the function, since it was pushed last, is accessible at this offset from BP; the others follow, at successively greater offsets.
- The callee may also wish to decrease SP further, so as to allocate space on the stack for local variables, which will then be accessible at negative offsets from BP.
- The callee, if it wishes to return a value to the caller, should leave the value in AL, AX or DX:AX depending on the size of the value. Floating-point results are returned in ST0. Results of type Real (Borland's own custom floating-point data type, not handled directly by the FPU) are returned in DX:BX:AX. To return a result of type String, the caller pushes a pointer to a temporary string before pushing the parameters, and the callee places the returned string value at that location. The pointer is not a parameter, and should not be removed from the stack by the RETF instruction.
- Once the callee has finished processing, it restores SP from BP if it had allocated local stack space, then pops the previous value of BP, and returns via RETF. It uses the form of RETF with an immediate parameter, giving the number of bytes taken up by the parameters on the stack. This causes the parameters to be removed from the stack as a side effect of the return instruction.
- When the caller regains control from the callee, the function parameters have already been removed from the stack, so it needs to do nothing further.

Thus, you would define a function in Pascal style, taking two Integer-type parameters, in the following way:

```
global myfunc

myfunc: push    bp
        mov     bp,sp
        sub     sp,0x40          ; 64 bytes of local stack space
        mov     bx,[bp+8]       ; first parameter to function
        mov     bx,[bp+6]       ; second parameter to function

        ; some more code

        mov     sp,bp          ; undo "sub sp,0x40" above
        pop     bp
        retf    4              ; total size of params is 4
```

At the other end of the process, to call a Pascal function from your assembly code, you would do something like this:

```
extern SomeFunc

; and then, further down...

push word seg mystring ; Now push the segment, and...
push word mystring ; ... offset of "mystring"
push word [myint] ; one of my variables
call far SomeFunc
```

This is equivalent to the Pascal code

```
procedure SomeFunc(String: PChar; Int: Integer);
  SomeFunc(@mystring, myint);
```

9.5.2 Borland Pascal Segment Name Restrictions

Since Borland Pascal's internal unit file format is completely different from OBJ, it only makes a very sketchy job of actually reading and understanding the various information contained in a real OBJ file when it links that in. Therefore an object file intended to be linked to a Pascal program must obey a number of restrictions:

- Procedures and functions must be in a segment whose name is either CODE, CSEG, or something ending in _TEXT.
- initialized data must be in a segment whose name is either CONST or something ending in _DATA.
- Uninitialized data must be in a segment whose name is either DATA, DSEG, or something ending in _BSS.
- Any other segments in the object file are completely ignored. GROUP directives and segment attributes are also ignored.

9.5.3 Using c16.mac With Pascal Programs

The c16.mac macro package, described in section 9.4.5, can also be used to simplify writing functions to be called from Pascal programs, if you code `%define PASCAL`. This definition ensures that functions are far (it implies FARCODE), and also causes procedure return instructions to be generated with an operand.

Defining PASCAL does not change the code which calculates the argument offsets; you must declare your function's arguments in reverse order. For example:

```
%define PASCAL

proc _pascalproc

%$j arg 4
%$i arg
  mov ax,[bp + %$i]
  mov bx,[bp + %$j]
  mov es,[bp + %$j + 2]
  add ax,[bx]

endproc
```

This defines the same routine, conceptually, as the example in section 9.4.5: it defines a function taking two arguments, an integer and a pointer to an integer, which returns the sum of the integer and the

contents of the pointer. The only difference between this code and the large-model C version is that PASCAL is defined instead of FARCODE, and that the arguments are declared in reverse order.

Chapter 10: Writing 32-bit Code (Unix, Win32, DJGPP)

This chapter attempts to cover some of the common issues involved when writing 32-bit code, to run under Win32 or Unix, or to be linked with C code generated by a Unix-style C compiler such as DJGPP. It covers how to write assembly code to interface with 32-bit C routines, and how to write position-independent code for shared libraries.

Almost all 32-bit code, and in particular all code running under Win32, DJGPP or any of the PC Unix variants, runs in *flat* memory model. This means that the segment registers and paging have already been set up to give you the same 32-bit 4Gb address space no matter what segment you work relative to, and that you should ignore all segment registers completely. When writing flat-model application code, you never need to use a segment override or modify any segment register, and the code-section addresses you pass to CALL and JMP live in the same address space as the data-section addresses you access your variables by and the stack-section addresses you access local variables and procedure parameters by. Every address is 32 bits long and contains only an offset part.

10.1 Interfacing to 32-bit C Programs

A lot of the discussion in section 9.4, about interfacing to 16-bit C programs, still applies when working in 32 bits. The absence of memory models or segmentation worries simplifies things a lot.

10.1.1 External Symbol Names

Most 32-bit C compilers share the convention used by 16-bit compilers, that the names of all global symbols (functions or data) they define are formed by prefixing an underscore to the name as it appears in the C program. However, not all of them do: the ELF specification states that C symbols do *not* have a leading underscore on their assembly-language names.

The older Linux `a.out` C compiler, all Win32 compilers, DJGPP, and NetBSD and FreeBSD, all use the leading underscore; for these compilers, the macros `cextern` and `cglobaL`, as given in section 9.4.1, will still work. For ELF, though, the leading underscore should not be used.

See also section 2.1.28.

10.1.2 Function Definitions and Function Calls

The C calling convention in 32-bit programs is as follows. In the following description, the words *caller* and *callee* are used to denote the function doing the calling and the function which gets called.

- The caller pushes the function's parameters on the stack, one after another, in reverse order (right to left, so that the first argument specified to the function is pushed last).
- The caller then executes a near CALL instruction to pass control to the callee.
- The callee receives control, and typically (although this is not actually necessary, in functions which do not need to access their parameters) starts by saving the value of ESP in EBP so as to be able to use EBP as a base pointer to find its parameters on the stack. However, the caller was probably doing this too, so part of the calling convention states that EBP must be preserved by any C function. Hence the callee, if it is going to set up EBP as a frame pointer, must push the previous value first.
- The callee may then access its parameters relative to EBP. The doubleword at `[EBP]` holds the previous value of EBP as it was pushed; the next doubleword, at `[EBP+4]`, holds the return address, pushed implicitly by CALL. The parameters start after that, at `[EBP+8]`. The leftmost parameter of the function, since it was pushed last, is accessible at this offset from EBP; the others follow, at successively greater offsets. Thus, in a function such as `printf` which takes a variable

number of parameters, the pushing of the parameters in reverse order means that the function knows where to find its first parameter, which tells it the number and type of the remaining ones.

- The callee may also wish to decrease ESP further, so as to allocate space on the stack for local variables, which will then be accessible at negative offsets from EBP.
- The callee, if it wishes to return a value to the caller, should leave the value in AL, AX or EAX depending on the size of the value. Floating-point results are typically returned in ST0.
- Once the callee has finished processing, it restores ESP from EBP if it had allocated local stack space, then pops the previous value of EBP, and returns via RET (equivalently, RETN).
- When the caller regains control from the callee, the function parameters are still on the stack, so it typically adds an immediate constant to ESP to remove them (instead of executing a number of slow POP instructions). Thus, if a function is accidentally called with the wrong number of parameters due to a prototype mismatch, the stack will still be returned to a sensible state since the caller, which *knows* how many parameters it pushed, does the removing.

There is an alternative calling convention used by Win32 programs for Windows API calls, and also for functions called *by* the Windows API such as window procedures: they follow what Microsoft calls the `__stdcall` convention. This is slightly closer to the Pascal convention, in that the callee clears the stack by passing a parameter to the RET instruction. However, the parameters are still pushed in right-to-left order.

Thus, you would define a function in C style in the following way:

```
global _myfunc

_myfunc:
    push    ebp
    mov     ebp,esp
    sub     esp,0x40        ; 64 bytes of local stack space
    mov     ebx,[ebp+8]    ; first parameter to function

    ; some more code

    leave           ; mov esp,ebp / pop ebp
    ret
```

At the other end of the process, to call a C function from your assembly code, you would do something like this:

```
extern _printf

    ; and then, further down...

    push    dword [myint]  ; one of my integer variables
    push    dword mystring ; pointer into my data segment
    call    _printf
    add     esp,byte 8      ; 'byte' saves space

    ; then those data items...

segment _DATA

myint      dd    1234
mystring   db    'This number -> %d <- should be 1234',10,0
```

This piece of code is the assembly equivalent of the C code

```
int myint = 1234;
printf("This number -> %d <- should be 1234\n", myint);
```

10.1.3 Accessing Data Items

To get at the contents of C variables, or to declare variables which C can access, you need only declare the names as GLOBAL or EXTERN. (Again, the names require leading underscores, as stated in section 10.1.1.) Thus, a C variable declared as `int i` can be accessed from assembler as

```
extern _i
mov eax,[_i]
```

And to declare your own integer variable which C programs can access as `extern int j`, you do this (making sure you are assembling in the `_DATA` segment, if necessary):

```
_j      global _j
        dd 0
```

To access a C array, you need to know the size of the components of the array. For example, `int` variables are four bytes long, so if a C program declares an array as `int a[10]`, you can access `a[3]` by coding `mov ax,[_a+12]`. (The byte offset 12 is obtained by multiplying the desired array index, 3, by the size of the array element, 4.) The sizes of the C base types in 32-bit compilers are: 1 for `char`, 2 for `short`, 4 for `int`, `long` and `float`, and 8 for `double`. Pointers, being 32-bit addresses, are also 4 bytes long.

To access a C data structure, you need to know the offset from the base of the structure to the field you are interested in. You can either do this by converting the C structure definition into a NASM structure definition (using `STRUC`), or by calculating the one offset and using just that.

To do either of these, you should read your C compiler's manual to find out how it organizes data structures. NASM gives no special alignment to structure members in its own `STRUC` macro, so you have to specify alignment yourself if the C compiler generates it. Typically, you might find that a structure like

```
struct {
    char c;
    int i;
} foo;
```

might be eight bytes long rather than five, since the `int` field would be aligned to a four-byte boundary. However, this sort of feature is sometimes a configurable option in the C compiler, either using command-line options or `#pragma` lines, so you have to find out how your own compiler does it.

10.1.4 c32.mac: Helper Macros for the 32-bit C Interface

Included in the NASM archives, in the `misc` directory, is a file `c32.mac` of macros. It defines three macros: `proc`, `arg` and `endproc`. These are intended to be used for C-style procedure definitions, and they automate a lot of the work involved in keeping track of the calling convention.

An example of an assembly function using the macro set is given here:

```
proc    _proc32

%$i    arg
%$j    arg
        mov    eax,[ebp + %$i]
        mov    ebx,[ebp + %$j]
        add    eax,[ebx]

endproc
```

This defines `_proc32` to be a procedure taking two arguments, the first (`i`) an integer and the second (`j`) a pointer to an integer. It returns `i + *j`.

Note that the `arg` macro has an `EQU` as the first line of its expansion, and since the label before the macro call gets prepended to the first line of the expanded macro, the `EQU` works, defining `_%$i` to be an offset from `BP`. A context-local variable is used, local to the context pushed by the `proc` macro and popped by the `endproc` macro, so that the same argument name can be used in later procedures. Of course, you don't *have* to do that.

`arg` can take an optional parameter, giving the size of the argument. If no size is given, 4 is assumed, since it is likely that many function parameters will be of type `int` or pointers.

10.2 Writing NetBSD/FreeBSD/OpenBSD and Linux/ELF Shared Libraries

ELF replaced the older `a.out` object file format under Linux because it contains support for position-independent code (PIC), which makes writing shared libraries much easier. NASM supports the ELF position-independent code features, so you can write Linux ELF shared libraries in NASM.

NetBSD, and its close cousins FreeBSD and OpenBSD, take a different approach by hacking PIC support into the `a.out` format. NASM supports this as the `aoutb` output format, so you can write BSD shared libraries in NASM too.

The operating system loads a PIC shared library by memory-mapping the library file at an arbitrarily chosen point in the address space of the running process. The contents of the library's code section must therefore not depend on where it is loaded in memory.

Therefore, you cannot get at your variables by writing code like this:

```
mov     eax, [myvar]           ; WRONG
```

Instead, the linker provides an area of memory called the *global offset table*, or GOT; the GOT is situated at a constant distance from your library's code, so if you can find out where your library is loaded (which is typically done using a `CALL` and `POP` combination), you can obtain the address of the GOT, and you can then load the addresses of your variables out of linker-generated entries in the GOT.

The *data* section of a PIC shared library does not have these restrictions: since the data section is writable, it has to be copied into memory anyway rather than just paged in from the library file, so as long as it's being copied it can be relocated too. So you can put ordinary types of relocation in the data section without too much worry (but see section 10.2.4 for a caveat).

10.2.1 Obtaining the Address of the GOT

Each code module in your shared library should define the GOT as an external symbol:

```
extern  _GLOBAL_OFFSET_TABLE_  ; in ELF
extern  __GLOBAL_OFFSET_TABLE_ ; in BSD a.out
```

At the beginning of any function in your shared library which plans to access your data or BSS sections, you must first calculate the address of the GOT. This is typically done by writing the function in this form:

```
func:  push    ebp
       mov     ebp, esp
       push   ebx
       call   .get_GOT
.get_GOT:
       pop    ebx
       add    ebx, _GLOBAL_OFFSET_TABLE_ + $$ - .get_GOT wrt ..gotpc

       ; the function body comes here
```

```

mov     ebx,[ebp-4]
mov     esp,ebp
pop     ebp
ret

```

(For BSD, again, the symbol `_GLOBAL_OFFSET_TABLE` requires a second leading underscore.)

The first two lines of this function are simply the standard C prologue to set up a stack frame, and the last three lines are standard C function epilogue. The third line, and the fourth to last line, save and restore the EBX register, because PIC shared libraries use this register to store the address of the GOT.

The interesting bit is the CALL instruction and the following two lines. The CALL and POP combination obtains the address of the label `.get_GOT`, without having to know in advance where the program was loaded (since the CALL instruction is encoded relative to the current position). The ADD instruction makes use of one of the special PIC relocation types: GOTPC relocation. With the WRT `..gotpc` qualifier specified, the symbol referenced (here `_GLOBAL_OFFSET_TABLE_`, the special symbol assigned to the GOT) is given as an offset from the beginning of the section. (Actually, ELF encodes it as the offset from the operand field of the ADD instruction, but NASM simplifies this deliberately, so you do things the same way for both ELF and BSD.) So the instruction then *adds* the beginning of the section, to get the real address of the GOT, and subtracts the value of `.get_GOT` which it knows is in EBX. Therefore, by the time that instruction has finished, EBX contains the address of the GOT.

If you didn't follow that, don't worry: it's never necessary to obtain the address of the GOT by any other means, so you can put those three instructions into a macro and safely ignore them:

```

%macro  get_GOT 0

        call    %%getgot
%%getgot:
        pop     ebx
        add     ebx,_GLOBAL_OFFSET_TABLE_+$$-%%getgot wrt ..gotpc

%endmacro

```

10.2.2 Finding Your Local Data Items

Having got the GOT, you can then use it to obtain the addresses of your data items. Most variables will reside in the sections you have declared; they can be accessed using the `..gotoff` special WRT type. The way this works is like this:

```

lea     eax,[ebx+myvar wrt ..gotoff]

```

The expression `myvar wrt ..gotoff` is calculated, when the shared library is linked, to be the offset to the local variable `myvar` from the beginning of the GOT. Therefore, adding it to EBX as above will place the real address of `myvar` in EAX.

If you declare variables as GLOBAL without specifying a size for them, they are shared between code modules in the library, but do not get exported from the library to the program that loaded it. They will still be in your ordinary data and BSS sections, so you can access them in the same way as local variables, using the above `..gotoff` mechanism.

Note that due to a peculiarity of the way BSD a.out format handles this relocation type, there must be at least one non-local symbol in the same section as the address you're trying to access.

10.2.3 Finding External and Common Data Items

If your library needs to get at an external variable (external to the *library*, not just to one of the modules within it), you must use the `..got` type to get at it. The `..got` type, instead of giving you the offset

from the GOT base to the variable, gives you the offset from the GOT base to a GOT *entry* containing the address of the variable. The linker will set up this GOT entry when it builds the library, and the dynamic linker will place the correct address in it at load time. So to obtain the address of an external variable `extvar` in EAX, you would code

```
mov    eax,[ebx+extvar wrt ..got]
```

This loads the address of `extvar` out of an entry in the GOT. The linker, when it builds the shared library, collects together every relocation of type `..got`, and builds the GOT so as to ensure it has every necessary entry present.

Common variables must also be accessed in this way.

10.2.4 Exporting Symbols to the Library User

If you want to export symbols to the user of the library, you have to declare whether they are functions or data, and if they are data, you have to give the size of the data item. This is because the dynamic linker has to build procedure linkage table entries for any exported functions, and also moves exported data items away from the library's data section in which they were declared.

So to export a function to users of the library, you must use

```
global func:function          ; declare it as a function

func:  push    ebp

      ; etc.
```

And to export a data item such as an array, you would have to code

```
global array:data array.end=array      ; give the size too

array:  resd   128
       .end:
```

Be careful: If you export a variable to the library user, by declaring it as GLOBAL and supplying a size, the variable will end up living in the data section of the main program, rather than in your library's data section, where you declared it. So you will have to access your own global variable with the `..got` mechanism rather than `..gotoff`, as if it were external (which, effectively, it has become).

Equally, if you need to store the address of an exported global in one of your data sections, you can't do it by means of the standard sort of code:

```
dataptr:      dd      global_data_item      ; WRONG
```

NASM will interpret this code as an ordinary relocation, in which `global_data_item` is merely an offset from the beginning of the `.data` section (or whatever); so this reference will end up pointing at your data section instead of at the exported global which resides elsewhere.

Instead of the above code, then, you must write

```
dataptr:      dd      global_data_item wrt ..sym
```

which makes use of the special WRT type `..sym` to instruct NASM to search the symbol table for a particular symbol at that address, rather than just relocating by section base.

Either method will work for functions: referring to one of your functions by means of

```
funcptr:      dd      my_function
```

will give the user the address of the code you wrote, whereas

```
funcptr:      dd      my_function wrt ..sym
```

will give the address of the procedure linkage table for the function, which is where the calling program will *believe* the function lives. Either address is a valid way to call the function.

10.2.5 Calling Procedures Outside the Library

Calling procedures outside your shared library has to be done by means of a *procedure linkage table*, or PLT. The PLT is placed at a known offset from where the library is loaded, so the library code can make calls to the PLT in a position-independent way. Within the PLT there is code to jump to offsets contained in the GOT, so function calls to other shared libraries or to routines in the main program can be transparently passed off to their real destinations.

To call an external routine, you must use another special PIC relocation type, `WRT ..plt`. This is much easier than the GOT-based ones: you simply replace calls such as `CALL printf` with the PLT-relative version `CALL printf WRT ..plt`.

10.2.6 Generating the Library File

Having written some code modules and assembled them to `.o` files, you then generate your shared library with a command such as

```
ld -shared -o library.so module1.o module2.o      # for ELF
ld -Bshareable -o library.so module1.o module2.o  # for BSD
```

For ELF, if your shared library is going to reside in system directories such as `/usr/lib` or `/lib`, it is usually worth using the `-soname` flag to the linker, to store the final library file name, with a version number, into the library:

```
ld -shared -soname library.so.1 -o library.so.1.2 *.o
```

You would then copy `library.so.1.2` into the library directory, and create `library.so.1` as a symbolic link to it.

Chapter 11: Mixing 16- and 32-bit Code

This chapter tries to cover some of the issues, largely related to unusual forms of addressing and jump instructions, encountered when writing operating system code such as protected-mode initialisation routines, which require code that operates in mixed segment sizes, such as code in a 16-bit segment trying to modify data in a 32-bit one, or jumps between different-size segments.

11.1 Mixed-Size Jumps

The most common form of mixed-size instruction is the one used when writing a 32-bit OS: having done your setup in 16-bit mode, such as loading the kernel, you then have to boot it by switching into protected mode and jumping to the 32-bit kernel start address. In a fully 32-bit OS, this tends to be the *only* mixed-size instruction you need, since everything before it can be done in pure 16-bit code, and everything after it can be pure 32-bit.

This jump must specify a 48-bit far address, since the target segment is a 32-bit one. However, it must be assembled in a 16-bit segment, so just coding, for example,

```
jmp    0x1234:0x56789ABC    ; wrong!
```

will not work, since the offset part of the address will be truncated to 0x9ABC and the jump will be an ordinary 16-bit far one.

The Linux kernel setup code gets round the inability of `as86` to generate the required instruction by coding it manually, using `DB` instructions. NASM can go one better than that, by actually generating the right instruction itself. Here's how to do it right:

```
jmp    dword 0x1234:0x56789ABC    ; right
```

The `DWORD` prefix (strictly speaking, it should come *after* the colon, since it is declaring the *offset* field to be a doubleword; but NASM will accept either form, since both are unambiguous) forces the offset part to be treated as far, in the assumption that you are deliberately writing a jump from a 16-bit segment to a 32-bit one.

You can do the reverse operation, jumping from a 32-bit segment to a 16-bit one, by means of the `WORD` prefix:

```
jmp    word 0x8765:0x4321    ; 32 to 16 bit
```

If the `WORD` prefix is specified in 16-bit mode, or the `DWORD` prefix in 32-bit mode, they will be ignored, since each is explicitly forcing NASM into a mode it was in anyway.

11.2 Addressing Between Different-Size Segments

If your OS is mixed 16 and 32-bit, or if you are writing a DOS extender, you are likely to have to deal with some 16-bit segments and some 32-bit ones. At some point, you will probably end up writing code in a 16-bit segment which has to access data in a 32-bit segment, or vice versa.

If the data you are trying to access in a 32-bit segment lies within the first 64K of the segment, you may be able to get away with using an ordinary 16-bit addressing operation for the purpose; but sooner or later, you will want to do 32-bit addressing from 16-bit mode.

The easiest way to do this is to make sure you use a register for the address, since any effective address containing a 32-bit register is forced to be a 32-bit address. So you can do

```
mov    eax,offset_into_32_bit_segment_specified_by_fs
mov    dword [fs:eax],0x11223344
```

This is fine, but slightly cumbersome (since it wastes an instruction and a register) if you already know the precise offset you are aiming at. The x86 architecture does allow 32-bit effective addresses to specify nothing but a 4-byte offset, so why shouldn't NASM be able to generate the best instruction for the purpose?

It can. As in section 11.1, you need only prefix the address with the DWORD keyword, and it will be forced to be a 32-bit address:

```
mov     dword [fs:dword my_offset],0x11223344
```

Also as in section 11.1, NASM is not fussy about whether the DWORD prefix comes before or after the segment override, so arguably a nicer-looking way to code the above instruction is

```
mov     dword [dword fs:my_offset],0x11223344
```

Don't confuse the DWORD prefix *outside* the square brackets, which controls the size of the data stored at the address, with the one *inside* the square brackets which controls the length of the address itself. The two can quite easily be different:

```
mov     word [dword 0x12345678],0x9ABC
```

This moves 16 bits of data to an address specified by a 32-bit offset.

You can also specify WORD or DWORD prefixes along with the FAR prefix to indirect far jumps or calls. For example:

```
call    dword far [fs:word 0x4321]
```

This instruction contains an address specified by a 16-bit offset; it loads a 48-bit far pointer from that (16-bit segment and 32-bit offset), and calls that address.

11.3 Other Mixed-Size Instructions

The other way you might want to access data might be using the string instructions (LODSx, STOSx and so on) or the XLATB instruction. These instructions, since they take no parameters, might seem to have no easy way to make them perform 32-bit addressing when assembled in a 16-bit segment.

This is the purpose of NASM's a16, a32 and a64 prefixes. If you are coding LODSB in a 16-bit segment but it is supposed to be accessing a string in a 32-bit segment, you should load the desired address into ESI and then code

```
a32     lodsb
```

The prefix forces the addressing size to 32 bits, meaning that LODSB loads from [DS:ESI] instead of [DS:SI]. To access a string in a 16-bit segment when coding in a 32-bit one, the corresponding a16 prefix can be used.

The a16, a32 and a64 prefixes can be applied to any instruction in NASM's instruction table, but most of them can generate all the useful forms without them. The prefixes are necessary only for instructions with implicit addressing: CMPSx, SCASx, LODSx, STOSx, MOVSx, INSx, OUTSx, and XLATB. Also, the various push and pop instructions (PUSHA and POPF as well as the more usual PUSH and POP) can accept a16, a32 or a64 prefixes to force a particular one of SP, ESP or RSP to be used as a stack pointer, in case the stack segment in use is a different size from the code segment.

PUSH and POP, when applied to segment registers in 32-bit mode, also have the slightly odd behaviour that they push and pop 4 bytes at a time, of which the top two are ignored and the bottom two give the value of the segment register being manipulated. To force the 16-bit behaviour of segment-register push and pop instructions, you can use the operand-size prefix o16:

```
o16 push    ss
o16 push    ds
```

This code saves a doubleword of stack space by fitting two segment registers into the space which would normally be consumed by pushing one.

(You can also use the `o32` prefix to force the 32-bit behaviour when in 16-bit mode, but this seems less useful.)

Chapter 12: Writing 64-bit Code (Unix, Win64)

This chapter attempts to cover some of the common issues involved when writing 64-bit code, to run under Win64 or Unix. It covers how to write assembly code to interface with 64-bit C routines, and how to write position-independent code for shared libraries.

All 64-bit code uses a flat memory model, since segmentation is not available in 64-bit mode. The one exception is the FS and GS registers, which still add their bases.

Position independence in 64-bit mode is significantly simpler, since the processor supports RIP-relative addressing directly; see the REL keyword (section 3.3). On most 64-bit platforms, it is probably desirable to make that the default, using the directive `DEFAULT REL` (section 7.2).

64-bit programming is relatively similar to 32-bit programming, but of course pointers are 64 bits long; additionally, all existing platforms pass arguments in registers rather than on the stack. Furthermore, 64-bit platforms use SSE2 by default for floating point. Please see the ABI documentation for your platform.

64-bit platforms differ in the sizes of the C/C++ fundamental datatypes, not just from 32-bit platforms but from each other. If a specific size data type is desired, it is probably best to use the types defined in the standard C header `<inttypes.h>`.

All known 64-bit platforms except some embedded platforms require that the stack is 16-byte aligned at the entry to a function. In order to enforce that, the stack pointer (RSP) needs to be aligned on an odd multiple of 8 bytes before the CALL instruction.

In 64-bit mode, the default instruction size is still 32 bits. When loading a value into a 32-bit register (but not an 8- or 16-bit register), the upper 32 bits of the corresponding 64-bit register are set to zero.

12.1 Register Names in 64-bit Mode

NASM uses the following names for general-purpose registers in 64-bit mode, for 8-, 16-, 32- and 64-bit references, respectively:

```
AL/AH, CL/CH, DL/DH, BL/BH, SPL, BPL, SIL, DIL, R8B-R15B
AX, CX, DX, BX, SP, BP, SI, DI, R8W-R15W
EAX, ECX, EDX, EBX, ESP, EBP, ESI, EDI, R8D-R15D
RAX, RCX, RDX, RBX, RSP, RBP, RSI, RDI, R8-R15
```

This is consistent with the AMD documentation and most other assemblers. The Intel documentation, however, uses the names R8L-R15L for 8-bit references to the higher registers. It is possible to use those names by defining them as macros; similarly, if one wants to use numeric names for the low 8 registers, define them as macros. The standard macro package `altreg` (see section 6.1) can be used for this purpose.

12.2 immediates and Displacements in 64-bit Mode

In 64-bit mode, immediates and displacements are generally only 32 bits wide. NASM will therefore truncate most displacements and immediates to 32 bits.

The only instruction which takes a full 64-bit immediate is:

```
MOV reg64,imm64
```

NASM will produce this instruction whenever the programmer uses MOV with an immediate into a 64-bit register. If this is not desirable, simply specify the equivalent 32-bit register, which will be automatically zero-extended by the processor, or specify the immediate as `DWORD`:

```

mov rax,foo           ; 64-bit immediate
mov rax,qword foo    ; (identical)
mov eax,foo           ; 32-bit immediate, zero-extended
mov rax,dword foo    ; 32-bit immediate, sign-extended

```

The length of these instructions are 10, 5 and 7 bytes, respectively.

If optimization is enabled and NASM can determine at assembly time that a shorter instruction will suffice, the shorter instruction will be emitted unless of course `STRICT QWORD` or `STRICT DWORD` is specified (see section 3.7):

```

mov rax,1             ; Assembles as "mov eax,1" (5 bytes)
mov rax,strict qword 1 ; Full 10-byte instruction
mov rax,strict dword 1 ; 7-byte instruction
mov rax,symbol        ; 10 bytes, not known at assembly time
lea rax,[rel symbol]  ; 7 bytes, usually preferred by the ABI

```

Note that `lea rax,[rel symbol]` is position-independent, whereas `mov rax,symbol` is not. Most ABIs prefer or even require position-independent code in 64-bit mode. However, the `MOV` instruction is able to reference a symbol anywhere in the 64-bit address space, whereas `LEA` is only able to access a symbol within within 2 GB of the instruction itself (see below.)

The only instructions which take a full 64-bit *displacement* is loading or storing, using `MOV`, `AL`, `AX`, `EAX` or `RAX` (but no other registers) to an absolute 64-bit address. Since this is a relatively rarely used instruction (64-bit code generally uses relative addressing), the programmer has to explicitly declare the displacement size as `ABS QWORD`:

```

default abs

mov eax,[foo]         ; 32-bit absolute disp, sign-extended
mov eax,[a32 foo]     ; 32-bit absolute disp, zero-extended
mov eax,[qword foo]   ; 64-bit absolute disp

default rel

mov eax,[foo]         ; 32-bit relative disp
mov eax,[a32 foo]     ; d:o, address truncated to 32 bits(!)
mov eax,[qword foo]   ; error
mov eax,[abs qword foo] ; 64-bit absolute disp

```

A sign-extended absolute displacement can access from -2 GB to +2 GB; a zero-extended absolute displacement can access from 0 to 4 GB.

12.3 Interfacing to 64-bit C Programs (Unix)

On Unix, the 64-bit ABI as well as the x32 ABI (32-bit ABI with the CPU in 64-bit mode) is defined by the documents at:

<http://www.nasm.us/abi/unix64>

Although written for AT&T-syntax assembly, the concepts apply equally well for NASM-style assembly. What follows is a simplified summary.

The first six integer arguments (from the left) are passed in `RDI`, `RSI`, `RDX`, `RCX`, `R8`, and `R9`, in that order. Additional integer arguments are passed on the stack. These registers, plus `RAX`, `R10` and `R11` are destroyed by function calls, and thus are available for use by the function without saving.

Integer return values are passed in `RAX` and `RDX`, in that order.

Floating point is done using SSE registers, except for `long double`, which is 80 bits (TWORD) on most platforms (Android is one exception; there `long double` is 64 bits and treated the same as `double`.) Floating-point arguments are passed in XMM0 to XMM7; return is XMM0 and XMM1. `long double` are passed on the stack, and returned in ST0 and ST1.

All SSE and x87 registers are destroyed by function calls.

On 64-bit Unix, `long` is 64 bits.

Integer and SSE register arguments are counted separately, so for the case of

```
void foo(long a, double b, int c)
```

a is passed in RDI, b in XMM0, and c in ESI.

12.4 Interfacing to 64-bit C Programs (Win64)

The Win64 ABI is described by the document at:

<http://www.nasm.us/abi/win64>

What follows is a simplified summary.

The first four integer arguments are passed in RCX, RDX, R8 and R9, in that order. Additional integer arguments are passed on the stack. These registers, plus RAX, R10 and R11 are destroyed by function calls, and thus are available for use by the function without saving.

Integer return values are passed in RAX only.

Floating point is done using SSE registers, except for `long double`. Floating-point arguments are passed in XMM0 to XMM3; return is XMM0 only.

On Win64, `long` is 32 bits; `long long` or `_int64` is 64 bits.

Integer and SSE register arguments are counted together, so for the case of

```
void foo(long long a, double b, int c)
```

a is passed in RCX, b in XMM1, and c in R8D.

Chapter 13: Troubleshooting

This chapter describes some of the common problems that users have been known to encounter with NASM, and answers them. If you think you have found a bug in NASM, please see section E.2.

13.1 Common Problems

13.1.1 NASM Generates Inefficient Code

We sometimes get ‘bug’ reports about NASM generating inefficient, or even ‘wrong’, code on instructions such as `ADD ESP, 8`. This is a deliberate design feature, connected to predictability of output: NASM, on seeing `ADD ESP, 8`, will generate the form of the instruction which leaves room for a 32-bit offset. You need to code `ADD ESP, BYTE 8` if you want the space-efficient form of the instruction. This isn’t a bug, it’s user error: if you prefer to have NASM produce the more efficient code automatically enable optimization with the `-O` option (see section 2.1.24).

13.1.2 My Jumps are Out of Range

Similarly, people complain that when they issue conditional jumps (which are `SHORT` by default) that try to jump too far, NASM reports ‘short jump out of range’ instead of making the jumps longer.

This, again, is partly a predictability issue, but in fact has a more practical reason as well. NASM has no means of being told what type of processor the code it is generating will be run on; so it cannot decide for itself that it should generate `Jcc NEAR` type instructions, because it doesn’t know that it’s working for a 386 or above. Alternatively, it could replace the out-of-range short `JNE` instruction with a very short `JE` instruction that jumps over a `JMP NEAR`; this is a sensible solution for processors below a 386, but hardly efficient on processors which have good branch prediction *and* could have used `JNE NEAR` instead. So, once again, it’s up to the user, not the assembler, to decide what instructions should be generated. See section 2.1.24.

13.1.3 ORG Doesn’t Work

People writing boot sector programs in the `bin` format often complain that `ORG` doesn’t work the way they’d like: in order to place the `0xAA55` signature word at the end of a 512-byte boot sector, people who are used to MASM tend to code

```
ORG 0

; some boot sector code

ORG 510
DW 0xAA55
```

This is not the intended use of the `ORG` directive in NASM, and will not work. The correct way to solve this problem in NASM is to use the `TIMES` directive, like this:

```
ORG 0

; some boot sector code

TIMES 510-($-$$) DB 0
DW 0xAA55
```

The `TIMES` directive will insert exactly enough zero bytes into the output to move the assembly point up to 510. This method also has the advantage that if you accidentally fill your boot sector too full, NASM will catch the problem at assembly time and report it, so you won’t end up with a boot sector that you have to disassemble to find out what’s wrong with it.

13.1.4 TIMES Doesn't Work

The other common problem with the above code is people who write the TIMES line as

```
TIMES 510-$ DB 0
```

by reasoning that \$ should be a pure number, just like 510, so the difference between them is also a pure number and can happily be fed to TIMES.

NASM is a *modular* assembler: the various component parts are designed to be easily separable for re-use, so they don't exchange information unnecessarily. In consequence, the `bin` output format, even though it has been told by the `ORG` directive that the `.text` section should start at 0, does not pass that information back to the expression evaluator. So from the evaluator's point of view, \$ isn't a pure number: it's an offset from a section base. Therefore the difference between \$ and 510 is also not a pure number, but involves a section base. Values involving section bases cannot be passed as arguments to TIMES.

The solution, as in the previous section, is to code the TIMES line in the form

```
TIMES 510-($-$$) DB 0
```

in which \$ and \$\$ are offsets from the same section base, and so their difference is a pure number. This will solve the problem and generate sensible code.

Appendix A: Ndisasm

The Netwide Disassembler, NDISASM

A.1 Introduction

The Netwide Disassembler is a small companion program to the Netwide Assembler, NASM. It seemed a shame to have an x86 assembler, complete with a full instruction table, and not make as much use of it as possible, so here's a disassembler which shares the instruction table (and some other bits of code) with NASM.

The Netwide Disassembler does nothing except to produce disassemblies of *binary* source files. NDISASM does not have any understanding of object file formats, like objdump, and it will not understand DOS .EXE files like debug will. It just disassembles.

A.2 Running NDISASM

To disassemble a file, you will typically use a command of the form

```
ndisasm -b {16|32|64} filename
```

NDISASM can disassemble 16-, 32- or 64-bit code equally easily, provided of course that you remember to specify which it is to work with. If no `-b` switch is present, NDISASM works in 16-bit mode by default. The `-u` switch (for USE32) also invokes 32-bit mode.

Two more command line options are `-r` which reports the version number of NDISASM you are running, and `-h` which gives a short summary of command line options.

A.2.1 COM Files: Specifying an Origin

To disassemble a DOS .COM file correctly, a disassembler must assume that the first instruction in the file is loaded at address `0x100`, rather than at zero. NDISASM, which assumes by default that any file you give it is loaded at zero, will therefore need to be informed of this.

The `-o` option allows you to declare a different origin for the file you are disassembling. Its argument may be expressed in any of the NASM numeric formats: decimal by default, if it begins with '\$' or '0x' or ends in 'H' it's hex, if it ends in 'Q' it's octal, and if it ends in 'B' it's binary.

Hence, to disassemble a .COM file:

```
ndisasm -o100h filename.com
```

will do the trick.

A.2.2 Code Following Data: Synchronisation

Suppose you are disassembling a file which contains some data which isn't machine code, and *then* contains some machine code. NDISASM will faithfully plough through the data section, producing machine instructions wherever it can (although most of them will look bizarre, and some may have unusual prefixes, e.g. 'FS OR AX, 0x240A'), and generating 'DB' instructions ever so often if it's totally stumped. Then it will reach the code section.

Supposing NDISASM has just finished generating a strange machine instruction from part of the data section, and its file position is now one byte *before* the beginning of the code section. It's entirely possible that another spurious instruction will get generated, starting with the final byte of the data section, and then the correct first instruction in the code section will not be seen because the starting point skipped over it. This isn't really ideal.

To avoid this, you can specify a ‘synchronisation’ point, or indeed as many synchronisation points as you like (although NDISASM can only handle 2147483647 sync points internally). The definition of a sync point is this: NDISASM guarantees to hit sync points exactly during disassembly. If it is thinking about generating an instruction which would cause it to jump over a sync point, it will discard that instruction and output a ‘db’ instead. So it *will* start disassembly exactly from the sync point, and so you *will* see all the instructions in your code section.

Sync points are specified using the `-s` option: they are measured in terms of the program origin, not the file position. So if you want to synchronize after 32 bytes of a .COM file, you would have to do

```
ndisasm -o100h -s120h file.com
```

rather than

```
ndisasm -o100h -s20h file.com
```

As stated above, you can specify multiple sync markers if you need to, just by repeating the `-s` option.

A.2.3 Mixed Code and Data: Automatic (Intelligent) Synchronisation

Suppose you are disassembling the boot sector of a DOS floppy (maybe it has a virus, and you need to understand the virus so that you know what kinds of damage it might have done you). Typically, this will contain a JMP instruction, then some data, then the rest of the code. So there is a very good chance of NDISASM being *misaligned* when the data ends and the code begins. Hence a sync point is needed.

On the other hand, why should you have to specify the sync point manually? What you’d do in order to find where the sync point would be, surely, would be to read the JMP instruction, and then to use its target address as a sync point. So can NDISASM do that for you?

The answer, of course, is yes: using either of the synonymous switches `-a` (for automatic sync) or `-i` (for intelligent sync) will enable auto-sync mode. Auto-sync mode automatically generates a sync point for any forward-referring PC-relative jump or call instruction that NDISASM encounters. (Since NDISASM is one-pass, if it encounters a PC-relative jump whose target has already been processed, there isn’t much it can do about it...)

Only PC-relative jumps are processed, since an absolute jump is either through a register (in which case NDISASM doesn’t know what the register contains) or involves a segment address (in which case the target code isn’t in the same segment that NDISASM is working in, and so the sync point can’t be placed anywhere useful).

For some kinds of file, this mechanism will automatically put sync points in all the right places, and save you from having to place any sync points manually. However, it should be stressed that auto-sync mode is *not* guaranteed to catch all the sync points, and you may still have to place some manually.

Auto-sync mode doesn’t prevent you from declaring manual sync points: it just adds automatically generated ones to the ones you provide. It’s perfectly feasible to specify `-i` *and* some `-s` options.

Another caveat with auto-sync mode is that if, by some unpleasant fluke, something in your data section should disassemble to a PC-relative call or jump instruction, NDISASM may obediently place a sync point in a totally random place, for example in the middle of one of the instructions in your code section. So you may end up with a wrong disassembly even if you use auto-sync. Again, there isn’t much I can do about this. If you have problems, you’ll have to use manual sync points, or use the `-k` option (documented below) to suppress disassembly of the data area.

A.2.4 Other Options

The `-e` option skips a header on the file, by ignoring the first N bytes. This means that the header is *not* counted towards the disassembly offset: if you give `-e10 -o10`, disassembly will start at byte 10 in the file, and this will be given offset 10, not 20.

The `-k` option is provided with two comma-separated numeric arguments, the first of which is an assembly offset and the second is a number of bytes to skip. This *will* count the skipped bytes towards the assembly offset: its use is to suppress disassembly of a data section which wouldn't contain anything you wanted to see anyway.

Appendix B: Instruction List

B.1 Introduction

The following sections show the instructions which NASM currently supports. For each instruction, there is a separate entry for each supported addressing mode. The third column shows the processor type in which the instruction was introduced and, when appropriate, one or more usage flags.

B.1.1 Special instructions (pseudo-ops)

DB		
DW		
DD		
DQ		
DT		
DO		
DY		
DZ		
RESB	imm	8086
RESW	imm	8086
RESD	imm	8086
RESQ	imm	8086
REST	imm	8086
RESO	imm	8086
RESY	imm	8086
RESZ	imm	8086
INCBIN		

B.1.2 Conventional instructions

AAA		8086, NOLONG
AAD		8086, NOLONG
AAD	imm	8086, NOLONG
AAM		8086, NOLONG
AAM	imm	8086, NOLONG
AAS		8086, NOLONG
ADC	mem, reg8	8086, LOCK
ADC	reg8, reg8	8086
ADC	mem, reg16	8086, LOCK
ADC	reg16, reg16	8086
ADC	mem, reg32	386, LOCK
ADC	reg32, reg32	386
ADC	mem, reg64	X64, LOCK
ADC	reg64, reg64	X64
ADC	reg8, mem	8086
ADC	reg8, reg8	8086
ADC	reg16, mem	8086
ADC	reg16, reg16	8086
ADC	reg32, mem	386
ADC	reg32, reg32	386
ADC	reg64, mem	X64
ADC	reg64, reg64	X64
ADC	rm16, imm8	8086, LOCK

ADC	rm32,imm8	386, LOCK
ADC	rm64,imm8	X64, LOCK
ADC	reg_al,imm	8086
ADC	reg_ax,sbytedword	8086,ND
ADC	reg_ax,imm	8086
ADC	reg_eax,sbytedword	386,ND
ADC	reg_eax,imm	386
ADC	reg_rax,sbytedword	X64,ND
ADC	reg_rax,imm	X64
ADC	rm8,imm	8086, LOCK
ADC	rm16,sbytedword	8086, LOCK,ND
ADC	rm16,imm	8086, LOCK
ADC	rm32,sbytedword	386, LOCK,ND
ADC	rm32,imm	386, LOCK
ADC	rm64,sbytedword	X64, LOCK,ND
ADC	rm64,imm	X64, LOCK
ADC	mem,imm8	8086, LOCK,ND
ADC	mem,sbytedword16	8086, LOCK,ND
ADC	mem,imm16	8086, LOCK
ADC	mem,sbytedword32	386, LOCK,ND
ADC	mem,imm32	386, LOCK
ADC	rm8,imm	8086, LOCK,ND,NOLONG
ADD	mem,reg8	8086, LOCK
ADD	reg8,reg8	8086
ADD	mem,reg16	8086, LOCK
ADD	reg16,reg16	8086
ADD	mem,reg32	386, LOCK
ADD	reg32,reg32	386
ADD	mem,reg64	X64, LOCK
ADD	reg64,reg64	X64
ADD	reg8,mem	8086
ADD	reg8,reg8	8086
ADD	reg16,mem	8086
ADD	reg16,reg16	8086
ADD	reg32,mem	386
ADD	reg32,reg32	386
ADD	reg64,mem	X64
ADD	reg64,reg64	X64
ADD	rm16,imm8	8086, LOCK
ADD	rm32,imm8	386, LOCK
ADD	rm64,imm8	X64, LOCK
ADD	reg_al,imm	8086
ADD	reg_ax,sbytedword	8086,ND
ADD	reg_ax,imm	8086
ADD	reg_eax,sbytedword	386,ND
ADD	reg_eax,imm	386
ADD	reg_rax,sbytedword	X64,ND
ADD	reg_rax,imm	X64
ADD	rm8,imm	8086, LOCK
ADD	rm16,sbytedword	8086, LOCK,ND
ADD	rm16,imm	8086, LOCK
ADD	rm32,sbytedword	386, LOCK,ND
ADD	rm32,imm	386, LOCK
ADD	rm64,sbytedword	X64, LOCK,ND

ADD	rm64,imm	X64,LOCK
ADD	mem,imm8	8086,LOCK
ADD	mem,sbytedword16	8086,LOCK,ND
ADD	mem,imm16	8086,LOCK
ADD	mem,sbytedword32	386,LOCK,ND
ADD	mem,imm32	386,LOCK
ADD	rm8,imm	8086,LOCK,ND,NOLONG
AND	mem,reg8	8086,LOCK
AND	reg8,reg8	8086
AND	mem,reg16	8086,LOCK
AND	reg16,reg16	8086
AND	mem,reg32	386,LOCK
AND	reg32,reg32	386
AND	mem,reg64	X64,LOCK
AND	reg64,reg64	X64
AND	reg8,mem	8086
AND	reg8,reg8	8086
AND	reg16,mem	8086
AND	reg16,reg16	8086
AND	reg32,mem	386
AND	reg32,reg32	386
AND	reg64,mem	X64
AND	reg64,reg64	X64
AND	rm16,imm8	8086,LOCK
AND	rm32,imm8	386,LOCK
AND	rm64,imm8	X64,LOCK
AND	reg_al,imm	8086
AND	reg_ax,sbytedword	8086,ND
AND	reg_ax,imm	8086
AND	reg_eax,sbytedword	386,ND
AND	reg_eax,imm	386
AND	reg_rax,sbytedword	X64,ND
AND	reg_rax,imm	X64
AND	rm8,imm	8086,LOCK
AND	rm16,sbytedword	8086,LOCK,ND
AND	rm16,imm	8086,LOCK
AND	rm32,sbytedword	386,LOCK,ND
AND	rm32,imm	386,LOCK
AND	rm64,sbytedword	X64,LOCK,ND
AND	rm64,imm	X64,LOCK
AND	mem,imm8	8086,LOCK
AND	mem,sbytedword16	8086,LOCK,ND
AND	mem,imm16	8086,LOCK
AND	mem,sbytedword32	386,LOCK,ND
AND	mem,imm32	386,LOCK
AND	rm8,imm	8086,LOCK,ND,NOLONG
ARPL	mem,reg16	286,PROT,NOLONG
ARPL	reg16,reg16	286,PROT,NOLONG
BB0_RESET		PENT,CYRIX,ND,OBSOLETE
BB1_RESET		PENT,CYRIX,ND,OBSOLETE
BOUND	reg16,mem	186,NOLONG
BOUND	reg32,mem	386,NOLONG
BSF	reg16,mem	386
BSF	reg16,reg16	386

BSF	reg32,mem	386
BSF	reg32,reg32	386
BSF	reg64,mem	X64
BSF	reg64,reg64	X64
BSR	reg16,mem	386
BSR	reg16,reg16	386
BSR	reg32,mem	386
BSR	reg32,reg32	386
BSR	reg64,mem	X64
BSR	reg64,reg64	X64
BSWAP	reg32	486
BSWAP	reg64	X64
BT	mem,reg16	386
BT	reg16,reg16	386
BT	mem,reg32	386
BT	reg32,reg32	386
BT	mem,reg64	X64
BT	reg64,reg64	X64
BT	rm16,imm	386
BT	rm32,imm	386
BT	rm64,imm	X64
BTC	mem,reg16	386, LOCK
BTC	reg16,reg16	386
BTC	mem,reg32	386, LOCK
BTC	reg32,reg32	386
BTC	mem,reg64	X64, LOCK
BTC	reg64,reg64	X64
BTC	rm16,imm	386, LOCK
BTC	rm32,imm	386, LOCK
BTC	rm64,imm	X64, LOCK
BTR	mem,reg16	386, LOCK
BTR	reg16,reg16	386
BTR	mem,reg32	386, LOCK
BTR	reg32,reg32	386
BTR	mem,reg64	X64, LOCK
BTR	reg64,reg64	X64
BTR	rm16,imm	386, LOCK
BTR	rm32,imm	386, LOCK
BTR	rm64,imm	X64, LOCK
BTS	mem,reg16	386, LOCK
BTS	reg16,reg16	386
BTS	mem,reg32	386, LOCK
BTS	reg32,reg32	386
BTS	mem,reg64	X64, LOCK
BTS	reg64,reg64	X64
BTS	rm16,imm	386, LOCK
BTS	rm32,imm	386, LOCK
BTS	rm64,imm	X64, LOCK
CALL	imm	8086, BND
CALL	imm near	8086, ND, BND
CALL	imm far	8086, ND, NOLONG
CALL	imm16	8086, NOLONG, BND
CALL	imm16 near	8086, ND, NOLONG, BND
CALL	imm16 far	8086, ND, NOLONG

CALL	imm32	386,NOLONG,BND
CALL	imm32 near	386,ND,NOLONG,BND
CALL	imm32 far	386,ND,NOLONG
CALL	imm64	X64,BND
CALL	imm64 near	X64,ND,BND
CALL	imm:imm	8086,NOLONG
CALL	imm16:imm	8086,NOLONG
CALL	imm:imm16	8086,NOLONG
CALL	imm32:imm	386,NOLONG
CALL	imm:imm32	386,NOLONG
CALL	mem far	8086,NOLONG
CALL	mem far	X64
CALL	mem16 far	8086
CALL	mem32 far	386
CALL	mem64 far	X64
CALL	mem near	8086,ND,BND
CALL	rm16 near	8086,NOLONG,ND,BND
CALL	rm32 near	386,NOLONG,ND,BND
CALL	rm64 near	X64,ND,BND
CALL	mem	8086,BND
CALL	rm16	8086,NOLONG,BND
CALL	rm32	386,NOLONG,BND
CALL	rm64	X64,BND
CBW		8086
CDQ		386
CDQE		X64
CLC		8086
CLD		8086
CLI		8086
CLTS		286,PRIV
CMC		8086
CMP	mem,reg8	8086
CMP	reg8,reg8	8086
CMP	mem,reg16	8086
CMP	reg16,reg16	8086
CMP	mem,reg32	386
CMP	reg32,reg32	386
CMP	mem,reg64	X64
CMP	reg64,reg64	X64
CMP	reg8,mem	8086
CMP	reg8,reg8	8086
CMP	reg16,mem	8086
CMP	reg16,reg16	8086
CMP	reg32,mem	386
CMP	reg32,reg32	386
CMP	reg64,mem	X64
CMP	reg64,reg64	X64
CMP	rm16,imm8	8086
CMP	rm32,imm8	386
CMP	rm64,imm8	X64
CMP	reg_al,imm	8086
CMP	reg_ax,sbytedword	8086,ND
CMP	reg_ax,imm	8086
CMP	reg_eax,sbytedword	386,ND

CMP	reg_eax,imm	386
CMP	reg_rax,sbytedword	X64,ND
CMP	reg_rax,imm	X64
CMP	rm8,imm	8086
CMP	rm16,sbytedword	8086,ND
CMP	rm16,imm	8086
CMP	rm32,sbytedword	386,ND
CMP	rm32,imm	386
CMP	rm64,sbytedword	X64,ND
CMP	rm64,imm	X64
CMP	mem,imm8	8086
CMP	mem,sbytedword16	8086,ND
CMP	mem,imm16	8086
CMP	mem,sbytedword32	386,ND
CMP	mem,imm32	386
CMP	rm8,imm	8086,ND,NOLONG
CMPSB		8086
CMPSD		386
CMPSQ		X64
CMPSW		8086
CMPXCHG	mem,reg8	PENT,LOCK
CMPXCHG	reg8,reg8	PENT
CMPXCHG	mem,reg16	PENT,LOCK
CMPXCHG	reg16,reg16	PENT
CMPXCHG	mem,reg32	PENT,LOCK
CMPXCHG	reg32,reg32	PENT
CMPXCHG	mem,reg64	X64,LOCK
CMPXCHG	reg64,reg64	X64
CMPXCHG486	mem,reg8	486,UNDOC,ND,LOCK,OBSOLETE
CMPXCHG486	reg8,reg8	486,UNDOC,ND,OBSOLETE
CMPXCHG486	mem,reg16	486,UNDOC,ND,LOCK,OBSOLETE
CMPXCHG486	reg16,reg16	486,UNDOC,ND,OBSOLETE
CMPXCHG486	mem,reg32	486,UNDOC,ND,LOCK,OBSOLETE
CMPXCHG486	reg32,reg32	486,UNDOC,ND,OBSOLETE
CMPXCHG8B	mem64	PENT,LOCK
CMPXCHG16B	mem128	X64,LOCK
CPUID		PENT
CPU_READ		PENT,CYRIX
CPU_WRITE		PENT,CYRIX
CQO		X64
CWD		8086
CWDE		386
DAA		8086,NOLONG
DAS		8086,NOLONG
DEC	reg16	8086,NOLONG
DEC	reg32	386,NOLONG
DEC	rm8	8086,LOCK
DEC	rm16	8086,LOCK
DEC	rm32	386,LOCK
DEC	rm64	X64,LOCK
DIV	rm8	8086
DIV	rm16	8086
DIV	rm32	386
DIV	rm64	X64

DMINT		P6,CYRIX
EMMS		PENT,MMX
ENTER	imm,imm	186
EQU	imm	8086
EQU	imm:imm	8086
F2XM1		8086,FPU
FABS		8086,FPU
FADD	mem32	8086,FPU
FADD	mem64	8086,FPU
FADD	fpureg to	8086,FPU
FADD	fpureg	8086,FPU
FADD	fpureg,fpu0	8086,FPU
FADD	fpu0,fpureg	8086,FPU
FADD		8086,FPU,ND
FADDP	fpureg	8086,FPU
FADDP	fpureg,fpu0	8086,FPU
FADDP		8086,FPU,ND
FBLD	mem80	8086,FPU
FBLD	mem	8086,FPU
FBSTP	mem80	8086,FPU
FBSTP	mem	8086,FPU
FCHS		8086,FPU
FCLEX		8086,FPU
FCMOVB	fpureg	P6,FPU
FCMOVB	fpu0,fpureg	P6,FPU
FCMOVB		P6,FPU,ND
FCMOVBE	fpureg	P6,FPU
FCMOVBE	fpu0,fpureg	P6,FPU
FCMOVBE		P6,FPU,ND
FCMOVE	fpureg	P6,FPU
FCMOVE	fpu0,fpureg	P6,FPU
FCMOVE		P6,FPU,ND
FCMOVNB	fpureg	P6,FPU
FCMOVNB	fpu0,fpureg	P6,FPU
FCMOVNB		P6,FPU,ND
FCMOVNBE	fpureg	P6,FPU
FCMOVNBE	fpu0,fpureg	P6,FPU
FCMOVNBE		P6,FPU,ND
FCMOVNE	fpureg	P6,FPU
FCMOVNE	fpu0,fpureg	P6,FPU
FCMOVNE		P6,FPU,ND
FCMOVNU	fpureg	P6,FPU
FCMOVNU	fpu0,fpureg	P6,FPU
FCMOVNU		P6,FPU,ND
FCMOVU	fpureg	P6,FPU
FCMOVU	fpu0,fpureg	P6,FPU
FCMOVU		P6,FPU,ND
FCOM	mem32	8086,FPU
FCOM	mem64	8086,FPU
FCOM	fpureg	8086,FPU
FCOM	fpu0,fpureg	8086,FPU
FCOM		8086,FPU,ND
FCOMI	fpureg	P6,FPU
FCOMI	fpu0,fpureg	P6,FPU

FCOMI		P6, FPU, ND
FCOMIP	fpureg	P6, FPU
FCOMIP	fpu0, fpureg	P6, FPU
FCOMIP		P6, FPU, ND
FCOMP	mem32	8086, FPU
FCOMP	mem64	8086, FPU
FCOMP	fpureg	8086, FPU
FCOMP	fpu0, fpureg	8086, FPU
FCOMP		8086, FPU, ND
FCOMPP		8086, FPU
FCOS		386, FPU
FDECSTP		8086, FPU
FDISI		8086, FPU
FDIV	mem32	8086, FPU
FDIV	mem64	8086, FPU
FDIV	fpureg to	8086, FPU
FDIV	fpureg	8086, FPU
FDIV	fpureg, fpu0	8086, FPU
FDIV	fpu0, fpureg	8086, FPU
FDIV		8086, FPU, ND
FDIVP	fpureg	8086, FPU
FDIVP	fpureg, fpu0	8086, FPU
FDIVP		8086, FPU, ND
FDIVR	mem32	8086, FPU
FDIVR	mem64	8086, FPU
FDIVR	fpureg to	8086, FPU
FDIVR	fpureg, fpu0	8086, FPU
FDIVR	fpureg	8086, FPU
FDIVR	fpu0, fpureg	8086, FPU
FDIVR		8086, FPU, ND
FDIVRP	fpureg	8086, FPU
FDIVRP	fpureg, fpu0	8086, FPU
FDIVRP		8086, FPU, ND
FEMMS		PENT, 3DNOW
FENI		8086, FPU
FFREE	fpureg	8086, FPU
FFREE		8086, FPU
FFREEP	fpureg	286, FPU, UNDOC
FFREEP		286, FPU, UNDOC
FIADD	mem32	8086, FPU
FIADD	mem16	8086, FPU
FICOM	mem32	8086, FPU
FICOM	mem16	8086, FPU
FICOMP	mem32	8086, FPU
FICOMP	mem16	8086, FPU
FIDIV	mem32	8086, FPU
FIDIV	mem16	8086, FPU
FIDIVR	mem32	8086, FPU
FIDIVR	mem16	8086, FPU
FILD	mem32	8086, FPU
FILD	mem16	8086, FPU
FILD	mem64	8086, FPU
FIMUL	mem32	8086, FPU
FIMUL	mem16	8086, FPU

FINCSTP		8086, FPU
FINIT		8086, FPU
FIST	mem32	8086, FPU
FIST	mem16	8086, FPU
FISTP	mem32	8086, FPU
FISTP	mem16	8086, FPU
FISTP	mem64	8086, FPU
FISTTP	mem16	PRESCOTT, FPU
FISTTP	mem32	PRESCOTT, FPU
FISTTP	mem64	PRESCOTT, FPU
FISUB	mem32	8086, FPU
FISUB	mem16	8086, FPU
FISUBR	mem32	8086, FPU
FISUBR	mem16	8086, FPU
FLD	mem32	8086, FPU
FLD	mem64	8086, FPU
FLD	mem80	8086, FPU
FLD	fpureg	8086, FPU
FLD		8086, FPU, ND
FLD1		8086, FPU
FLDCW	mem	8086, FPU, SW
FLDENV	mem	8086, FPU
FLDL2E		8086, FPU
FLDL2T		8086, FPU
FLDLG2		8086, FPU
FLDLN2		8086, FPU
FLDPI		8086, FPU
FLDZ		8086, FPU
FMUL	mem32	8086, FPU
FMUL	mem64	8086, FPU
FMUL	fpureg to	8086, FPU
FMUL	fpureg, fpu0	8086, FPU
FMUL	fpureg	8086, FPU
FMUL	fpu0, fpureg	8086, FPU
FMUL		8086, FPU, ND
FMULP	fpureg	8086, FPU
FMULP	fpureg, fpu0	8086, FPU
FMULP		8086, FPU, ND
FNCLEX		8086, FPU
FNDISI		8086, FPU
FNENI		8086, FPU
FNINIT		8086, FPU
FNOP		8086, FPU
FNSAVE	mem	8086, FPU
FNSTCW	mem	8086, FPU, SW
FNSTENV	mem	8086, FPU
FNSTSW	mem	8086, FPU, SW
FNSTSW	reg_ax	286, FPU
FPATAN		8086, FPU
FPREM		8086, FPU
FPREM1		386, FPU
FPTAN		8086, FPU
FRNDINT		8086, FPU
FRSTOR	mem	8086, FPU

FSAVE	mem	8086, FPU
FSCALE		8086, FPU
FSETPM		286, FPU
FSIN		386, FPU
FSINCOS		386, FPU
FSQRT		8086, FPU
FST	mem32	8086, FPU
FST	mem64	8086, FPU
FST	fpureg	8086, FPU
FST		8086, FPU, ND
FSTCW	mem	8086, FPU, SW
FSTENV	mem	8086, FPU
FSTP	mem32	8086, FPU
FSTP	mem64	8086, FPU
FSTP	mem80	8086, FPU
FSTP	fpureg	8086, FPU
FSTP		8086, FPU, ND
FSTSW	mem	8086, FPU, SW
FSTSW	reg_ax	286, FPU
FSUB	mem32	8086, FPU
FSUB	mem64	8086, FPU
FSUB	fpureg to	8086, FPU
FSUB	fpureg, fpu0	8086, FPU
FSUB	fpureg	8086, FPU
FSUB	fpu0, fpureg	8086, FPU
FSUB		8086, FPU, ND
FSUBP	fpureg	8086, FPU
FSUBP	fpureg, fpu0	8086, FPU
FSUBP		8086, FPU, ND
FSUBR	mem32	8086, FPU
FSUBR	mem64	8086, FPU
FSUBR	fpureg to	8086, FPU
FSUBR	fpureg, fpu0	8086, FPU
FSUBR	fpureg	8086, FPU
FSUBR	fpu0, fpureg	8086, FPU
FSUBR		8086, FPU, ND
FSUBRP	fpureg	8086, FPU
FSUBRP	fpureg, fpu0	8086, FPU
FSUBRP		8086, FPU, ND
FTST		8086, FPU
FUCOM	fpureg	386, FPU
FUCOM	fpu0, fpureg	386, FPU
FUCOM		386, FPU, ND
FUCOMI	fpureg	P6, FPU
FUCOMI	fpu0, fpureg	P6, FPU
FUCOMI		P6, FPU, ND
FUCOMIP	fpureg	P6, FPU
FUCOMIP	fpu0, fpureg	P6, FPU
FUCOMIP		P6, FPU, ND
FUCOMP	fpureg	386, FPU
FUCOMP	fpu0, fpureg	386, FPU
FUCOMP		386, FPU, ND
FUCOMPP		386, FPU
FXAM		8086, FPU

FXCH	fpureg	8086, FPU
FXCH	fpureg, fpu0	8086, FPU
FXCH	fpu0, fpureg	8086, FPU
FXCH		8086, FPU, ND
FXTRACT		8086, FPU
FYL2X		8086, FPU
FYL2XP1		8086, FPU
HLT		8086, PRIV
IBTS	mem, reg16	386, SW, UNDOC, ND, OBSOLETE
IBTS	reg16, reg16	386, UNDOC, ND, OBSOLETE
IBTS	mem, reg32	386, SD, UNDOC, ND, OBSOLETE
IBTS	reg32, reg32	386, UNDOC, ND, OBSOLETE
ICEBP		386, ND
IDIV	rm8	8086
IDIV	rm16	8086
IDIV	rm32	386
IDIV	rm64	X64
IMUL	rm8	8086
IMUL	rm16	8086
IMUL	rm32	386
IMUL	rm64	X64
IMUL	reg16, mem	386
IMUL	reg16, reg16	386
IMUL	reg32, mem	386
IMUL	reg32, reg32	386
IMUL	reg64, mem	X64
IMUL	reg64, reg64	X64
IMUL	reg16, mem, imm8	186
IMUL	reg16, mem, sbytedword	186, ND
IMUL	reg16, mem, imm16	186
IMUL	reg16, mem, imm	186, ND
IMUL	reg16, reg16, imm8	186
IMUL	reg16, reg16, sbytedword	186, ND
IMUL	reg16, reg16, imm16	186
IMUL	reg16, reg16, imm	186, ND
IMUL	reg32, mem, imm8	386
IMUL	reg32, mem, sbytedword	386, ND
IMUL	reg32, mem, imm32	386
IMUL	reg32, mem, imm	386, ND
IMUL	reg32, reg32, imm8	386
IMUL	reg32, reg32, sbytedword	386, ND
IMUL	reg32, reg32, imm32	386
IMUL	reg32, reg32, imm	386, ND
IMUL	reg64, mem, imm8	X64
IMUL	reg64, mem, sbytedword	X64, ND
IMUL	reg64, mem, imm32	X64
IMUL	reg64, mem, imm	X64, ND
IMUL	reg64, reg64, imm8	X64
IMUL	reg64, reg64, sbytedword	X64, ND
IMUL	reg64, reg64, imm32	X64
IMUL	reg64, reg64, imm	X64, ND
IMUL	reg16, imm8	186
IMUL	reg16, sbytedword	186, ND
IMUL	reg16, imm16	186

IMUL	reg16,imm	186,ND
IMUL	reg32,imm8	386
IMUL	reg32,sbytedword	386,ND
IMUL	reg32,imm32	386
IMUL	reg32,imm	386,ND
IMUL	reg64,imm8	X64
IMUL	reg64,sbytedword	X64,ND
IMUL	reg64,imm32	X64
IMUL	reg64,imm	X64,ND
IN	reg_al,imm	8086
IN	reg_ax,imm	8086
IN	reg_eax,imm	386
IN	reg_al,reg_dx	8086
IN	reg_ax,reg_dx	8086
IN	reg_eax,reg_dx	386
INC	reg16	8086,NOLONG
INC	reg32	386,NOLONG
INC	rm8	8086,LOCK
INC	rm16	8086,LOCK
INC	rm32	386,LOCK
INC	rm64	X64,LOCK
INSB		186
INSD		386
INSW		186
INT	imm	8086
INT01		386,ND
INT1		386
INT03		8086,ND
INT3		8086
INTO		8086,NOLONG
INVD		486,PRIV
INVPCID	reg32,mem128	INVPCID,PRIV,NOLONG
INVPCID	reg64,mem128	INVPCID,PRIV, LONG
INVLPG	mem	486,PRIV
INVLPGA	reg_ax,reg_ecx	X86_64,AMD,NOLONG
INVLPGA	reg_eax,reg_ecx	X86_64,AMD
INVLPGA	reg_rax,reg_ecx	X64,AMD
INVLPGA		X86_64,AMD
IRET		8086
IRETD		386
IRETQ		X64
IRETW		8086
JCXZ	imm	8086,NOLONG
JECXZ	imm	386
JRCXZ	imm	X64
JMP	imm short	8086
JMP	imm	8086,ND
JMP	imm	8086,BND
JMP	imm near	8086,ND,BND
JMP	imm far	8086,ND,NOLONG
JMP	imm16	8086,NOLONG,BND
JMP	imm16 near	8086,ND,NOLONG,BND
JMP	imm16 far	8086,ND,NOLONG
JMP	imm32	386,NOLONG,BND

JMP	imm32 near	386,ND,NOLONG,BND
JMP	imm32 far	386,ND,NOLONG
JMP	imm64	X64,BND
JMP	imm64 near	X64,ND,BND
JMP	imm:imm	8086,NOLONG
JMP	imm16:imm	8086,NOLONG
JMP	imm:imm16	8086,NOLONG
JMP	imm32:imm	386,NOLONG
JMP	imm:imm32	386,NOLONG
JMP	mem far	8086,NOLONG
JMP	mem far	X64
JMP	mem16 far	8086
JMP	mem32 far	386
JMP	mem64 far	X64
JMP	mem near	8086,ND,BND
JMP	rm16 near	8086,NOLONG,ND,BND
JMP	rm32 near	386,NOLONG,ND,BND
JMP	rm64 near	X64,ND,BND
JMP	mem	8086,BND
JMP	rm16	8086,NOLONG,BND
JMP	rm32	386,NOLONG,BND
JMP	rm64	X64,BND
JMPE	imm	IA64
JMPE	imm16	IA64
JMPE	imm32	IA64
JMPE	rm16	IA64
JMPE	rm32	IA64
LAHF		8086
LAR	reg16,mem	286,PROT,SW
LAR	reg16,reg16	286,PROT
LAR	reg16,reg32	386,PROT
LAR	reg16,reg64	X64,PROT,ND
LAR	reg32,mem	386,PROT,SW
LAR	reg32,reg16	386,PROT
LAR	reg32,reg32	386,PROT
LAR	reg32,reg64	X64,PROT,ND
LAR	reg64,mem	X64,PROT,SW
LAR	reg64,reg16	X64,PROT
LAR	reg64,reg32	X64,PROT
LAR	reg64,reg64	X64,PROT
LDS	reg16,mem	8086,NOLONG
LDS	reg32,mem	386,NOLONG
LEA	reg16,mem	8086,ANYSIZE
LEA	reg32,mem	386,ANYSIZE
LEA	reg64,mem	X64,ANYSIZE
LEA	reg16,imm	8086,ND,ANYSIZE
LEA	reg32,imm	386,ND,ANYSIZE
LEA	reg64,imm	X64,ND,ANYSIZE
LEAVE		186
LES	reg16,mem	8086,NOLONG
LES	reg32,mem	386,NOLONG
LFENCE		X64,AMD
LFS	reg16,mem	386
LFS	reg32,mem	386

LFS	reg64,mem	X64
LGDT	mem	286,PRIV
LGS	reg16,mem	386
LGS	reg32,mem	386
LGS	reg64,mem	X64
LIDT	mem	286,PRIV
LLDT	mem	286,PROT,PRIV
LLDT	mem16	286,PROT,PRIV
LLDT	reg16	286,PROT,PRIV
LMSW	mem	286,PRIV
LMSW	mem16	286,PRIV
LMSW	reg16	286,PRIV
LOADALL		386,UNDOC,ND,OBSOLETE
LOADALL286		286,UNDOC,ND,OBSOLETE
LODSB		8086
LODSD		386
LODSQ		X64
LODSW		8086
LOOP	imm	8086
LOOP	imm,reg_cx	8086,NOLONG
LOOP	imm,reg_ecx	386
LOOP	imm,reg_rcx	X64
LOOPE	imm	8086
LOOPE	imm,reg_cx	8086,NOLONG
LOOPE	imm,reg_ecx	386
LOOPE	imm,reg_rcx	X64
LOOPNE	imm	8086
LOOPNE	imm,reg_cx	8086,NOLONG
LOOPNE	imm,reg_ecx	386
LOOPNE	imm,reg_rcx	X64
LOOPNZ	imm	8086
LOOPNZ	imm,reg_cx	8086,NOLONG
LOOPNZ	imm,reg_ecx	386
LOOPNZ	imm,reg_rcx	X64
LOOPZ	imm	8086
LOOPZ	imm,reg_cx	8086,NOLONG
LOOPZ	imm,reg_ecx	386
LOOPZ	imm,reg_rcx	X64
LSL	reg16,mem	286,PROT,SW
LSL	reg16,reg16	286,PROT
LSL	reg16,reg32	386,PROT
LSL	reg16,reg64	X64,PROT,ND
LSL	reg32,mem	386,PROT,SW
LSL	reg32,reg16	386,PROT
LSL	reg32,reg32	386,PROT
LSL	reg32,reg64	X64,PROT,ND
LSL	reg64,mem	X64,PROT,SW
LSL	reg64,reg16	X64,PROT
LSL	reg64,reg32	X64,PROT
LSL	reg64,reg64	X64,PROT
LSS	reg16,mem	386
LSS	reg32,mem	386
LSS	reg64,mem	X64
LTR	mem	286,PROT,PRIV

LTR	mem16	286,PROT,PRIV
LTR	reg16	286,PROT,PRIV
MFENCE		X64,AMD
MONITOR		PRESCOTT
MONITOR	reg_eax,reg_ecx,reg_edx	PRESCOTT,NOLONG,ND
MONITOR	reg_rax,reg_ecx,reg_edx	X64,ND
MONITORX		AMD
MONITORX	reg_rax,reg_ecx,reg_edx	X64,AMD,ND
MONITORX	reg_eax,reg_ecx,reg_edx	AMD,ND
MONITORX	reg_ax,reg_ecx,reg_edx	AMD,ND
MOV	mem,reg_sreg	8086,SW
MOV	reg16,reg_sreg	8086
MOV	reg32,reg_sreg	386
MOV	reg64,reg_sreg	X64,OPT,ND
MOV	rm64,reg_sreg	X64
MOV	reg_sreg,mem	8086,SW
MOV	reg_sreg,reg16	8086,OPT,ND
MOV	reg_sreg,reg32	386,OPT,ND
MOV	reg_sreg,reg64	X64,OPT,ND
MOV	reg_sreg,reg16	8086
MOV	reg_sreg,reg32	386
MOV	reg_sreg,rm64	X64
MOV	reg_al,mem_offs	8086
MOV	reg_ax,mem_offs	8086
MOV	reg_eax,mem_offs	386
MOV	reg_rax,mem_offs	X64
MOV	mem_offs,reg_al	8086,NOHLE
MOV	mem_offs,reg_ax	8086,NOHLE
MOV	mem_offs,reg_eax	386,NOHLE
MOV	mem_offs,reg_rax	X64,NOHLE
MOV	reg32,reg_creg	386,PRIV,NOLONG
MOV	reg64,reg_creg	X64,PRIV
MOV	reg_creg,reg32	386,PRIV,NOLONG
MOV	reg_creg,reg64	X64,PRIV
MOV	reg32,reg_dreg	386,PRIV,NOLONG
MOV	reg64,reg_dreg	X64,PRIV
MOV	reg_dreg,reg32	386,PRIV,NOLONG
MOV	reg_dreg,reg64	X64,PRIV
MOV	reg32,reg_treg	386,NOLONG,ND
MOV	reg_treg,reg32	386,NOLONG,ND
MOV	mem,reg8	8086
MOV	reg8,reg8	8086
MOV	mem,reg16	8086
MOV	reg16,reg16	8086
MOV	mem,reg32	386
MOV	reg32,reg32	386
MOV	mem,reg64	X64
MOV	reg64,reg64	X64
MOV	reg8,mem	8086
MOV	reg8,reg8	8086
MOV	reg16,mem	8086
MOV	reg16,reg16	8086
MOV	reg32,mem	386
MOV	reg32,reg32	386

MOV	reg64,mem	X64
MOV	reg64,reg64	X64
MOV	reg8,imm	8086
MOV	reg16,imm	8086
MOV	reg32,imm	386
MOV	reg64,udword	X64,OPT,ND
MOV	reg64,sdword	X64,OPT,ND
MOV	reg64,imm	X64
MOV	rm8,imm	8086
MOV	rm16,imm	8086
MOV	rm32,imm	386
MOV	rm64,imm	X64
MOV	rm64,imm32	X64
MOV	mem,imm8	8086
MOV	mem,imm16	8086
MOV	mem,imm32	386
MOVD	mmxreg,rm32	PENT,MMX,SD
MOVD	rm32,mmxreg	PENT,MMX,SD
MOVD	mmxreg,rm64	X64,MMX,SX,ND
MOVD	rm64,mmxreg	X64,MMX,SX,ND
MOVQ	mmxreg,mmxrm	PENT,MMX
MOVQ	mmxrm,mmxreg	PENT,MMX
MOVQ	mmxreg,rm64	X64,MMX
MOVQ	rm64,mmxreg	X64,MMX
MOVSB		8086
MOVSD		386
MOVSQ		X64
MOVSW		8086
MOVSX	reg16,mem	386
MOVSX	reg16,reg8	386
MOVSX	reg32,rm8	386
MOVSX	reg32,rm16	386
MOVSX	reg64,rm8	X64
MOVSX	reg64,rm16	X64
MOVFXD	reg64,rm32	X64
MOVFX	reg64,rm32	X64,ND
MOVZX	reg16,mem	386
MOVZX	reg16,reg8	386
MOVZX	reg32,rm8	386
MOVZX	reg32,rm16	386
MOVZX	reg64,rm8	X64
MOVZX	reg64,rm16	X64
MUL	rm8	8086
MUL	rm16	8086
MUL	rm32	386
MUL	rm64	X64
MWAIT		PRESCOTT
MWAIT	reg_eax,reg_ecx	PRESCOTT,ND
MWAITX		AMD
MWAITX	reg_eax,reg_ecx	AMD,ND
NEG	rm8	8086,LOCK
NEG	rm16	8086,LOCK
NEG	rm32	386,LOCK
NEG	rm64	X64,LOCK

NOP		8086
NOP	rm16	P6
NOP	rm32	P6
NOP	rm64	X64
NOT	rm8	8086, LOCK
NOT	rm16	8086, LOCK
NOT	rm32	386, LOCK
NOT	rm64	X64, LOCK
OR	mem, reg8	8086, LOCK
OR	reg8, reg8	8086
OR	mem, reg16	8086, LOCK
OR	reg16, reg16	8086
OR	mem, reg32	386, LOCK
OR	reg32, reg32	386
OR	mem, reg64	X64, LOCK
OR	reg64, reg64	X64
OR	reg8, mem	8086
OR	reg8, reg8	8086
OR	reg16, mem	8086
OR	reg16, reg16	8086
OR	reg32, mem	386
OR	reg32, reg32	386
OR	reg64, mem	X64
OR	reg64, reg64	X64
OR	rm16, imm8	8086, LOCK
OR	rm32, imm8	386, LOCK
OR	rm64, imm8	X64, LOCK
OR	reg_al, imm	8086
OR	reg_ax, sbytedword	8086, ND
OR	reg_ax, imm	8086
OR	reg_eax, sbytedword	386, ND
OR	reg_eax, imm	386
OR	reg_rax, sbytedword	X64, ND
OR	reg_rax, imm	X64
OR	rm8, imm	8086, LOCK
OR	rm16, sbytedword	8086, LOCK, ND
OR	rm16, imm	8086, LOCK
OR	rm32, sbytedword	386, LOCK, ND
OR	rm32, imm	386, LOCK
OR	rm64, sbytedword	X64, LOCK, ND
OR	rm64, imm	X64, LOCK
OR	mem, imm8	8086, LOCK
OR	mem, sbytedword16	8086, LOCK, ND
OR	mem, imm16	8086, LOCK
OR	mem, sbytedword32	386, LOCK, ND
OR	mem, imm32	386, LOCK
OR	rm8, imm	8086, LOCK, ND, NOLONG
OUT	imm, reg_al	8086
OUT	imm, reg_ax	8086
OUT	imm, reg_eax	386
OUT	reg_dx, reg_al	8086
OUT	reg_dx, reg_ax	8086
OUT	reg_dx, reg_eax	386
OUTSB		186

OUTSD		386
OUTSW		186
PACKSSDW	mmxreg,mmxrm	PENT,MMX
PACKSSWB	mmxreg,mmxrm	PENT,MMX
PACKUSWB	mmxreg,mmxrm	PENT,MMX
PADDB	mmxreg,mmxrm	PENT,MMX
PADDD	mmxreg,mmxrm	PENT,MMX
PADDSB	mmxreg,mmxrm	PENT,MMX
PADDSIW	mmxreg,mmxrm	PENT,MMX,CYRIX
PADDSW	mmxreg,mmxrm	PENT,MMX
PADDUSB	mmxreg,mmxrm	PENT,MMX
PADDUSW	mmxreg,mmxrm	PENT,MMX
PADDW	mmxreg,mmxrm	PENT,MMX
PAND	mmxreg,mmxrm	PENT,MMX
PANDN	mmxreg,mmxrm	PENT,MMX
PAUSE		8086
PAVEB	mmxreg,mmxrm	PENT,MMX,CYRIX
PAVGUSB	mmxreg,mmxrm	PENT,3DNOW
PCMPEQB	mmxreg,mmxrm	PENT,MMX
PCMPEQD	mmxreg,mmxrm	PENT,MMX
PCMPEQW	mmxreg,mmxrm	PENT,MMX
PCMPGTB	mmxreg,mmxrm	PENT,MMX
PCMPGTD	mmxreg,mmxrm	PENT,MMX
PCMPGTW	mmxreg,mmxrm	PENT,MMX
PDISTIB	mmxreg,mem	PENT,MMX,CYRIX
PF2ID	mmxreg,mmxrm	PENT,3DNOW
PFACC	mmxreg,mmxrm	PENT,3DNOW
PFADD	mmxreg,mmxrm	PENT,3DNOW
PFCMPEQ	mmxreg,mmxrm	PENT,3DNOW
PFCMPGE	mmxreg,mmxrm	PENT,3DNOW
PFCMPGT	mmxreg,mmxrm	PENT,3DNOW
PFMAX	mmxreg,mmxrm	PENT,3DNOW
PFMIN	mmxreg,mmxrm	PENT,3DNOW
PFMUL	mmxreg,mmxrm	PENT,3DNOW
PFRCP	mmxreg,mmxrm	PENT,3DNOW
PFRCPIT1	mmxreg,mmxrm	PENT,3DNOW
PFRCPIT2	mmxreg,mmxrm	PENT,3DNOW
PFRSQIT1	mmxreg,mmxrm	PENT,3DNOW
PFRSQRT	mmxreg,mmxrm	PENT,3DNOW
PFSUB	mmxreg,mmxrm	PENT,3DNOW
PFSUBR	mmxreg,mmxrm	PENT,3DNOW
PI2FD	mmxreg,mmxrm	PENT,3DNOW
PMACHRIW	mmxreg,mem	PENT,MMX,CYRIX
PMADDWD	mmxreg,mmxrm	PENT,MMX
PMAGW	mmxreg,mmxrm	PENT,MMX,CYRIX
PMULHRIW	mmxreg,mmxrm	PENT,MMX,CYRIX
PMULHRWA	mmxreg,mmxrm	PENT,3DNOW
PMULHRWC	mmxreg,mmxrm	PENT,MMX,CYRIX
PMULHW	mmxreg,mmxrm	PENT,MMX
PMULLW	mmxreg,mmxrm	PENT,MMX
PMVGEZB	mmxreg,mem	PENT,MMX,CYRIX
PMVLZB	mmxreg,mem	PENT,MMX,CYRIX
PMVNZB	mmxreg,mem	PENT,MMX,CYRIX
PMVZB	mmxreg,mem	PENT,MMX,CYRIX

POP	reg16	8086
POP	reg32	386,NOLONG
POP	reg64	X64
POP	rm16	8086
POP	rm32	386,NOLONG
POP	rm64	X64
POP	reg_es	8086,NOLONG
POP	reg_cs	8086,UNDOC,ND,OBSOLETE
POP	reg_ss	8086,NOLONG
POP	reg_ds	8086,NOLONG
POP	reg_fs	386
POP	reg_gs	386
POPA		186,NOLONG
POPAD		386,NOLONG
POPAW		186,NOLONG
POPF		8086
POPFD		386,NOLONG
POPfq		X64
POPFW		8086
POR	mmxreg,mmxrm	PENT,MMX
PREFETCH	mem	PENT,3DNOW
PREFETCHW	mem	PENT,3DNOW
PSLLD	mmxreg,mmxrm	PENT,MMX
PSLLD	mmxreg,imm	PENT,MMX
PSLLQ	mmxreg,mmxrm	PENT,MMX
PSLLQ	mmxreg,imm	PENT,MMX
PSLLW	mmxreg,mmxrm	PENT,MMX
PSLLW	mmxreg,imm	PENT,MMX
PSRAD	mmxreg,mmxrm	PENT,MMX
PSRAD	mmxreg,imm	PENT,MMX
PSRAW	mmxreg,mmxrm	PENT,MMX
PSRAW	mmxreg,imm	PENT,MMX
PSRLD	mmxreg,mmxrm	PENT,MMX
PSRLD	mmxreg,imm	PENT,MMX
PSRLQ	mmxreg,mmxrm	PENT,MMX
PSRLQ	mmxreg,imm	PENT,MMX
PSRLW	mmxreg,mmxrm	PENT,MMX
PSRLW	mmxreg,imm	PENT,MMX
PSUBB	mmxreg,mmxrm	PENT,MMX
PSUBD	mmxreg,mmxrm	PENT,MMX
PSUBSB	mmxreg,mmxrm	PENT,MMX
PSUBSIW	mmxreg,mmxrm	PENT,MMX,CYRIX
PSUBSW	mmxreg,mmxrm	PENT,MMX
PSUBUSB	mmxreg,mmxrm	PENT,MMX
PSUBUSW	mmxreg,mmxrm	PENT,MMX
PSUBW	mmxreg,mmxrm	PENT,MMX
PUNPCKHBW	mmxreg,mmxrm	PENT,MMX
PUNPCKHDQ	mmxreg,mmxrm	PENT,MMX
PUNPCKHWD	mmxreg,mmxrm	PENT,MMX
PUNPCKLBW	mmxreg,mmxrm	PENT,MMX
PUNPCKLDQ	mmxreg,mmxrm	PENT,MMX
PUNPCKLWD	mmxreg,mmxrm	PENT,MMX
PUSH	reg16	8086
PUSH	reg32	386,NOLONG

PUSH	reg64	X64
PUSH	rm16	8086
PUSH	rm32	386,NOLONG
PUSH	rm64	X64
PUSH	reg_es	8086,NOLONG
PUSH	reg_cs	8086,NOLONG
PUSH	reg_ss	8086,NOLONG
PUSH	reg_ds	8086,NOLONG
PUSH	reg_fs	386
PUSH	reg_gs	386
PUSH	imm8	186
PUSH	sbytedword16	186,AR0,SIZE,ND
PUSH	imm16	186,AR0,SIZE
PUSH	sbytedword32	386,NOLONG,AR0,SIZE,ND
PUSH	imm32	386,NOLONG,AR0,SIZE
PUSH	sbytedword32	386,NOLONG,SD,ND
PUSH	imm32	386,NOLONG,SD
PUSH	sbytedword64	X64,AR0,SIZE,ND
PUSH	imm64	X64,AR0,SIZE
PUSH	sbytedword32	X64,AR0,SIZE,ND
PUSH	imm32	X64,AR0,SIZE
PUSHA		186,NOLONG
PUSHAD		386,NOLONG
PUSHAW		186,NOLONG
PUSHF		8086
PUSHFD		386,NOLONG
PUSHFQ		X64
PUSHFW		8086
PXOR	mmxreg,mmxrm	PENT,MMX
RCL	rm8,unity	8086
RCL	rm8,reg_cl	8086
RCL	rm8,imm8	186
RCL	rm16,unity	8086
RCL	rm16,reg_cl	8086
RCL	rm16,imm8	186
RCL	rm32,unity	386
RCL	rm32,reg_cl	386
RCL	rm32,imm8	386
RCL	rm64,unity	X64
RCL	rm64,reg_cl	X64
RCL	rm64,imm8	X64
RCR	rm8,unity	8086
RCR	rm8,reg_cl	8086
RCR	rm8,imm8	186
RCR	rm16,unity	8086
RCR	rm16,reg_cl	8086
RCR	rm16,imm8	186
RCR	rm32,unity	386
RCR	rm32,reg_cl	386
RCR	rm32,imm8	386
RCR	rm64,unity	X64
RCR	rm64,reg_cl	X64
RCR	rm64,imm8	X64
RDSHR	rm32	P6,CYRIX,SMM

RDMSR		PENT, PRIV
RDPMC		P6
RDTSC		PENT
RDTSCP		X86_64
RET		8086, BND
RET	imm	8086, SW, BND
RETF		8086
RETF	imm	8086, SW
RETN		8086, BND
RETN	imm	8086, SW, BND
RETW		8086, BND
RETW	imm	8086, SW, BND
RETFW		8086
RETFW	imm	8086, SW
RETNW		8086, BND
RETNW	imm	8086, SW, BND
RETD		8086, BND, NOLONG
RETD	imm	8086, SW, BND, NOLONG
RETFD		8086
RETFD	imm	8086, SW
RETND		8086, BND, NOLONG
RETND	imm	8086, SW, BND, NOLONG
RETQ		X64, BND
RETQ	imm	X64, SW, BND
RETFQ		X64
RETFQ	imm	X64, SW
RETNQ		X64, BND
RETNQ	imm	X64, SW, BND
ROL	rm8, unity	8086
ROL	rm8, reg_cl	8086
ROL	rm8, imm8	186
ROL	rm16, unity	8086
ROL	rm16, reg_cl	8086
ROL	rm16, imm8	186
ROL	rm32, unity	386
ROL	rm32, reg_cl	386
ROL	rm32, imm8	386
ROL	rm64, unity	X64
ROL	rm64, reg_cl	X64
ROL	rm64, imm8	X64
ROR	rm8, unity	8086
ROR	rm8, reg_cl	8086
ROR	rm8, imm8	186
ROR	rm16, unity	8086
ROR	rm16, reg_cl	8086
ROR	rm16, imm8	186
ROR	rm32, unity	386
ROR	rm32, reg_cl	386
ROR	rm32, imm8	386
ROR	rm64, unity	X64
ROR	rm64, reg_cl	X64
ROR	rm64, imm8	X64
RDM		P6, CYRIX, ND
RSDC	reg_sreg, mem80	486, CYRIX, SMM

RSLDT	mem80	486,CYRIX,SMM
RSM		PENT,SMM
RSTS	mem80	486,CYRIX,SMM
SAHF		8086
SAL	rm8,unity	8086,ND
SAL	rm8,reg_cl	8086,ND
SAL	rm8,imm8	186,ND
SAL	rm16,unity	8086,ND
SAL	rm16,reg_cl	8086,ND
SAL	rm16,imm8	186,ND
SAL	rm32,unity	386,ND
SAL	rm32,reg_cl	386,ND
SAL	rm32,imm8	386,ND
SAL	rm64,unity	X64,ND
SAL	rm64,reg_cl	X64,ND
SAL	rm64,imm8	X64,ND
SALC		8086,UNDOC
SAR	rm8,unity	8086
SAR	rm8,reg_cl	8086
SAR	rm8,imm8	186
SAR	rm16,unity	8086
SAR	rm16,reg_cl	8086
SAR	rm16,imm8	186
SAR	rm32,unity	386
SAR	rm32,reg_cl	386
SAR	rm32,imm8	386
SAR	rm64,unity	X64
SAR	rm64,reg_cl	X64
SAR	rm64,imm8	X64
SBB	mem,reg8	8086,LOCK
SBB	reg8,reg8	8086
SBB	mem,reg16	8086,LOCK
SBB	reg16,reg16	8086
SBB	mem,reg32	386,LOCK
SBB	reg32,reg32	386
SBB	mem,reg64	X64,LOCK
SBB	reg64,reg64	X64
SBB	reg8,mem	8086
SBB	reg8,reg8	8086
SBB	reg16,mem	8086
SBB	reg16,reg16	8086
SBB	reg32,mem	386
SBB	reg32,reg32	386
SBB	reg64,mem	X64
SBB	reg64,reg64	X64
SBB	rm16,imm8	8086,LOCK
SBB	rm32,imm8	386,LOCK
SBB	rm64,imm8	X64,LOCK
SBB	reg_al,imm	8086
SBB	reg_ax,sbytedword	8086,ND
SBB	reg_ax,imm	8086
SBB	reg_eax,sbytedword	386,ND
SBB	reg_eax,imm	386
SBB	reg_rax,sbytedword	X64,ND

SBB	reg_rax,imm	X64
SBB	rm8,imm	8086,LOCK
SBB	rm16,sbytedword	8086,LOCK,ND
SBB	rm16,imm	8086,LOCK
SBB	rm32,sbytedword	386,LOCK,ND
SBB	rm32,imm	386,LOCK
SBB	rm64,sbytedword	X64,LOCK,ND
SBB	rm64,imm	X64,LOCK
SBB	mem,imm8	8086,LOCK
SBB	mem,sbytedword16	8086,LOCK,ND
SBB	mem,imm16	8086,LOCK
SBB	mem,sbytedword32	386,LOCK,ND
SBB	mem,imm32	386,LOCK
SBB	rm8,imm	8086,LOCK,ND,NOLONG
SCASB		8086
SCASD		386
SCASQ		X64
SCASW		8086
SFENCE		X64,AMD
SGDT	mem	286
SHL	rm8,unity	8086
SHL	rm8,reg_cl	8086
SHL	rm8,imm8	186
SHL	rm16,unity	8086
SHL	rm16,reg_cl	8086
SHL	rm16,imm8	186
SHL	rm32,unity	386
SHL	rm32,reg_cl	386
SHL	rm32,imm8	386
SHL	rm64,unity	X64
SHL	rm64,reg_cl	X64
SHL	rm64,imm8	X64
SHLD	mem,reg16,imm	386
SHLD	reg16,reg16,imm	386
SHLD	mem,reg32,imm	386
SHLD	reg32,reg32,imm	386
SHLD	mem,reg64,imm	X64
SHLD	reg64,reg64,imm	X64
SHLD	mem,reg16,reg_cl	386
SHLD	reg16,reg16,reg_cl	386
SHLD	mem,reg32,reg_cl	386
SHLD	reg32,reg32,reg_cl	386
SHLD	mem,reg64,reg_cl	X64
SHLD	reg64,reg64,reg_cl	X64
SHR	rm8,unity	8086
SHR	rm8,reg_cl	8086
SHR	rm8,imm8	186
SHR	rm16,unity	8086
SHR	rm16,reg_cl	8086
SHR	rm16,imm8	186
SHR	rm32,unity	386
SHR	rm32,reg_cl	386
SHR	rm32,imm8	386
SHR	rm64,unity	X64

SHR	rm64,reg_cl	X64
SHR	rm64,imm8	X64
SHRD	mem,reg16,imm	386
SHRD	reg16,reg16,imm	386
SHRD	mem,reg32,imm	386
SHRD	reg32,reg32,imm	386
SHRD	mem,reg64,imm	X64
SHRD	reg64,reg64,imm	X64
SHRD	mem,reg16,reg_cl	386
SHRD	reg16,reg16,reg_cl	386
SHRD	mem,reg32,reg_cl	386
SHRD	reg32,reg32,reg_cl	386
SHRD	mem,reg64,reg_cl	X64
SHRD	reg64,reg64,reg_cl	X64
SIDT	mem	286
SLDT	mem	286
SLDT	mem16	286
SLDT	reg16	286
SLDT	reg32	386
SLDT	reg64	X64,ND
SLDT	reg64	X64
SKINIT		X64
SMI		386,UNDOC
SMINT		P6,CYRIX,ND
SMINTOLD		486,CYRIX,ND,OBSOLETE
SMSW	mem	286
SMSW	mem16	286
SMSW	reg16	286
SMSW	reg32	386
SMSW	reg64	X64
STC		8086
STD		8086
STI		8086
STOSB		8086
STOSD		386
STOSQ		X64
STOSW		8086
STR	mem	286,PROT
STR	mem16	286,PROT
STR	reg16	286,PROT
STR	reg32	386,PROT
STR	reg64	X64
SUB	mem,reg8	8086,LOCK
SUB	reg8,reg8	8086
SUB	mem,reg16	8086,LOCK
SUB	reg16,reg16	8086
SUB	mem,reg32	386,LOCK
SUB	reg32,reg32	386
SUB	mem,reg64	X64,LOCK
SUB	reg64,reg64	X64
SUB	reg8,mem	8086
SUB	reg8,reg8	8086
SUB	reg16,mem	8086
SUB	reg16,reg16	8086

SUB	reg32,mem	386
SUB	reg32,reg32	386
SUB	reg64,mem	X64
SUB	reg64,reg64	X64
SUB	rm16,imm8	8086, LOCK
SUB	rm32,imm8	386, LOCK
SUB	rm64,imm8	X64, LOCK
SUB	reg_al,imm	8086
SUB	reg_ax,sbytedword	8086,ND
SUB	reg_ax,imm	8086
SUB	reg_eax,sbytedword	386,ND
SUB	reg_eax,imm	386
SUB	reg_rax,sbytedword	X64,ND
SUB	reg_rax,imm	X64
SUB	rm8,imm	8086, LOCK
SUB	rm16,sbytedword	8086, LOCK,ND
SUB	rm16,imm	8086, LOCK
SUB	rm32,sbytedword	386, LOCK,ND
SUB	rm32,imm	386, LOCK
SUB	rm64,sbytedword	X64, LOCK,ND
SUB	rm64,imm	X64, LOCK
SUB	mem,imm8	8086, LOCK
SUB	mem,sbytedword16	8086, LOCK,ND
SUB	mem,imm16	8086, LOCK
SUB	mem,sbytedword32	386, LOCK,ND
SUB	mem,imm32	386, LOCK
SUB	rm8,imm	8086, LOCK,ND,NOLONG
SVDC	mem80,reg_sreg	486,CYRIX,SMM
SVLDT	mem80	486,CYRIX,SMM,ND
SVTS	mem80	486,CYRIX,SMM
SWAPGS		X64
SYSCALL		P6,AMD
SYSENTER		P6
SYSEXIT		P6,PRIV
SYSRET		P6,PRIV,AMD
TEST	mem,reg8	8086
TEST	reg8,reg8	8086
TEST	mem,reg16	8086
TEST	reg16,reg16	8086
TEST	mem,reg32	386
TEST	reg32,reg32	386
TEST	mem,reg64	X64
TEST	reg64,reg64	X64
TEST	reg8,mem	8086
TEST	reg16,mem	8086
TEST	reg32,mem	386
TEST	reg64,mem	X64
TEST	reg_al,imm	8086
TEST	reg_ax,imm	8086
TEST	reg_eax,imm	386
TEST	reg_rax,imm	X64
TEST	rm8,imm	8086
TEST	rm16,imm	8086
TEST	rm32,imm	386

TEST	rm64,imm	X64
TEST	mem,imm8	8086
TEST	mem,imm16	8086
TEST	mem,imm32	386
UD0		186,OBSOLETE
UD0	reg16,rm16	186
UD0	reg32,rm32	186
UD0	reg64,rm64	186
UD1	reg16,rm16	186
UD1	reg32,rm32	186
UD1	reg64,rm64	186
UD1		186,ND
UD2B		186,ND
UD2B	reg16,rm16	186,ND
UD2B	reg32,rm32	186,ND
UD2B	reg64,rm64	186,ND
UD2		186
UD2A		186,ND
UMOV	mem,reg8	386,UNDOC,ND
UMOV	reg8,reg8	386,UNDOC,ND
UMOV	mem,reg16	386,UNDOC,ND
UMOV	reg16,reg16	386,UNDOC,ND
UMOV	mem,reg32	386,UNDOC,ND
UMOV	reg32,reg32	386,UNDOC,ND
UMOV	reg8,mem	386,UNDOC,ND
UMOV	reg8,reg8	386,UNDOC,ND
UMOV	reg16,mem	386,UNDOC,ND
UMOV	reg16,reg16	386,UNDOC,ND
UMOV	reg32,mem	386,UNDOC,ND
UMOV	reg32,reg32	386,UNDOC,ND
VERR	mem	286,PROT
VERR	mem16	286,PROT
VERR	reg16	286,PROT
VERW	mem	286,PROT
VERW	mem16	286,PROT
VERW	reg16	286,PROT
FWAIT		8086
WBINVD		486,PRIV
WRSHR	rm32	P6,CYRIX,SMM
WRMSR		PENT,PRIV
XADD	mem,reg8	486,LOCK
XADD	reg8,reg8	486
XADD	mem,reg16	486,LOCK
XADD	reg16,reg16	486
XADD	mem,reg32	486,LOCK
XADD	reg32,reg32	486
XADD	mem,reg64	X64,LOCK
XADD	reg64,reg64	X64
XBTS	reg16,mem	386,SW,UNDOC,ND
XBTS	reg16,reg16	386,UNDOC,ND
XBTS	reg32,mem	386,SD,UNDOC,ND
XBTS	reg32,reg32	386,UNDOC,ND
XCHG	reg_ax,reg16	8086
XCHG	reg_eax,reg32na	386

XCHG	reg_rax, reg64	X64
XCHG	reg16, reg_ax	8086
XCHG	reg32na, reg_eax	386
XCHG	reg64, reg_rax	X64
XCHG	reg_eax, reg_eax	386, NOLONG
XCHG	reg8, mem	8086, LOCK
XCHG	reg8, reg8	8086
XCHG	reg16, mem	8086, LOCK
XCHG	reg16, reg16	8086
XCHG	reg32, mem	386, LOCK
XCHG	reg32, reg32	386
XCHG	reg64, mem	X64, LOCK
XCHG	reg64, reg64	X64
XCHG	mem, reg8	8086, LOCK
XCHG	reg8, reg8	8086
XCHG	mem, reg16	8086, LOCK
XCHG	reg16, reg16	8086
XCHG	mem, reg32	386, LOCK
XCHG	reg32, reg32	386
XCHG	mem, reg64	X64, LOCK
XCHG	reg64, reg64	X64
XLATB		8086
XLAT		8086
XOR	mem, reg8	8086, LOCK
XOR	reg8, reg8	8086
XOR	mem, reg16	8086, LOCK
XOR	reg16, reg16	8086
XOR	mem, reg32	386, LOCK
XOR	reg32, reg32	386
XOR	mem, reg64	X64, LOCK
XOR	reg64, reg64	X64
XOR	reg8, mem	8086
XOR	reg8, reg8	8086
XOR	reg16, mem	8086
XOR	reg16, reg16	8086
XOR	reg32, mem	386
XOR	reg32, reg32	386
XOR	reg64, mem	X64
XOR	reg64, reg64	X64
XOR	rm16, imm8	8086, LOCK
XOR	rm32, imm8	386, LOCK
XOR	rm64, imm8	X64, LOCK
XOR	reg_al, imm	8086
XOR	reg_ax, sbytedword	8086, ND
XOR	reg_ax, imm	8086
XOR	reg_eax, sbytedword	386, ND
XOR	reg_eax, imm	386
XOR	reg_rax, sbytedword	X64, ND
XOR	reg_rax, imm	X64
XOR	rm8, imm	8086, LOCK
XOR	rm16, sbytedword	8086, LOCK, ND
XOR	rm16, imm	8086, LOCK
XOR	rm32, sbytedword	386, LOCK, ND
XOR	rm32, imm	386, LOCK

XOR	rm64,sbytedword	X64, LOCK, ND
XOR	rm64, imm	X64, LOCK
XOR	mem, imm8	8086, LOCK
XOR	mem, sbytedword16	8086, LOCK, ND
XOR	mem, imm16	8086, LOCK
XOR	mem, sbytedword32	386, LOCK, ND
XOR	mem, imm32	386, LOCK
XOR	rm8, imm	8086, LOCK, ND, NOLONG
CMOVcc	reg16, mem	P6
CMOVcc	reg16, reg16	P6
CMOVcc	reg32, mem	P6
CMOVcc	reg32, reg32	P6
CMOVcc	reg64, mem	X64
CMOVcc	reg64, reg64	X64
Jcc	imm near	386, BND
Jcc	imm16 near	386, NOLONG, BND
Jcc	imm32 near	386, NOLONG, BND
Jcc	imm64 near	X64, BND
Jcc	imm short	8086, ND, BND
Jcc	imm	8086, ND, BND
Jcc	imm	386, ND, BND
Jcc	imm	8086, ND, BND
Jcc	imm	8086, BND
SETcc	mem	386
SETcc	reg8	386

B.1.3 Katmai Streaming SIMD instructions (SSE -- a.k.a. KNI, XMM, MMX2)

ADDPS	xmmreg, xmmrm128	KATMAI, SSE
ADDSS	xmmreg, xmmrm32	KATMAI, SSE
ANDNPS	xmmreg, xmmrm128	KATMAI, SSE
ANDPS	xmmreg, xmmrm128	KATMAI, SSE
CMPEQPS	xmmreg, xmmrm128	KATMAI, SSE
CMPEQSS	xmmreg, xmmrm32	KATMAI, SSE
CMPLEPS	xmmreg, xmmrm128	KATMAI, SSE
CMPLESS	xmmreg, xmmrm32	KATMAI, SSE
CMPLTPS	xmmreg, xmmrm128	KATMAI, SSE
CMPLTSS	xmmreg, xmmrm32	KATMAI, SSE
CMPNEQPS	xmmreg, xmmrm128	KATMAI, SSE
CMPNEQSS	xmmreg, xmmrm32	KATMAI, SSE
CMPNLEPS	xmmreg, xmmrm128	KATMAI, SSE
CMPNLESS	xmmreg, xmmrm32	KATMAI, SSE
CMPNLTPS	xmmreg, xmmrm128	KATMAI, SSE
CMPNLTSS	xmmreg, xmmrm32	KATMAI, SSE
CMPORDPS	xmmreg, xmmrm128	KATMAI, SSE
CMPORDSS	xmmreg, xmmrm32	KATMAI, SSE
CMPUNORDPS	xmmreg, xmmrm128	KATMAI, SSE
CMPUNORDSS	xmmreg, xmmrm32	KATMAI, SSE
CMPPS	xmmreg, mem, imm	KATMAI, SSE
CMPPS	xmmreg, xmmreg, imm	KATMAI, SSE
CMPSS	xmmreg, mem, imm	KATMAI, SSE
CMPSS	xmmreg, xmmreg, imm	KATMAI, SSE
COMISS	xmmreg, xmmrm32	KATMAI, SSE
CVTPI2PS	xmmreg, mmxrm64	KATMAI, SSE, MMX

CVTPS2PI	mmxreg, xmmrm64	KATMAI, SSE, MMX
CVTSI2SS	xmmreg, mem	KATMAI, SSE, SD, AR1, ND
CVTSI2SS	xmmreg, rm32	KATMAI, SSE, SD, AR1
CVTSI2SS	xmmreg, rm64	X64, SSE, AR1
CVTSS2SI	reg32, xmmreg	KATMAI, SSE, SD, AR1
CVTSS2SI	reg32, mem	KATMAI, SSE, SD, AR1
CVTSS2SI	reg64, xmmreg	X64, SSE, SD, AR1
CVTSS2SI	reg64, mem	X64, SSE, SD, AR1
CVTTPS2PI	mmxreg, xmmrm	KATMAI, SSE, MMX
CVTTSS2SI	reg32, xmmrm	KATMAI, SSE, SD, AR1
CVTTSS2SI	reg64, xmmrm	X64, SSE, SD, AR1
DIVPS	xmmreg, xmmrm128	KATMAI, SSE
DIVSS	xmmreg, xmmrm32	KATMAI, SSE
LDMXCSR	mem32	KATMAI, SSE
MAXPS	xmmreg, xmmrm128	KATMAI, SSE
MAXSS	xmmreg, xmmrm32	KATMAI, SSE
MINPS	xmmreg, xmmrm128	KATMAI, SSE
MINSS	xmmreg, xmmrm32	KATMAI, SSE
MOVAPS	xmmreg, xmmrm128	KATMAI, SSE
MOVAPS	xmmrm128, xmmreg	KATMAI, SSE
MOVHPS	xmmreg, mem64	KATMAI, SSE
MOVHPS	mem64, xmmreg	KATMAI, SSE
MOVLHPS	xmmreg, xmmreg	KATMAI, SSE
MOVLPS	xmmreg, mem64	KATMAI, SSE
MOVLPS	mem64, xmmreg	KATMAI, SSE
MOVHLPS	xmmreg, xmmreg	KATMAI, SSE
MOVMSKPS	reg32, xmmreg	KATMAI, SSE
MOVMSKPS	reg64, xmmreg	X64, SSE
MOVNTPS	mem128, xmmreg	KATMAI, SSE
MOVSS	xmmreg, xmmrm32	KATMAI, SSE
MOVSS	mem32, xmmreg	KATMAI, SSE
MOVSS	xmmreg, xmmreg	KATMAI, SSE
MOVUPS	xmmreg, xmmrm128	KATMAI, SSE
MOVUPS	xmmrm128, xmmreg	KATMAI, SSE
MULPS	xmmreg, xmmrm128	KATMAI, SSE
MULSS	xmmreg, xmmrm32	KATMAI, SSE
ORPS	xmmreg, xmmrm128	KATMAI, SSE
RCPPS	xmmreg, xmmrm128	KATMAI, SSE
RCPSS	xmmreg, xmmrm32	KATMAI, SSE
RSQRTPS	xmmreg, xmmrm128	KATMAI, SSE
RSQRTSS	xmmreg, xmmrm32	KATMAI, SSE
SHUFPS	xmmreg, xmmrm128, imm8	KATMAI, SSE
SQRTPS	xmmreg, xmmrm128	KATMAI, SSE
SQRTSS	xmmreg, xmmrm32	KATMAI, SSE
STMXCSR	mem32	KATMAI, SSE
SUBPS	xmmreg, xmmrm128	KATMAI, SSE
SUBSS	xmmreg, xmmrm32	KATMAI, SSE
UCOMISS	xmmreg, xmmrm32	KATMAI, SSE
UNPCKHPS	xmmreg, xmmrm128	KATMAI, SSE
UNPCKLPS	xmmreg, xmmrm128	KATMAI, SSE
XORPS	xmmreg, xmmrm128	KATMAI, SSE

B.1.4 Introduced in Deschutes but necessary for SSE support

FXRSTOR	mem	P6, SSE, FPU
FXRSTOR64	mem	X64, SSE, FPU
FXSAVE	mem	P6, SSE, FPU
FXSAVE64	mem	X64, SSE, FPU

B.1.5 XSAVE group (AVX and extended state)

XGETBV		NEHALEM
XSETBV		NEHALEM, PRIV
XSAVE	mem	NEHALEM
XSAVE64	mem	LONG, NEHALEM
XSAVEC	mem	
XSAVEC64	mem	LONG
XSAVEOPT	mem	
XSAVEOPT64	mem	LONG
XSAVES	mem	
XSAVES64	mem	LONG
XRSTOR	mem	NEHALEM
XRSTOR64	mem	LONG, NEHALEM
XRSTORS	mem	
XRSTORS64	mem	LONG

B.1.6 Generic memory operations

PREFETCHNTA	mem8	KATMAI
PREFETCHT0	mem8	KATMAI
PREFETCHT1	mem8	KATMAI
PREFETCHT2	mem8	KATMAI
SFENCE		KATMAI

B.1.7 New MMX instructions introduced in Katmai

MASKMOVQ	mmxreg, mmxreg	KATMAI, MMX
MOVNTQ	mem, mmxreg	KATMAI, MMX
PAVGB	mmxreg, mmxrm	KATMAI, MMX
PAVGW	mmxreg, mmxrm	KATMAI, MMX
PEXTRW	reg32, mmxreg, imm	KATMAI, MMX
PINSRW	mmxreg, mem, imm	KATMAI, MMX
PINSRW	mmxreg, rm16, imm	KATMAI, MMX
PINSRW	mmxreg, reg32, imm	KATMAI, MMX
PMAXSW	mmxreg, mmxrm	KATMAI, MMX
PMAXUB	mmxreg, mmxrm	KATMAI, MMX
PMINSW	mmxreg, mmxrm	KATMAI, MMX
PMINUB	mmxreg, mmxrm	KATMAI, MMX
PMOVMASK	reg32, mmxreg	KATMAI, MMX
PMULHUW	mmxreg, mmxrm	KATMAI, MMX
PSADBW	mmxreg, mmxrm	KATMAI, MMX
PSHUFW	mmxreg, mmxrm, imm	KATMAI, MMX

B.1.8 AMD Enhanced 3DNow! (Athlon) instructions

PF2IW	mmxreg, mmxrm	PENT, 3DNOW
PFNACC	mmxreg, mmxrm	PENT, 3DNOW
PFPNACC	mmxreg, mmxrm	PENT, 3DNOW

PI2FW	mmxreg,mmxrm	PENT,3DNOW
PSWAPD	mmxreg,mmxrm	PENT,3DNOW

B.1.9 Willamette SSE2 Cacheability Instructions

MASKMOVDQU	xmmreg,xmmreg	WILLAMETTE,SSE2
CLFLUSH	mem	WILLAMETTE,SSE2
MOVNTDQ	mem,xmmreg	WILLAMETTE,SSE2,S0
MOVNTI	mem,reg32	WILLAMETTE,SD
MOVNTI	mem,reg64	X64
MOVNTPD	mem,xmmreg	WILLAMETTE,SSE2,S0
LFENCE		WILLAMETTE,SSE2
MFENCE		WILLAMETTE,SSE2

B.1.10 Willamette MMX instructions (SSE2 SIMD Integer Instructions)

MOVD	mem,xmmreg	WILLAMETTE,SSE2,SD
MOVD	xmmreg,mem	WILLAMETTE,SSE2,SD
MOVD	xmmreg,rm32	WILLAMETTE,SSE2
MOVD	rm32,xmmreg	WILLAMETTE,SSE2
MOVDQA	xmmreg,xmmreg	WILLAMETTE,SSE2
MOVDQA	mem,xmmreg	WILLAMETTE,SSE2,S0
MOVDQA	xmmreg,mem	WILLAMETTE,SSE2,S0
MOVDQA	xmmreg,xmmreg	WILLAMETTE,SSE2
MOVDQU	xmmreg,xmmreg	WILLAMETTE,SSE2
MOVDQU	mem,xmmreg	WILLAMETTE,SSE2,S0
MOVDQU	xmmreg,mem	WILLAMETTE,SSE2,S0
MOVDQU	xmmreg,xmmreg	WILLAMETTE,SSE2
MOVDQ2Q	mmxreg,xmmreg	WILLAMETTE,SSE2
MOVQ	xmmreg,xmmreg	WILLAMETTE,SSE2
MOVQ	xmmreg,xmmreg	WILLAMETTE,SSE2
MOVQ	mem,xmmreg	WILLAMETTE,SSE2
MOVQ	xmmreg,mem	WILLAMETTE,SSE2
MOVQ	xmmreg,rm64	X64,SSE2
MOVQ	rm64,xmmreg	X64,SSE2
MOVQ2DQ	xmmreg,mmxreg	WILLAMETTE,SSE2
PACKSSWB	xmmreg,xmmrm	WILLAMETTE,SSE2,S0
PACKSSDW	xmmreg,xmmrm	WILLAMETTE,SSE2,S0
PACKUSWB	xmmreg,xmmrm	WILLAMETTE,SSE2,S0
PADDB	xmmreg,xmmrm	WILLAMETTE,SSE2,S0
PADDW	xmmreg,xmmrm	WILLAMETTE,SSE2,S0
PADD	xmmreg,xmmrm	WILLAMETTE,SSE2,S0
PADDQ	mmxreg,mmxrm	WILLAMETTE,MMX
PADDQ	xmmreg,xmmrm	WILLAMETTE,SSE2,S0
PADDSB	xmmreg,xmmrm	WILLAMETTE,SSE2,S0
PADDSW	xmmreg,xmmrm	WILLAMETTE,SSE2,S0
PADDUSB	xmmreg,xmmrm	WILLAMETTE,SSE2,S0
PADDUSW	xmmreg,xmmrm	WILLAMETTE,SSE2,S0
PAND	xmmreg,xmmrm	WILLAMETTE,SSE2,S0
PANDN	xmmreg,xmmrm	WILLAMETTE,SSE2,S0
PAVGB	xmmreg,xmmrm	WILLAMETTE,SSE2,S0
PAVGW	xmmreg,xmmrm	WILLAMETTE,SSE2,S0
PCMPEQB	xmmreg,xmmrm	WILLAMETTE,SSE2,S0
PCMPEQW	xmmreg,xmmrm	WILLAMETTE,SSE2,S0
PCMPEQD	xmmreg,xmmrm	WILLAMETTE,SSE2,S0

PCMPGTB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PCMPGTW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PCMPGTD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PEXTRW	reg32, xmmreg, imm	WILLAMETTE, SSE2
PEXTRW	reg64, xmmreg, imm	X64, SSE2, ND
PINSRW	xmmreg, reg16, imm	WILLAMETTE, SSE2
PINSRW	xmmreg, reg32, imm	WILLAMETTE, SSE2, ND
PINSRW	xmmreg, reg64, imm	X64, SSE2, ND
PINSRW	xmmreg, mem, imm	WILLAMETTE, SSE2
PINSRW	xmmreg, mem16, imm	WILLAMETTE, SSE2
PMADDWD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PMAXSW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PMAXUB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PMINSW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PMINUB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PMOVMSKB	reg32, xmmreg	WILLAMETTE, SSE2
PMULHUW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PMULHW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PMULLW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PMULUDQ	mmxreg, mmxrm	WILLAMETTE, SSE2, SO
PMULUDQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
POR	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSADBW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSHUFD	xmmreg, xmmreg, imm	WILLAMETTE, SSE2
PSHUFD	xmmreg, mem, imm	WILLAMETTE, SSE2
PSHUFW	xmmreg, xmmreg, imm	WILLAMETTE, SSE2
PSHUFW	xmmreg, mem, imm	WILLAMETTE, SSE2
PSHUFLW	xmmreg, xmmreg, imm	WILLAMETTE, SSE2
PSHUFLW	xmmreg, mem, imm	WILLAMETTE, SSE2
PSLLDQ	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSLLW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSLLW	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSLLD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSLLD	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSLLQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSLLQ	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSRAW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSRAW	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSRAD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSRAD	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSRLDQ	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSRLW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSRLW	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSRLD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSRLD	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSRLQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSRLQ	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSUBB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSUBW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSUBD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSUBQ	mmxreg, mmxrm	WILLAMETTE, SSE2, SO
PSUBQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSUBSB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSUBSW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO

PSUBUSB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSUBUSW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PUNPCKHBW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PUNPCKHWD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PUNPCKHDQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PUNPCKHQDQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PUNPCKLBW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PUNPCKLWD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PUNPCKLDQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PUNPCKLQDQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PXOR	xmmreg, xmmrm	WILLAMETTE, SSE2, SO

B.1.11 Willamette Streaming SIMD instructions (SSE2)

ADDPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
ADDSD	xmmreg, xmmrm	WILLAMETTE, SSE2
ANDNPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
ANDPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPEQPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPEQSD	xmmreg, xmmrm	WILLAMETTE, SSE2
CMPLEPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPLESD	xmmreg, xmmrm	WILLAMETTE, SSE2
CMPLTPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPLTSD	xmmreg, xmmrm	WILLAMETTE, SSE2
CMPNEQPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPNEQSD	xmmreg, xmmrm	WILLAMETTE, SSE2
CMPNLEPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPNLESD	xmmreg, xmmrm	WILLAMETTE, SSE2
CMPNLTPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPNLTSD	xmmreg, xmmrm	WILLAMETTE, SSE2
CMPORDPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPORDSD	xmmreg, xmmrm	WILLAMETTE, SSE2
CMPUNORDPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPUNORDSD	xmmreg, xmmrm	WILLAMETTE, SSE2
CMPPD	xmmreg, xmmrm128, imm8	WILLAMETTE, SSE2
CMPSD	xmmreg, xmmrm128, imm8	WILLAMETTE, SSE2
COMISD	xmmreg, xmmrm	WILLAMETTE, SSE2
CVTDQ2PD	xmmreg, xmmrm	WILLAMETTE, SSE2
CVTDQ2PS	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CVTPD2DQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CVTPD2PI	mmxreg, xmmrm	WILLAMETTE, SSE2, SO
CVTPD2PS	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CVTPI2PD	xmmreg, mmxrm	WILLAMETTE, SSE2
CVTPS2DQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CVTPS2PD	xmmreg, xmmrm	WILLAMETTE, SSE2
CVTSD2SI	reg32, xmmreg	WILLAMETTE, SSE2, AR1
CVTSD2SI	reg32, mem	WILLAMETTE, SSE2, AR1
CVTSD2SI	reg64, xmmreg	X64, SSE2, AR1
CVTSD2SI	reg64, mem	X64, SSE2, AR1
CVTSD2SS	xmmreg, xmmrm	WILLAMETTE, SSE2
CVTSI2SD	xmmreg, mem	WILLAMETTE, SSE2, SD, AR1, ND
CVTSI2SD	xmmreg, rm32	WILLAMETTE, SSE2, SD, AR1
CVTSI2SD	xmmreg, rm64	X64, SSE2, AR1
CVTSS2SD	xmmreg, xmmrm	WILLAMETTE, SSE2, SD

CVTTPD2PI	mmxreg, xmmrm	WILLAMETTE, SSE2, SO
CVTTPD2DQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CVTTPS2DQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CVTTSD2SI	reg32, xmmreg	WILLAMETTE, SSE2, AR1
CVTTSD2SI	reg32, mem	WILLAMETTE, SSE2, AR1
CVTTSD2SI	reg64, xmmreg	X64, SSE2, AR1
CVTTSD2SI	reg64, mem	X64, SSE2, AR1
DIVPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
DIVSD	xmmreg, xmmrm	WILLAMETTE, SSE2
MAXPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
MAXSD	xmmreg, xmmrm	WILLAMETTE, SSE2
MINPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
MINSD	xmmreg, xmmrm	WILLAMETTE, SSE2
MOVAPD	xmmreg, xmmreg	WILLAMETTE, SSE2
MOVAPD	xmmreg, xmmreg	WILLAMETTE, SSE2
MOVAPD	mem, xmmreg	WILLAMETTE, SSE2, SO
MOVAPD	xmmreg, mem	WILLAMETTE, SSE2, SO
MOVHPD	mem, xmmreg	WILLAMETTE, SSE2
MOVHPD	xmmreg, mem	WILLAMETTE, SSE2
MOVLPD	mem64, xmmreg	WILLAMETTE, SSE2
MOVLPD	xmmreg, mem64	WILLAMETTE, SSE2
MOVMSKPD	reg32, xmmreg	WILLAMETTE, SSE2
MOVMSKPD	reg64, xmmreg	X64, SSE2
MOVSD	xmmreg, xmmreg	WILLAMETTE, SSE2
MOVSD	xmmreg, xmmreg	WILLAMETTE, SSE2
MOVSD	mem64, xmmreg	WILLAMETTE, SSE2
MOVSD	xmmreg, mem64	WILLAMETTE, SSE2
MOVUPD	xmmreg, xmmreg	WILLAMETTE, SSE2
MOVUPD	xmmreg, xmmreg	WILLAMETTE, SSE2
MOVUPD	mem, xmmreg	WILLAMETTE, SSE2, SO
MOVUPD	xmmreg, mem	WILLAMETTE, SSE2, SO
MULPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
MULSD	xmmreg, xmmrm	WILLAMETTE, SSE2
ORPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
SHUFPD	xmmreg, xmmreg, imm	WILLAMETTE, SSE2
SHUFPD	xmmreg, mem, imm	WILLAMETTE, SSE2
SQRTPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
SQRTSD	xmmreg, xmmrm	WILLAMETTE, SSE2
SUBPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
SUBSD	xmmreg, xmmrm	WILLAMETTE, SSE2
UCOMISD	xmmreg, xmmrm	WILLAMETTE, SSE2
UNPCKHPD	xmmreg, xmmrm128	WILLAMETTE, SSE2
UNPCKLPD	xmmreg, xmmrm128	WILLAMETTE, SSE2
XORPD	xmmreg, xmmrm128	WILLAMETTE, SSE2

B.1.12 Prescott New Instructions (SSE3)

ADDSUBPD	xmmreg, xmmrm	PRESCOTT, SSE3, SO
ADDSUBPS	xmmreg, xmmrm	PRESCOTT, SSE3, SO
HADDPD	xmmreg, xmmrm	PRESCOTT, SSE3, SO
HADDPS	xmmreg, xmmrm	PRESCOTT, SSE3, SO
HSUBPD	xmmreg, xmmrm	PRESCOTT, SSE3, SO
HSUBPS	xmmreg, xmmrm	PRESCOTT, SSE3, SO
LDDQU	xmmreg, mem	PRESCOTT, SSE3, SO

MOVDDUP	xmmreg, xmmrm	PRESCOTT, SSE3
MOVSHDUP	xmmreg, xmmrm	PRESCOTT, SSE3
MOVSLDUP	xmmreg, xmmrm	PRESCOTT, SSE3

B.1.13 VMX/SVM Instructions

CLGI		VMX, AMD
STGI		VMX, AMD
VMCALL		VMX
VMCLEAR	mem	VMX
VMFUNC		VMX
VMLAUNCH		VMX
VMLOAD		VMX, AMD
VMMCALL		VMX, AMD
VMPTRLD	mem	VMX
VMPTRST	mem	VMX
VMREAD	rm32, reg32	VMX, NOLONG, SD
VMREAD	rm64, reg64	X64, VMX
VMRESUME		VMX
VMRUN		VMX, AMD
VMSAVE		VMX, AMD
VMWRITE	reg32, rm32	VMX, NOLONG, SD
VMWRITE	reg64, rm64	X64, VMX
VMXOFF		VMX
VMXON	mem	VMX

B.1.14 Extended Page Tables VMX instructions

INVEPT	reg32, mem	VMX, SO, NOLONG
INVEPT	reg64, mem	VMX, SO, LONG
INVVPID	reg32, mem	VMX, SO, NOLONG
INVVPID	reg64, mem	VMX, SO, LONG

B.1.15 Tejas New Instructions (SSSE3)

PABSB	mmxreg, mmxrm	SSSE3, MMX
PABSB	xmmreg, xmmrm	SSSE3
PABSW	mmxreg, mmxrm	SSSE3, MMX
PABSW	xmmreg, xmmrm	SSSE3
PABSD	mmxreg, mmxrm	SSSE3, MMX
PABSD	xmmreg, xmmrm	SSSE3
PALIGNR	mmxreg, mmxrm, imm	SSSE3, MMX
PALIGNR	xmmreg, xmmrm, imm	SSSE3
PHADDW	mmxreg, mmxrm	SSSE3, MMX
PHADDW	xmmreg, xmmrm	SSSE3
PHADDD	mmxreg, mmxrm	SSSE3, MMX
PHADDD	xmmreg, xmmrm	SSSE3
PHADDSW	mmxreg, mmxrm	SSSE3, MMX
PHADDSW	xmmreg, xmmrm	SSSE3
PHSUBW	mmxreg, mmxrm	SSSE3, MMX
PHSUBW	xmmreg, xmmrm	SSSE3
PHSUBD	mmxreg, mmxrm	SSSE3, MMX
PHSUBD	xmmreg, xmmrm	SSSE3
PHSUBSW	mmxreg, mmxrm	SSSE3, MMX
PHSUBSW	xmmreg, xmmrm	SSSE3
PMADDUBSW	mmxreg, mmxrm	SSSE3, MMX

PMADDUBSW	xmmreg, xmmrm	SSSE3
PMULHRWSW	mmxreg, mmxrm	SSSE3, MMX
PMULHRSW	xmmreg, xmmrm	SSSE3
PSHUFB	mmxreg, mmxrm	SSSE3, MMX
PSHUFB	xmmreg, xmmrm	SSSE3
PSIGNB	mmxreg, mmxrm	SSSE3, MMX
PSIGNB	xmmreg, xmmrm	SSSE3
PSIGNW	mmxreg, mmxrm	SSSE3, MMX
PSIGNW	xmmreg, xmmrm	SSSE3
PSIGND	mmxreg, mmxrm	SSSE3, MMX
PSIGND	xmmreg, xmmrm	SSSE3

B.1.16 AMD SSE4A

EXTRQ	xmmreg, imm, imm	SSE4A, AMD
EXTRQ	xmmreg, xmmreg	SSE4A, AMD
INSERTQ	xmmreg, xmmreg, imm, imm	SSE4A, AMD
INSERTQ	xmmreg, xmmreg	SSE4A, AMD
MOVNTSD	mem, xmmreg	SSE4A, AMD
MOVNTSS	mem, xmmreg	SSE4A, AMD, SD

B.1.17 New instructions in Barcelona

LZCNT	reg16, rm16	P6, AMD
LZCNT	reg32, rm32	P6, AMD
LZCNT	reg64, rm64	X64, AMD

B.1.18 Penryn New Instructions (SSE4.1)

BLENDPD	xmmreg, xmmrm, imm	SSE41
BLENDPS	xmmreg, xmmrm, imm	SSE41
BLENDVPD	xmmreg, xmmrm, xmm0	SSE41
BLENDVPD	xmmreg, xmmrm	SSE41
BLENDVPS	xmmreg, xmmrm, xmm0	SSE41
BLENDVPS	xmmreg, xmmrm	SSE41
DPPD	xmmreg, xmmrm, imm	SSE41
DPPS	xmmreg, xmmrm, imm	SSE41
EXTRACTPS	rm32, xmmreg, imm	SSE41
EXTRACTPS	reg64, xmmreg, imm	SSE41, X64
INSERTPS	xmmreg, xmmrm, imm	SSE41, SD
MOVNTDQA	xmmreg, mem128	SSE41
MPSADBW	xmmreg, xmmrm, imm	SSE41
PACKUSDW	xmmreg, xmmrm	SSE41
PBLENDVB	xmmreg, xmmrm, xmm0	SSE41
PBLENDVB	xmmreg, xmmrm	SSE41
PBLENDW	xmmreg, xmmrm, imm	SSE41
PCMPEQQ	xmmreg, xmmrm	SSE41
PEXTRB	reg32, xmmreg, imm	SSE41
PEXTRB	mem8, xmmreg, imm	SSE41
PEXTRB	reg64, xmmreg, imm	SSE41, X64
PEXTRD	rm32, xmmreg, imm	SSE41
PEXTRQ	rm64, xmmreg, imm	SSE41, X64
PEXTRW	reg32, xmmreg, imm	SSE41
PEXTRW	mem16, xmmreg, imm	SSE41
PEXTRW	reg64, xmmreg, imm	SSE41, X64
PHMINPOSUW	xmmreg, xmmrm	SSE41

PINSRB	xmmreg,mem,imm	SSE41
PINSRB	xmmreg,rm8,imm	SSE41
PINSRB	xmmreg,reg32,imm	SSE41
PINSRD	xmmreg,mem,imm	SSE41
PINSRD	xmmreg,rm32,imm	SSE41
PINSRQ	xmmreg,mem,imm	SSE41,X64
PINSRQ	xmmreg,rm64,imm	SSE41,X64
PMAXSB	xmmreg,xmmrm	SSE41
PMAXSD	xmmreg,xmmrm	SSE41
PMAXUD	xmmreg,xmmrm	SSE41
PMAXUW	xmmreg,xmmrm	SSE41
PMINSB	xmmreg,xmmrm	SSE41
PMINSD	xmmreg,xmmrm	SSE41
PMINUD	xmmreg,xmmrm	SSE41
PMINUW	xmmreg,xmmrm	SSE41
PMOVSXBW	xmmreg,xmmrm	SSE41
PMOVSXBD	xmmreg,xmmrm	SSE41,SD
PMOVSXBQ	xmmreg,xmmrm	SSE41,SW
PMOVSXWD	xmmreg,xmmrm	SSE41
PMOVSXWQ	xmmreg,xmmrm	SSE41,SD
PMOVSXDQ	xmmreg,xmmrm	SSE41
PMOVZXBW	xmmreg,xmmrm	SSE41
PMOVZXBBD	xmmreg,xmmrm	SSE41,SD
PMOVZXBQ	xmmreg,xmmrm	SSE41,SW
PMOVZXWD	xmmreg,xmmrm	SSE41
PMOVZXWQ	xmmreg,xmmrm	SSE41,SD
PMOVZXDQ	xmmreg,xmmrm	SSE41
PMULDQ	xmmreg,xmmrm	SSE41
PMULLD	xmmreg,xmmrm	SSE41
PTEST	xmmreg,xmmrm	SSE41
ROUNDPD	xmmreg,xmmrm,imm	SSE41
ROUNDPS	xmmreg,xmmrm,imm	SSE41
ROUNDSD	xmmreg,xmmrm,imm	SSE41
ROUNDSS	xmmreg,xmmrm,imm	SSE41

B.1.19 Nehalem New Instructions (SSE4.2)

CRC32	reg32,rm8	SSE42
CRC32	reg32,rm16	SSE42
CRC32	reg32,rm32	SSE42
CRC32	reg64,rm8	SSE42,X64
CRC32	reg64,rm64	SSE42,X64
PCMPESTRI	xmmreg,xmmrm,imm	SSE42
PCMPESTRM	xmmreg,xmmrm,imm	SSE42
PCMPISTRI	xmmreg,xmmrm,imm	SSE42
PCMPISTRM	xmmreg,xmmrm,imm	SSE42
PCMPGTQ	xmmreg,xmmrm	SSE42
POPCNT	reg16,rm16	NEHALEM,SW
POPCNT	reg32,rm32	NEHALEM,SD
POPCNT	reg64,rm64	NEHALEM,X64

B.1.20 Intel SMX

GETSEC		KATMAI
--------	--	--------

B.1.21 Geode (Cyril) 3DNow! additions

PFRCPV	mmxreg,mmxrm	PENT,3DNOW,CYRIX
PFRSQRTV	mmxreg,mmxrm	PENT,3DNOW,CYRIX

B.1.22 Intel new instructions in ???

MOVBE	reg16,mem16	NEHALEM
MOVBE	reg32,mem32	NEHALEM
MOVBE	reg64,mem64	NEHALEM
MOVBE	mem16,reg16	NEHALEM
MOVBE	mem32,reg32	NEHALEM
MOVBE	mem64,reg64	NEHALEM

B.1.23 Intel AES instructions

AESENC	xmmreg,xmmrm128	SSE,WESTMERE
AESENCLAST	xmmreg,xmmrm128	SSE,WESTMERE
AESDEC	xmmreg,xmmrm128	SSE,WESTMERE
AESDECLAST	xmmreg,xmmrm128	SSE,WESTMERE
AESIMC	xmmreg,xmmrm128	SSE,WESTMERE
AESKEYGENASSIST	xmmreg,xmmrm128,imm8	SSE,WESTMERE

B.1.24 Intel AVX AES instructions

VAESENC	xmmreg,xmmreg*,xmmrm128	AVX,SANDYBRIDGE
VAESENCLAST	xmmreg,xmmreg*,xmmrm128	AVX,SANDYBRIDGE
VAESDEC	xmmreg,xmmreg*,xmmrm128	AVX,SANDYBRIDGE
VAESDECLAST	xmmreg,xmmreg*,xmmrm128	AVX,SANDYBRIDGE
VAESIMC	xmmreg,xmmrm128	AVX,SANDYBRIDGE
VAESKEYGENASSIST	xmmreg,xmmrm128,imm8	AVX,SANDYBRIDGE

B.1.25 Intel instruction extension based on pub number 319433-030 dated October 2017

VAESENC	ymmreg,ymmreg*,ymmrm256	VAES
VAESENCLAST	ymmreg,ymmreg*,ymmrm256	VAES
VAESDEC	ymmreg,ymmreg*,ymmrm256	VAES
VAESDECLAST	ymmreg,ymmreg*,ymmrm256	VAES
VAESENC	xmmreg,xmmreg*,xmmrm128	AVX512VL,VAES
VAESENC	ymmreg,ymmreg*,ymmrm256	AVX512VL,VAES
VAESENCLAST	xmmreg,xmmreg*,xmmrm128	AVX512VL,VAES
VAESENCLAST	ymmreg,ymmreg*,ymmrm256	AVX512VL,VAES
VAESDEC	xmmreg,xmmreg*,xmmrm128	AVX512VL,VAES
VAESDEC	ymmreg,ymmreg*,ymmrm256	AVX512VL,VAES
VAESDECLAST	xmmreg,xmmreg*,xmmrm128	AVX512VL,VAES
VAESDECLAST	ymmreg,ymmreg*,ymmrm256	AVX512VL,VAES
VAESENC	zmmreg,zmmreg*,zmmrm512	AVX512,VAES
VAESENCLAST	zmmreg,zmmreg*,zmmrm512	AVX512,VAES
VAESDEC	zmmreg,zmmreg*,zmmrm512	AVX512,VAES
VAESDECLAST	zmmreg,zmmreg*,zmmrm512	AVX512,VAES

B.1.26 Intel AVX instructions

VADDPD	xmmreg,xmmreg*,xmmrm128	AVX,SANDYBRIDGE
VADDPD	ymmreg,ymmreg*,ymmrm256	AVX,SANDYBRIDGE
VADDPD	xmmreg,xmmreg*,xmmrm128	AVX,SANDYBRIDGE
VADDPD	ymmreg,ymmreg*,ymmrm256	AVX,SANDYBRIDGE
VADDS	xmmreg,xmmreg*,xmmrm64	AVX,SANDYBRIDGE

VADDSS	xmmreg, xmmreg*, xmrm32	AVX, SANDYBRIDGE
VADDSUBPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VADDSUBPD	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VADDSUBPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VADDSUBPS	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VANDPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VANDPD	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VANDPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VANDPS	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VANDNPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VANDNPD	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VANDNPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VANDNPS	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VBLENDPD	xmmreg, xmmreg*, xmrm128, imm8	AVX, SANDYBRIDGE
VBLENDPD	yymmreg, yymmreg*, yymrm256, imm8	AVX, SANDYBRIDGE
VBLENDPS	xmmreg, xmmreg*, xmrm128, imm8	AVX, SANDYBRIDGE
VBLENDPS	yymmreg, yymmreg*, yymrm256, imm8	AVX, SANDYBRIDGE
VBLENDVPD	xmmreg, xmmreg*, xmrm128, xmmreg	AVX, SANDYBRIDGE
VBLENDVPD	yymmreg, yymmreg*, yymrm256, yymmreg	AVX, SANDYBRIDGE
VBLENDVPS	xmmreg, xmmreg*, xmrm128, xmmreg	AVX, SANDYBRIDGE
VBLENDVPS	yymmreg, yymmreg*, yymrm256, yymmreg	AVX, SANDYBRIDGE
VBROADCASTSS	xmmreg, mem32	AVX, SANDYBRIDGE
VBROADCASTSS	yymmreg, mem32	AVX, SANDYBRIDGE
VBROADCASTSD	yymmreg, mem64	AVX, SANDYBRIDGE
VBROADCASTF128	yymmreg, mem128	AVX, SANDYBRIDGE
VCMPEQ_OSPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPEQ_OSPD	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VCMPEQPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPEQPD	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VCMPLT_OSPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPLT_OSPD	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VCMPLTPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPLTPD	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VCMPLE_OSPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPLE_OSPD	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VCMPLEPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPLEPD	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VCMPUNORD_QPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPUNORD_QPD	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VCMPUNORDPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPUNORDPD	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VCMPNEQ_UQPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNEQ_UQPD	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VCMPNEQPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNEQPD	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VCMPNLT_USPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNLT_USPD	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VCMPNLTPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNLTPD	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VCMPNLE_USPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNLE_USPD	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VCMPNLEPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNLEPD	yymmreg, yymmreg*, yymrm256	AVX, SANDYBRIDGE
VCMPORD_QPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE

VCMPO RD_QPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCMPO RDPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCMPO RDPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCMPEQ_UQPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCMPEQ_UQPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P NGE_USPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P NGE_USPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P NGEPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P NGEPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P NGT_USPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P NGT_USPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P NGTPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P NGTPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P FALSE_OQPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P FALSE_OQPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P FALSEPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P FALSEPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P NEQ_OQPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P NEQ_OQPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P GE_OSPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P GE_OSPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P GEPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P GEPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P GT_OSPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P GT_OSPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P GTPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P GTPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P TRUE_UQPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P TRUE_UQPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P TRUEPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P TRUEPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCMPEQ_OSPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCMPEQ_OSPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCMPLT_OQPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCMPLT_OQPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCMPL E_OQPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCMPL E_OQPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P UNORD_SPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P UNORD_SPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P NEQ_USPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P NEQ_USPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P NLT_UQPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P NLT_UQPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P NLE_UQPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P NLE_UQPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCMPO RD_SPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCMPO RD_SPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCMPEQ_USPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCMPEQ_USPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P NGE_UQPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P NGE_UQPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P NGT_UQPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE
VCM P NGT_UQPD	y mmreg, y mmreg*, y mmrm256	AVX, SANDYBRIDGE
VCM P FALSE_OSPD	x mmreg, x mmreg*, x mmrm128	AVX, SANDYBRIDGE

VCMPFALSE_OSPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNEQ_OSPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNEQ_OSPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OQPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPGE_OQPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPGT_OQPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPGT_OQPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPTRUE_USPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPTRUE_USPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPDP	xmmreg, xmmreg*, xmrm128, imm8	AVX, SANDYBRIDGE
VCMPDP	ymmreg, ymmreg*, ymmrm256, imm8	AVX, SANDYBRIDGE
VCMPEQ_OSPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPEQ_OSPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPEQPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPEQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPLT_OSPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPLT_OSPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPLTPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPLTPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPLE_OSPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPLE_OSPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPLEPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPLEPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPUNORD_QPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPUNORD_QPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPUNORDPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPUNORDPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNEQ_UQPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNEQ_UQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNEQPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNEQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNLT_USPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNLT_USPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNLTPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNLTPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNLE_USPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNLE_USPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNLEPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNLEPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPORD_QPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPORD_QPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPORDPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPORDPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPEQ_UQPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPEQ_UQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNGE_USPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNGE_USPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNGEPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNGEPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNGT_USPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNGT_USPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNGTPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNGTPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPFALSE_OQPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE

VCMPFALSE_QQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPFALSEPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPFALSEPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNEQ_QQPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNEQ_QQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OSPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPGE_OSPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPGEP	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPGEP	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPGT_OSPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPGT_OSPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPGTSP	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPGTSP	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPTRUE_UQPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPTRUE_UQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPTRUEPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPTRUEPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPEQ_OSPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPEQ_OSPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPLT_QQPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPLT_QQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPLE_QQPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPLE_QQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPUNORD_SPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPUNORD_SPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNEQ_USPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNEQ_USPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNLT_UQPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNLT_UQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNLE_UQPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNLE_UQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPORD_SPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPORD_SPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPEQ_USPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPEQ_USPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNGE_UQPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNGE_UQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNGT_UQPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNGT_UQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPFALSE_OSPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPFALSE_OSPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNEQ_OSPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPNEQ_OSPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPGE_QQPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPGE_QQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPGT_QQPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPGT_QQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPTRUE_USPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VCMPTRUE_USPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPSP	xmmreg, xmmreg*, xmrm128, imm8	AVX, SANDYBRIDGE
VCMPSP	ymmreg, ymmreg*, ymmrm256, imm8	AVX, SANDYBRIDGE
VCMPEQ_OSSD	xmmreg, xmmreg*, xmrm64	AVX, SANDYBRIDGE
VCMPEQSD	xmmreg, xmmreg*, xmrm64	AVX, SANDYBRIDGE
VCMPLT_OSSD	xmmreg, xmmreg*, xmrm64	AVX, SANDYBRIDGE

VCMPLTSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLE_OSSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLESD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPUNORD_QSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPUNORDSSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNEQ_UQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNEQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNLT_USSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNLTSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNLE_USSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNLESD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPORD_QSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPORDSSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPEQ_UQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNGE_USSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNGESD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNGT_USSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNGTSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPFALSE_OQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPFALSESD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNEQ_OQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPGE_OSSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPGESD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPGT_OSSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPGTSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPTRUE_UQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPTRUESD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPEQ_OSSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLT_OQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLE_OQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPUNORD_SSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNEQ_USSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNLT_UQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNLE_UQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPORD_SSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPEQ_USSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNGE_UQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNGT_UQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPFALSE_OSSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNEQ_OSSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPGE_OQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPGT_OQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPTRUE_USSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPSD	xmmreg, xmmreg*, xmmrm64, imm8	AVX, SANDYBRIDGE
VCMPEQ_OSSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPEQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLT_OSSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLTSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLE_OSSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLESS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPUNORD_QSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPUNORDSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNEQ_UQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNEQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE

VCMPLT_USSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLTSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLNLE_USSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLNLESS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLORD_QSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLORDSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPEQ_UQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPGE_USSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPGESS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPNGT_USSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPNGTSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPFALSE_QQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPFALSESS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPNEQ_QQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPGE_OSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPGESS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPGT_OSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPGTSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPTRUE_UQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPTRUESS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPEQ_OSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPLT_QQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPLE_QQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPUNORD_SSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPNEQ_USSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPLT_UQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPLNLE_UQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPLORD_SSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPEQ_USSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPNGE_UQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPNGT_UQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPFALSE_OSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPNEQ_OSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPGE_QQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPGT_QQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPTRUE_USSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLPSS	xmmreg, xmmreg*, xmmrm64, imm8	AVX, SANDYBRIDGE
VCMPLISD	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VCMPLISS	xmmreg, xmmrm32	AVX, SANDYBRIDGE
VCMPLTDQ2PD	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VCMPLTDQ2PD	yymmreg, xmmrm128	AVX, SANDYBRIDGE
VCMPLTDQ2PS	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VCMPLTDQ2PS	yymmreg, yymmrm256	AVX, SANDYBRIDGE
VCMPLTPD2DQ	xmmreg, xmmreg	AVX, SANDYBRIDGE
VCMPLTPD2DQ	xmmreg, mem128	AVX, SANDYBRIDGE, SO
VCMPLTPD2DQ	xmmreg, yymmreg	AVX, SANDYBRIDGE
VCMPLTPD2DQ	xmmreg, mem256	AVX, SANDYBRIDGE, SY
VCMPLTPD2PS	xmmreg, xmmreg	AVX, SANDYBRIDGE
VCMPLTPD2PS	xmmreg, mem128	AVX, SANDYBRIDGE, SO
VCMPLTPD2PS	xmmreg, yymmreg	AVX, SANDYBRIDGE
VCMPLTPD2PS	xmmreg, mem256	AVX, SANDYBRIDGE, SY
VCMPLTPS2DQ	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VCMPLTPS2DQ	yymmreg, yymmrm256	AVX, SANDYBRIDGE
VCMPLTPS2PD	xmmreg, xmmrm64	AVX, SANDYBRIDGE

VCVTPS2PD	ymmreg, xmmrm128	AVX, SANDYBRIDGE
VCVTSD2SI	reg32, xmmrm64	AVX, SANDYBRIDGE
VCVTSD2SI	reg64, xmmrm64	AVX, SANDYBRIDGE, LONG
VCVTSD2SS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCVTSI2SD	xmmreg, xmmreg*, rm32	AVX, SANDYBRIDGE, SD
VCVTSI2SD	xmmreg, xmmreg*, mem32	AVX, SANDYBRIDGE, ND, SD
VCVTSI2SD	xmmreg, xmmreg*, rm64	AVX, SANDYBRIDGE, LONG
VCVTSI2SS	xmmreg, xmmreg*, rm32	AVX, SANDYBRIDGE, SD
VCVTSI2SS	xmmreg, xmmreg*, mem32	AVX, SANDYBRIDGE, ND, SD
VCVTSI2SS	xmmreg, xmmreg*, rm64	AVX, SANDYBRIDGE, LONG
VCVTSS2SD	xmmreg, xmmreg*, xmmrm32	AVX, SANDYBRIDGE
VCVTSS2SI	reg32, xmmrm32	AVX, SANDYBRIDGE
VCVTSS2SI	reg64, xmmrm32	AVX, SANDYBRIDGE, LONG
VCVTTPD2DQ	xmmreg, xmmreg	AVX, SANDYBRIDGE
VCVTTPD2DQ	xmmreg, mem128	AVX, SANDYBRIDGE, SO
VCVTTPD2DQ	xmmreg, ymmreg	AVX, SANDYBRIDGE
VCVTTPD2DQ	xmmreg, mem256	AVX, SANDYBRIDGE, SY
VCVTTPS2DQ	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VCVTTPS2DQ	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VCVTTSD2SI	reg32, xmmrm64	AVX, SANDYBRIDGE
VCVTTSD2SI	reg64, xmmrm64	AVX, SANDYBRIDGE, LONG
VCVTTSS2SI	reg32, xmmrm32	AVX, SANDYBRIDGE
VCVTTSS2SI	reg64, xmmrm32	AVX, SANDYBRIDGE, LONG
VDIVPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VDIVPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VDIVPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VDIVPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VDIVSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VDIVSS	xmmreg, xmmreg*, xmmrm32	AVX, SANDYBRIDGE
VDPPD	xmmreg, xmmreg*, xmmrm128, imm8	AVX, SANDYBRIDGE
VDPPS	xmmreg, xmmreg*, xmmrm128, imm8	AVX, SANDYBRIDGE
VDPPS	ymmreg, ymmreg*, ymmrm256, imm8	AVX, SANDYBRIDGE
VEXTRACTF128	xmmrm128, ymmreg, imm8	AVX, SANDYBRIDGE
VEXTRACTPS	rm32, xmmreg, imm8	AVX, SANDYBRIDGE
VHADDPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VHADDPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VHADDPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VHADDPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VHSDPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VHSDPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VHSDPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VHSDPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VINSERTF128	ymmreg, ymmreg*, xmmrm128, imm8	AVX, SANDYBRIDGE
VINSERTPS	xmmreg, xmmreg*, xmmrm32, imm8	AVX, SANDYBRIDGE
VLDQQU	xmmreg, mem128	AVX, SANDYBRIDGE
VLDQQU	ymmreg, mem256	AVX, SANDYBRIDGE
VLDQQU	ymmreg, mem256	AVX, SANDYBRIDGE
VLDMXCSR	mem32	AVX, SANDYBRIDGE
VMSKMOVDQU	xmmreg, xmmreg	AVX, SANDYBRIDGE
VMSKMOVPS	xmmreg, xmmreg, mem128	AVX, SANDYBRIDGE
VMSKMOVPS	ymmreg, ymmreg, mem256	AVX, SANDYBRIDGE
VMSKMOVPS	mem128, xmmreg, xmmreg	AVX, SANDYBRIDGE, SO
VMSKMOVPS	mem256, ymmreg, ymmreg	AVX, SANDYBRIDGE, SY
VMSKMOVPS	xmmreg, xmmreg, mem128	AVX, SANDYBRIDGE

VMSKMOVDPD	ymmreg, ymmreg, mem256	AVX, SANDYBRIDGE
VMSKMOVDPD	mem128, xmmreg, xmmreg	AVX, SANDYBRIDGE
VMSKMOVDPD	mem256, ymmreg, ymmreg	AVX, SANDYBRIDGE
VMAXPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VMAXPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VMAXPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VMAXPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VMAXSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VMAXSS	xmmreg, xmmreg*, xmmrm32	AVX, SANDYBRIDGE
VMINPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VMINPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VMINPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VMINPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VMINSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VMINSS	xmmreg, xmmreg*, xmmrm32	AVX, SANDYBRIDGE
VMOVAPD	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VMOVAPD	xmmrm128, xmmreg	AVX, SANDYBRIDGE
VMOVAPD	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVAPD	ymmrm256, ymmreg	AVX, SANDYBRIDGE
VMOVAPS	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VMOVAPS	xmmrm128, xmmreg	AVX, SANDYBRIDGE
VMOVAPS	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVAPS	ymmrm256, ymmreg	AVX, SANDYBRIDGE
VMOVD	xmmreg, rm32	AVX, SANDYBRIDGE
VMOVD	rm32, xmmreg	AVX, SANDYBRIDGE
VMOVQ	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VMOVQ	xmmrm64, xmmreg	AVX, SANDYBRIDGE
VMOVQ	xmmreg, rm64	AVX, SANDYBRIDGE, LONG
VMOVQ	rm64, xmmreg	AVX, SANDYBRIDGE, LONG
VMOVDDUP	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VMOVDDUP	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVQQA	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VMOVQQA	xmmrm128, xmmreg	AVX, SANDYBRIDGE
VMOVQQA	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVQQA	ymmrm256, ymmreg	AVX, SANDYBRIDGE
VMOVQQA	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVQQA	ymmrm256, ymmreg	AVX, SANDYBRIDGE
VMOVQQA	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVQQA	ymmrm256, ymmreg	AVX, SANDYBRIDGE
VMOVQQA	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVQQA	ymmrm256, ymmreg	AVX, SANDYBRIDGE
VMOVQQA	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVQQA	ymmrm256, ymmreg	AVX, SANDYBRIDGE
VMOVHPS	xmmreg, xmmreg*, xmmreg	AVX, SANDYBRIDGE
VMOVHPD	xmmreg, xmmreg*, mem64	AVX, SANDYBRIDGE
VMOVHPD	mem64, xmmreg	AVX, SANDYBRIDGE
VMOVHPS	xmmreg, xmmreg*, mem64	AVX, SANDYBRIDGE
VMOVHPS	mem64, xmmreg	AVX, SANDYBRIDGE
VMOVLPS	xmmreg, xmmreg*, xmmreg	AVX, SANDYBRIDGE
VMOVLPS	xmmreg, xmmreg*, mem64	AVX, SANDYBRIDGE
VMOVLPS	mem64, xmmreg	AVX, SANDYBRIDGE
VMOVLPS	xmmreg, xmmreg*, mem64	AVX, SANDYBRIDGE
VMOVLPS	mem64, xmmreg	AVX, SANDYBRIDGE
VMOVMSKPD	reg64, xmmreg	AVX, SANDYBRIDGE, LONG

VMOVMSKPD	reg32, xmmreg	AVX, SANDYBRIDGE
VMOVMSKPD	reg64, ymmreg	AVX, SANDYBRIDGE, LONG
VMOVMSKPD	reg32, ymmreg	AVX, SANDYBRIDGE
VMOVMSKPS	reg64, xmmreg	AVX, SANDYBRIDGE, LONG
VMOVMSKPS	reg32, xmmreg	AVX, SANDYBRIDGE
VMOVMSKPS	reg64, ymmreg	AVX, SANDYBRIDGE, LONG
VMOVMSKPS	reg32, ymmreg	AVX, SANDYBRIDGE
VMOVNTDQ	mem128, xmmreg	AVX, SANDYBRIDGE
VMOVNTQQ	mem256, ymmreg	AVX, SANDYBRIDGE
VMOVNTDQ	mem256, ymmreg	AVX, SANDYBRIDGE
VMOVNTDQA	xmmreg, mem128	AVX, SANDYBRIDGE
VMOVNTPD	mem128, xmmreg	AVX, SANDYBRIDGE
VMOVNTPD	mem256, ymmreg	AVX, SANDYBRIDGE
VMOVNTPS	mem128, xmmreg	AVX, SANDYBRIDGE
VMOVNTPS	mem256, ymmreg	AVX, SANDYBRIDGE
VMOVSD	xmmreg, xmmreg*, xmmreg	AVX, SANDYBRIDGE
VMOVSD	xmmreg, mem64	AVX, SANDYBRIDGE
VMOVSD	xmmreg, xmmreg*, xmmreg	AVX, SANDYBRIDGE
VMOVSD	mem64, xmmreg	AVX, SANDYBRIDGE
VMOVSHDUP	xmmreg, xmrm128	AVX, SANDYBRIDGE
VMOVSHDUP	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVSLDUP	xmmreg, xmrm128	AVX, SANDYBRIDGE
VMOVSLDUP	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVSS	xmmreg, xmmreg*, xmmreg	AVX, SANDYBRIDGE
VMOVSS	xmmreg, mem32	AVX, SANDYBRIDGE
VMOVSS	xmmreg, xmmreg*, xmmreg	AVX, SANDYBRIDGE
VMOVSS	mem32, xmmreg	AVX, SANDYBRIDGE
VMOVUPD	xmmreg, xmrm128	AVX, SANDYBRIDGE
VMOVUPD	xmrm128, xmmreg	AVX, SANDYBRIDGE
VMOVUPD	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVUPD	ymmrm256, ymmreg	AVX, SANDYBRIDGE
VMOVUPS	xmmreg, xmrm128	AVX, SANDYBRIDGE
VMOVUPS	xmrm128, xmmreg	AVX, SANDYBRIDGE
VMOVUPS	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVUPS	ymmrm256, ymmreg	AVX, SANDYBRIDGE
VMPSADBW	xmmreg, xmmreg*, xmrm128, imm8	AVX, SANDYBRIDGE
VMULPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VMULPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VMULPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VMULPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VMULSD	xmmreg, xmmreg*, xmrm64	AVX, SANDYBRIDGE
VMULSS	xmmreg, xmmreg*, xmrm32	AVX, SANDYBRIDGE
VORPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VORPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VORPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VORPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VPABSB	xmmreg, xmrm128	AVX, SANDYBRIDGE
VPABSW	xmmreg, xmrm128	AVX, SANDYBRIDGE
VPABSD	xmmreg, xmrm128	AVX, SANDYBRIDGE
VPACKSSWB	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPACKSSDW	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPACKUSWB	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPACKUSDW	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPADDB	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE

VPADDW	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPADD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPADDQ	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPADDSB	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPADDSW	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPADDUSB	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPADDUSW	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPALIGNR	xmmreg, xmmreg*, xmrm128, imm8	AVX, SANDYBRIDGE
VPAND	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPANDN	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPAVGB	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPAVGW	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPBLENDVB	xmmreg, xmmreg*, xmrm128, xmmreg	AVX, SANDYBRIDGE
VPBLENDW	xmmreg, xmmreg*, xmrm128, imm8	AVX, SANDYBRIDGE
VPCPESTRI	xmmreg, xmrm128, imm8	AVX, SANDYBRIDGE
VPCPESTRM	xmmreg, xmrm128, imm8	AVX, SANDYBRIDGE
VPCPISTRI	xmmreg, xmrm128, imm8	AVX, SANDYBRIDGE
VPCPISTRM	xmmreg, xmrm128, imm8	AVX, SANDYBRIDGE
VPCPEQB	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPCPEQW	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPCPEQD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPCPEQQ	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPCPGTB	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPCPGTW	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPCPGTD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPCPGTQ	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPERMILPD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPERMILPD	ymmreg, ymmreg*, ymrm256	AVX, SANDYBRIDGE
VPERMILPD	xmmreg, xmrm128, imm8	AVX, SANDYBRIDGE
VPERMILPD	ymmreg, ymrm256, imm8	AVX, SANDYBRIDGE
VPERMILPS	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPERMILPS	ymmreg, ymmreg*, ymrm256	AVX, SANDYBRIDGE
VPERMILPS	xmmreg, xmrm128, imm8	AVX, SANDYBRIDGE
VPERMILPS	ymmreg, ymrm256, imm8	AVX, SANDYBRIDGE
VPERM2F128	ymmreg, ymmreg*, ymrm256, imm8	AVX, SANDYBRIDGE
VPEXTRB	reg64, xmmreg, imm8	AVX, SANDYBRIDGE, LONG
VPEXTRB	reg32, xmmreg, imm8	AVX, SANDYBRIDGE
VPEXTRB	mem8, xmmreg, imm8	AVX, SANDYBRIDGE
VPEXTRW	reg64, xmmreg, imm8	AVX, SANDYBRIDGE, LONG
VPEXTRW	reg32, xmmreg, imm8	AVX, SANDYBRIDGE
VPEXTRW	reg64, xmmreg, imm8	AVX, SANDYBRIDGE, LONG
VPEXTRW	reg32, xmmreg, imm8	AVX, SANDYBRIDGE
VPEXTRW	mem16, xmmreg, imm8	AVX, SANDYBRIDGE
VPEXTRD	reg64, xmmreg, imm8	AVX, SANDYBRIDGE, LONG
VPEXTRD	rm32, xmmreg, imm8	AVX, SANDYBRIDGE
VPEXTRQ	rm64, xmmreg, imm8	AVX, SANDYBRIDGE, LONG
VPHADDW	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPHADD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPHADDSW	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPHMINPOSUW	xmmreg, xmrm128	AVX, SANDYBRIDGE
VPHSUBW	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPHSUBD	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPHSUBSW	xmmreg, xmmreg*, xmrm128	AVX, SANDYBRIDGE
VPINSRB	xmmreg, xmmreg*, mem8, imm8	AVX, SANDYBRIDGE

VPINSRB	xmmreg, xmmreg*, rm8, imm8	AVX, SANDYBRIDGE
VPINSRB	xmmreg, xmmreg*, reg32, imm8	AVX, SANDYBRIDGE
VPINSRW	xmmreg, xmmreg*, mem16, imm8	AVX, SANDYBRIDGE
VPINSRW	xmmreg, xmmreg*, rm16, imm8	AVX, SANDYBRIDGE
VPINSRW	xmmreg, xmmreg*, reg32, imm8	AVX, SANDYBRIDGE
VPINSRD	xmmreg, xmmreg*, mem32, imm8	AVX, SANDYBRIDGE
VPINSRD	xmmreg, xmmreg*, rm32, imm8	AVX, SANDYBRIDGE
VPINSRQ	xmmreg, xmmreg*, mem64, imm8	AVX, SANDYBRIDGE, LONG
VPINSRQ	xmmreg, xmmreg*, rm64, imm8	AVX, SANDYBRIDGE, LONG
VPMADDWD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMADDUBSW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMASB	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMASW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMASD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMASUB	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMASUW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMASUD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMINSB	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMINSW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMINSD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMINUB	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMINUW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMINUD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMOVMSKB	reg64, xmmreg	AVX, SANDYBRIDGE, LONG
VPMOVMSKB	reg32, xmmreg	AVX, SANDYBRIDGE
VPMOVXWB	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VPMOVXBD	xmmreg, xmmrm32	AVX, SANDYBRIDGE
VPMOVXBQ	xmmreg, xmmrm16	AVX, SANDYBRIDGE
VPMOVXWD	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VPMOVXWQ	xmmreg, xmmrm32	AVX, SANDYBRIDGE
VPMOVXDQ	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VPMOVZXBW	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VPMOVZxbd	xmmreg, xmmrm32	AVX, SANDYBRIDGE
VPMOVZXBQ	xmmreg, xmmrm16	AVX, SANDYBRIDGE
VPMOVZXWD	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VPMOVZXWQ	xmmreg, xmmrm32	AVX, SANDYBRIDGE
VPMOVZXDQ	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VPMULHUW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMULHRSW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMULHW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMULLW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMULLD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMULUDQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMULDQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPOR	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSADBW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSHUFb	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSHUFd	xmmreg, xmmrm128, imm8	AVX, SANDYBRIDGE
VPSHUFw	xmmreg, xmmrm128, imm8	AVX, SANDYBRIDGE
VPSHUFw	xmmreg, xmmrm128, imm8	AVX, SANDYBRIDGE
VPSIGNB	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSIGNW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSIGND	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSLLDQ	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE

VPSRLDQ	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPSLLW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSLLW	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPSLLD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSLLD	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPSLLQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSLLQ	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPSRAW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSRAW	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPSRAD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSRAD	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPSRLW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSRLW	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPSRLD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSRLD	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPSRLQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSRLQ	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPTEST	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VPTEST	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VPSUBB	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSUBW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSUBD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSUBQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSUBSB	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSUBSW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSUBUSB	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSUBUSW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPUNPCKHBW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPUNPCKHWD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPUNPCKHDQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPUNPCKHQDQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPUNPCKLBW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPUNPCKLWD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPUNPCKLDQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPUNPCKLQDQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPXOR	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VRCPPS	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VRCPPS	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VRCPS	xmmreg, xmmreg*, xmmrm32	AVX, SANDYBRIDGE
VRSQRTPS	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VRSQRTPS	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VRSQRTSS	xmmreg, xmmreg*, xmmrm32	AVX, SANDYBRIDGE
VRoundPD	xmmreg, xmmrm128, imm8	AVX, SANDYBRIDGE
VRoundPD	ymmreg, ymmrm256, imm8	AVX, SANDYBRIDGE
VRoundPS	xmmreg, xmmrm128, imm8	AVX, SANDYBRIDGE
VRoundPS	ymmreg, ymmrm256, imm8	AVX, SANDYBRIDGE
VRoundSD	xmmreg, xmmreg*, xmmrm64, imm8	AVX, SANDYBRIDGE
VRoundSS	xmmreg, xmmreg*, xmmrm32, imm8	AVX, SANDYBRIDGE
VSHUFPD	xmmreg, xmmreg*, xmmrm128, imm8	AVX, SANDYBRIDGE
VSHUFPD	ymmreg, ymmreg*, ymmrm256, imm8	AVX, SANDYBRIDGE
VSHUFPS	xmmreg, xmmreg*, xmmrm128, imm8	AVX, SANDYBRIDGE
VSHUFPS	ymmreg, ymmreg*, ymmrm256, imm8	AVX, SANDYBRIDGE
VSQRTPD	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VSQRTPD	ymmreg, ymmrm256	AVX, SANDYBRIDGE

VSQRTPS	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VSQRTPS	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VSQRTSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VSQRTSS	xmmreg, xmmreg*, xmmrm32	AVX, SANDYBRIDGE
VSTMXCSR	mem32	AVX, SANDYBRIDGE
VSUBPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VSUBPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VSUBPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VSUBPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VSUBSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VSUBSS	xmmreg, xmmreg*, xmmrm32	AVX, SANDYBRIDGE
VTESTPS	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VTESTPS	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VTESTPD	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VTESTPD	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VUCOMISD	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VUCOMISS	xmmreg, xmmrm32	AVX, SANDYBRIDGE
VUNPCKHPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VUNPCKHPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VUNPCKHPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VUNPCKHPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VUNPCKLPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VUNPCKLPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VUNPCKLPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VUNPCKLPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VXORPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VXORPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VXORPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VXORPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VZEROALL		AVX, SANDYBRIDGE
VZERoupper		AVX, SANDYBRIDGE

B.1.27 Intel Carry–Less Multiplication instructions (CLMUL)

PCLMULLQLQDQ	xmmreg, xmmrm128	SSE, WESTMERE
PCLMULHQLQDQ	xmmreg, xmmrm128	SSE, WESTMERE
PCLMULLQHQQDQ	xmmreg, xmmrm128	SSE, WESTMERE
PCLMULHQHQQDQ	xmmreg, xmmrm128	SSE, WESTMERE
PCLMULQDQ	xmmreg, xmmrm128, imm8	SSE, WESTMERE

B.1.28 Intel AVX Carry–Less Multiplication instructions (CLMUL)

VPCLMULLQLQDQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPCLMULHQLQDQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPCLMULLQHQQDQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPCLMULHQHQQDQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPCLMULQDQ	xmmreg, xmmreg*, xmmrm128, imm8	AVX, SANDYBRIDGE
VPCLMULLQLQDQ	ymmreg, ymmreg*, ymmrm256	VPCLMULQDQ
VPCLMULHQLQDQ	ymmreg, ymmreg*, ymmrm256	VPCLMULQDQ
VPCLMULLQHQQDQ	ymmreg, ymmreg*, ymmrm256	VPCLMULQDQ
VPCLMULHQHQQDQ	ymmreg, ymmreg*, ymmrm256	VPCLMULQDQ
VPCLMULQDQ	ymmreg, ymmreg*, ymmrm256, imm8	VPCLMULQDQ
VPCLMULLQLQDQ	xmmreg, xmmreg*, xmmrm128	AVX512VL, VPCLMULQDQ
VPCLMULHQLQDQ	xmmreg, xmmreg*, xmmrm128	AVX512VL, VPCLMULQDQ
VPCLMULLQHQQDQ	xmmreg, xmmreg*, xmmrm128	AVX512VL, VPCLMULQDQ

VPCLMULHQHQDQ	xmmreg, xmmreg*, xmmrm128	AVX512VL, VPCLMULQDQ
VPCLMULQDQ	xmmreg, xmmreg*, xmmrm128, imm8	AVX512VL, VPCLMULQDQ
VPCLMULLQLQDQ	ymmreg, ymmreg*, ymmrm256	AVX512VL, VPCLMULQDQ
VPCLMULHQHQDQ	ymmreg, ymmreg*, ymmrm256	AVX512VL, VPCLMULQDQ
VPCLMULLQHQQDQ	ymmreg, ymmreg*, ymmrm256	AVX512VL, VPCLMULQDQ
VPCLMULHQHQDQ	ymmreg, ymmreg*, ymmrm256	AVX512VL, VPCLMULQDQ
VPCLMULQDQ	ymmreg, ymmreg*, ymmrm256, imm8	AVX512VL, VPCLMULQDQ
VPCLMULLQLQDQ	zmmreg, zmmreg*, zmmrm512	AVX512, VPCLMULQDQ
VPCLMULHQHQDQ	zmmreg, zmmreg*, zmmrm512	AVX512, VPCLMULQDQ
VPCLMULLQHQQDQ	zmmreg, zmmreg*, zmmrm512	AVX512, VPCLMULQDQ
VPCLMULHQHQDQ	zmmreg, zmmreg*, zmmrm512	AVX512, VPCLMULQDQ
VPCLMULQDQ	zmmreg, zmmreg*, zmmrm512, imm8	AVX512, VPCLMULQDQ

B.1.29 Intel Fused Multiply–Add instructions (FMA)

VFMADD132PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADD132PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADD132PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADD132PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADD312PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADD312PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADD312PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADD312PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADD213PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADD213PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADD213PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADD213PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADD123PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADD123PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADD123PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADD123PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADD231PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADD231PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADD231PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADD231PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADD321PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADD321PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADD321PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADD321PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB132PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB132PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB132PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB132PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB312PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB312PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB312PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB312PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB213PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB213PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB213PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB213PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB123PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB123PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB123PD	xmmreg, xmmreg, xmmrm128	FMA

VFMADDSUB123PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB231PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB231PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB231PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB231PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB321PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB321PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB321PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB321PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB132PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB132PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB132PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB132PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB312PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB312PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB312PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB312PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB213PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB213PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB213PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB213PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB123PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB123PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB123PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB123PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB231PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB231PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB231PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB231PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB321PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB321PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB321PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB321PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD132PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD132PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD132PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD132PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD312PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD312PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD312PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD312PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD213PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD213PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD213PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD213PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD123PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD123PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD123PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD123PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD231PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD231PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD231PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD231PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD321PS	xmmreg, xmmreg, xmmrm128	FMA

VFMSUBADD321PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD321PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD321PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD132PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD132PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD132PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD132PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD312PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD312PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD312PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD312PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD213PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD213PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD213PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD213PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD123PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD123PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD123PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD123PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD231PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD231PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD231PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD231PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD321PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD321PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD321PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD321PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB132PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB132PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB132PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB132PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB312PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB312PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB312PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB312PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB213PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB213PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB213PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB213PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB123PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB123PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB123PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB123PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB231PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB231PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB231PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB231PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB321PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB321PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB321PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB321PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADD132SS	xmmreg, xmmreg, xmmrm32	FMA
VFMADD132SD	xmmreg, xmmreg, xmmrm64	FMA
VFMADD312SS	xmmreg, xmmreg, xmmrm32	FMA

VFMADD312SD	xmmreg, xmmreg, xmmrm64	FMA
VFMADD213SS	xmmreg, xmmreg, xmmrm32	FMA
VFMADD213SD	xmmreg, xmmreg, xmmrm64	FMA
VFMADD123SS	xmmreg, xmmreg, xmmrm32	FMA
VFMADD123SD	xmmreg, xmmreg, xmmrm64	FMA
VFMADD231SS	xmmreg, xmmreg, xmmrm32	FMA
VFMADD231SD	xmmreg, xmmreg, xmmrm64	FMA
VFMADD321SS	xmmreg, xmmreg, xmmrm32	FMA
VFMADD321SD	xmmreg, xmmreg, xmmrm64	FMA
VFMSUB132SS	xmmreg, xmmreg, xmmrm32	FMA
VFMSUB132SD	xmmreg, xmmreg, xmmrm64	FMA
VFMSUB312SS	xmmreg, xmmreg, xmmrm32	FMA
VFMSUB312SD	xmmreg, xmmreg, xmmrm64	FMA
VFMSUB213SS	xmmreg, xmmreg, xmmrm32	FMA
VFMSUB213SD	xmmreg, xmmreg, xmmrm64	FMA
VFMSUB123SS	xmmreg, xmmreg, xmmrm32	FMA
VFMSUB123SD	xmmreg, xmmreg, xmmrm64	FMA
VFMSUB231SS	xmmreg, xmmreg, xmmrm32	FMA
VFMSUB231SD	xmmreg, xmmreg, xmmrm64	FMA
VFMSUB321SS	xmmreg, xmmreg, xmmrm32	FMA
VFMSUB321SD	xmmreg, xmmreg, xmmrm64	FMA
VFNMADD132SS	xmmreg, xmmreg, xmmrm32	FMA
VFNMADD132SD	xmmreg, xmmreg, xmmrm64	FMA
VFNMADD312SS	xmmreg, xmmreg, xmmrm32	FMA
VFNMADD312SD	xmmreg, xmmreg, xmmrm64	FMA
VFNMADD213SS	xmmreg, xmmreg, xmmrm32	FMA
VFNMADD213SD	xmmreg, xmmreg, xmmrm64	FMA
VFNMADD123SS	xmmreg, xmmreg, xmmrm32	FMA
VFNMADD123SD	xmmreg, xmmreg, xmmrm64	FMA
VFNMADD231SS	xmmreg, xmmreg, xmmrm32	FMA
VFNMADD231SD	xmmreg, xmmreg, xmmrm64	FMA
VFNMADD321SS	xmmreg, xmmreg, xmmrm32	FMA
VFNMADD321SD	xmmreg, xmmreg, xmmrm64	FMA
VFNMSUB132SS	xmmreg, xmmreg, xmmrm32	FMA
VFNMSUB132SD	xmmreg, xmmreg, xmmrm64	FMA
VFNMSUB312SS	xmmreg, xmmreg, xmmrm32	FMA
VFNMSUB312SD	xmmreg, xmmreg, xmmrm64	FMA
VFNMSUB213SS	xmmreg, xmmreg, xmmrm32	FMA
VFNMSUB213SD	xmmreg, xmmreg, xmmrm64	FMA
VFNMSUB123SS	xmmreg, xmmreg, xmmrm32	FMA
VFNMSUB123SD	xmmreg, xmmreg, xmmrm64	FMA
VFNMSUB231SS	xmmreg, xmmreg, xmmrm32	FMA
VFNMSUB231SD	xmmreg, xmmreg, xmmrm64	FMA
VFNMSUB321SS	xmmreg, xmmreg, xmmrm32	FMA
VFNMSUB321SD	xmmreg, xmmreg, xmmrm64	FMA

B.1.30 Intel post-32 nm processor instructions

RDFSBASE	reg32	LONG
RDFSBASE	reg64	LONG
RDGSBASE	reg32	LONG
RDGSBASE	reg64	LONG
RDRAND	reg16	
RDRAND	reg32	

RDRAND	reg64	LONG
WRFSBASE	reg32	LONG
WRFSBASE	reg64	LONG
WRGSBASE	reg32	LONG
WRGSBASE	reg64	LONG
VCVTPH2PS	ymmreg, xmmrm128	AVX
VCVTPH2PS	xmmreg, xmmrm64	AVX
VCVTPS2PH	xmmrm128, ymmreg, imm8	AVX
VCVTPS2PH	xmmrm64, xmmreg, imm8	AVX
ADCX	reg32, rm32	
ADCX	reg64, rm64	LONG
ADOX	reg32, rm32	
ADOX	reg64, rm64	LONG
RDSEED	reg16	
RDSEED	reg32	
RDSEED	reg64	LONG
CLAC		PRIV
STAC		PRIV

B.1.31 VIA (Centaur) security instructions

XSTORE		PENT, CYRIX
XCRYPTECB		PENT, CYRIX
XCRYPTCBC		PENT, CYRIX
XCRYPTCTR		PENT, CYRIX
XCRYPTCFB		PENT, CYRIX
XCRYPTOFB		PENT, CYRIX
MONTMUL		PENT, CYRIX
XSHA1		PENT, CYRIX
XSHA256		PENT, CYRIX

B.1.32 AMD Lightweight Profiling (LWP) instructions

LLWPCB	reg32	AMD, 386
LLWPCB	reg64	AMD, X64
SLWPCB	reg32	AMD, 386
SLWPCB	reg64	AMD, X64
LWPVAL	reg32, rm32, imm32	AMD, 386
LWPVAL	reg64, rm32, imm32	AMD, X64
LWPINS	reg32, rm32, imm32	AMD, 386
LWPINS	reg64, rm32, imm32	AMD, X64

B.1.33 AMD XOP and FMA4 instructions (SSE5)

VFMADDPD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VFMADDPD	yymmreg, yymmreg*, ymmrm256, yymmreg	AMD, SSE5
VFMADDPD	xmmreg, xmmreg*, xmmreg, xmmrm128	AMD, SSE5
VFMADDPD	yymmreg, yymmreg*, yymmreg, ymmrm256	AMD, SSE5
VFMADDPD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VFMADDPD	yymmreg, yymmreg*, ymmrm256, yymmreg	AMD, SSE5
VFMADDPD	xmmreg, xmmreg*, xmmreg, xmmrm128	AMD, SSE5
VFMADDPD	yymmreg, yymmreg*, yymmreg, ymmrm256	AMD, SSE5
VFMADDS	xmmreg, xmmreg*, xmmrm64, xmmreg	AMD, SSE5
VFMADDS	xmmreg, xmmreg*, xmmreg, xmmrm64	AMD, SSE5
VFMADSS	xmmreg, xmmreg*, xmmrm32, xmmreg	AMD, SSE5
VFMADSS	xmmreg, xmmreg*, xmmreg, xmmrm32	AMD, SSE5

VFRCZPS	xmmreg, xmmrm128*	AMD, SSE5
VFRCZPS	ymmreg, ymmrm256*	AMD, SSE5
VFRCZSD	xmmreg, xmmrm64*	AMD, SSE5
VFRCZSS	xmmreg, xmmrm32*	AMD, SSE5
VPCMOV	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPCMOV	ymmreg, ymmreg*, ymmrm256, ymmreg	AMD, SSE5
VPCMOV	xmmreg, xmmreg*, xmmreg, xmmrm128	AMD, SSE5
VPCMOV	ymmreg, ymmreg*, ymmreg, ymmrm256	AMD, SSE5
VPCOMB	xmmreg, xmmreg*, xmmrm128, imm8	AMD, SSE5
VPCOMD	xmmreg, xmmreg*, xmmrm128, imm8	AMD, SSE5
VPCOMQ	xmmreg, xmmreg*, xmmrm128, imm8	AMD, SSE5
VPCOMUB	xmmreg, xmmreg*, xmmrm128, imm8	AMD, SSE5
VPCOMUD	xmmreg, xmmreg*, xmmrm128, imm8	AMD, SSE5
VPCOMUQ	xmmreg, xmmreg*, xmmrm128, imm8	AMD, SSE5
VPCOMUW	xmmreg, xmmreg*, xmmrm128, imm8	AMD, SSE5
VPCOMW	xmmreg, xmmreg*, xmmrm128, imm8	AMD, SSE5
VPHADDBD	xmmreg, xmmrm128*	AMD, SSE5
VPHADDBQ	xmmreg, xmmrm128*	AMD, SSE5
VPHADDBW	xmmreg, xmmrm128*	AMD, SSE5
VPHADDQ	xmmreg, xmmrm128*	AMD, SSE5
VPHADDUBD	xmmreg, xmmrm128*	AMD, SSE5
VPHADDUBQ	xmmreg, xmmrm128*	AMD, SSE5
VPHADDUBW	xmmreg, xmmrm128*	AMD, SSE5
VPHADDUDQ	xmmreg, xmmrm128*	AMD, SSE5
VPHADDUWD	xmmreg, xmmrm128*	AMD, SSE5
VPHADDUWQ	xmmreg, xmmrm128*	AMD, SSE5
VPHADDWD	xmmreg, xmmrm128*	AMD, SSE5
VPHADDWQ	xmmreg, xmmrm128*	AMD, SSE5
VPHSUBBW	xmmreg, xmmrm128*	AMD, SSE5
VPHSUBDQ	xmmreg, xmmrm128*	AMD, SSE5
VPHSUBWD	xmmreg, xmmrm128*	AMD, SSE5
VPMACSD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSDQH	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSDQL	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSSD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSSDQH	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSSDQL	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSSWD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSSW	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSWD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSW	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMADCSWD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMADCSWD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPPERM	xmmreg, xmmreg*, xmmreg, xmmrm128	AMD, SSE5
VPPERM	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPROTB	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPROTB	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPROTB	xmmreg, xmmrm128*, imm8	AMD, SSE5
VPROTD	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPROTD	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPROTD	xmmreg, xmmrm128*, imm8	AMD, SSE5
VPROTQ	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPROTQ	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPROTQ	xmmreg, xmmrm128*, imm8	AMD, SSE5

VPROTW	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPROTW	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPROTW	xmmreg, xmmrm128*, imm8	AMD, SSE5
VPSHAB	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPSHAB	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPSHAD	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPSHAD	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPSHAQ	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPSHAQ	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPSHAW	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPSHAW	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPSHLB	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPSHLB	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPSHLD	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPSHLD	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPSHLQ	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPSHLQ	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPSHLW	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPSHLW	xmmreg, xmmreg*, xmmrm128	AMD, SSE5

B.1.34 Intel AVX2 instructions

VMPADBWB	yymmreg, yymmreg*, ymmrm256, imm8	AVX2
VPABSB	yymmreg, ymmrm256	AVX2
VPABSW	yymmreg, ymmrm256	AVX2
VPABSD	yymmreg, ymmrm256	AVX2
VPACKSSWB	yymmreg, yymmreg*, ymmrm256	AVX2
VPACKSSDW	yymmreg, yymmreg*, ymmrm256	AVX2
VPACKUSDW	yymmreg, yymmreg*, ymmrm256	AVX2
VPACKUSWB	yymmreg, yymmreg*, ymmrm256	AVX2
VPADDB	yymmreg, yymmreg*, ymmrm256	AVX2
VPADDW	yymmreg, yymmreg*, ymmrm256	AVX2
VPADDD	yymmreg, yymmreg*, ymmrm256	AVX2
VPADDQ	yymmreg, yymmreg*, ymmrm256	AVX2
VPADDSB	yymmreg, yymmreg*, ymmrm256	AVX2
VPADDSW	yymmreg, yymmreg*, ymmrm256	AVX2
VPADDUSB	yymmreg, yymmreg*, ymmrm256	AVX2
VPADDUSW	yymmreg, yymmreg*, ymmrm256	AVX2
VPALIGNR	yymmreg, yymmreg*, ymmrm256, imm8	AVX2
VPAND	yymmreg, yymmreg*, ymmrm256	AVX2
VPANDN	yymmreg, yymmreg*, ymmrm256	AVX2
VPAVGB	yymmreg, yymmreg*, ymmrm256	AVX2
VPAVGW	yymmreg, yymmreg*, ymmrm256	AVX2
VPBLENDVB	yymmreg, yymmreg*, ymmrm256, yymmreg	AVX2
VPBLENDW	yymmreg, yymmreg*, ymmrm256, imm8	AVX2
VPCMPQB	yymmreg, yymmreg*, ymmrm256	AVX2
VPCMPQW	yymmreg, yymmreg*, ymmrm256	AVX2
VPCMPQD	yymmreg, yymmreg*, ymmrm256	AVX2
VPCMPQQ	yymmreg, yymmreg*, ymmrm256	AVX2
VPCMPGTB	yymmreg, yymmreg*, ymmrm256	AVX2
VPCMPGTW	yymmreg, yymmreg*, ymmrm256	AVX2
VPCMPGTD	yymmreg, yymmreg*, ymmrm256	AVX2
VPCMPGTQ	yymmreg, yymmreg*, ymmrm256	AVX2
VPHADDW	yymmreg, yymmreg*, ymmrm256	AVX2

VPHADD	ymmreg, ymmreg*, ymmrm256	AVX2
VPHADDSW	ymmreg, ymmreg*, ymmrm256	AVX2
VPHSUBW	ymmreg, ymmreg*, ymmrm256	AVX2
VPHSUBD	ymmreg, ymmreg*, ymmrm256	AVX2
VPHSUBSW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMADDUBSW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMADDWD	ymmreg, ymmreg*, ymmrm256	AVX2
VPMASB	ymmreg, ymmreg*, ymmrm256	AVX2
VPMASW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMASD	ymmreg, ymmreg*, ymmrm256	AVX2
VPMASUB	ymmreg, ymmreg*, ymmrm256	AVX2
VPMASUW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMASUD	ymmreg, ymmreg*, ymmrm256	AVX2
VPMINSB	ymmreg, ymmreg*, ymmrm256	AVX2
VPMINSW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMINSD	ymmreg, ymmreg*, ymmrm256	AVX2
VPMINUB	ymmreg, ymmreg*, ymmrm256	AVX2
VPMINUW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMINUD	ymmreg, ymmreg*, ymmrm256	AVX2
VPMOVMASKB	reg32, ymmreg	AVX2
VPMOVMASKB	reg64, ymmreg	AVX2
VPMOVSXBW	ymmreg, xmmrm128	AVX2
VPMOVSXBD	ymmreg, mem64	AVX2
VPMOVSXBD	ymmreg, xmmreg	AVX2
VPMOVSXBQ	ymmreg, mem32	AVX2
VPMOVSXBQ	ymmreg, xmmreg	AVX2
VPMOVSXWD	ymmreg, xmmrm128	AVX2
VPMOVSXWQ	ymmreg, mem64	AVX2
VPMOVSXWQ	ymmreg, xmmreg	AVX2
VPMOVSXDQ	ymmreg, xmmrm128	AVX2
VPMOVZXBW	ymmreg, xmmrm128	AVX2
VPMOVZXBW	ymmreg, mem64	AVX2
VPMOVZXBW	ymmreg, xmmreg	AVX2
VPMOVZXBQ	ymmreg, mem32	AVX2
VPMOVZXBQ	ymmreg, xmmreg	AVX2
VPMOVZXWD	ymmreg, xmmrm128	AVX2
VPMOVZXWQ	ymmreg, mem64	AVX2
VPMOVZXWQ	ymmreg, xmmreg	AVX2
VPMOVZXDQ	ymmreg, xmmrm128	AVX2
VPMULDQ	ymmreg, ymmreg*, ymmrm256	AVX2
VPMULHSW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMULHW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMULHW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMULLW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMULLD	ymmreg, ymmreg*, ymmrm256	AVX2
VPMULUDQ	ymmreg, ymmreg*, ymmrm256	AVX2
VPOR	ymmreg, ymmreg*, ymmrm256	AVX2
VPSADBW	ymmreg, ymmreg*, ymmrm256	AVX2
VPSHUF	ymmreg, ymmreg*, ymmrm256	AVX2
VPSHUF	ymmreg, ymmrm256, imm8	AVX2
VPSHUFHW	ymmreg, ymmrm256, imm8	AVX2
VPSHUFHW	ymmreg, ymmrm256, imm8	AVX2
VPSIGNB	ymmreg, ymmreg*, ymmrm256	AVX2
VPSIGNW	ymmreg, ymmreg*, ymmrm256	AVX2

VPSIGND	ymmreg,ymmreg*,ymmrm256	AVX2
VPSLLDQ	ymmreg,ymmreg*,imm8	AVX2
VPSLLW	ymmreg,ymmreg*,xmmrm128	AVX2
VPSLLW	ymmreg,ymmreg*,imm8	AVX2
VPSLLD	ymmreg,ymmreg*,xmmrm128	AVX2
VPSLLD	ymmreg,ymmreg*,imm8	AVX2
VPSLLQ	ymmreg,ymmreg*,xmmrm128	AVX2
VPSLLQ	ymmreg,ymmreg*,imm8	AVX2
VPSRAW	ymmreg,ymmreg*,xmmrm128	AVX2
VPSRAW	ymmreg,ymmreg*,imm8	AVX2
VPSRAD	ymmreg,ymmreg*,xmmrm128	AVX2
VPSRAD	ymmreg,ymmreg*,imm8	AVX2
VPSRLDQ	ymmreg,ymmreg*,imm8	AVX2
VPSRLW	ymmreg,ymmreg*,xmmrm128	AVX2
VPSRLW	ymmreg,ymmreg*,imm8	AVX2
VPSRLD	ymmreg,ymmreg*,xmmrm128	AVX2
VPSRLD	ymmreg,ymmreg*,imm8	AVX2
VPSRLQ	ymmreg,ymmreg*,xmmrm128	AVX2
VPSRLQ	ymmreg,ymmreg*,imm8	AVX2
VPSUBB	ymmreg,ymmreg*,ymmrm256	AVX2
VPSUBW	ymmreg,ymmreg*,ymmrm256	AVX2
VPSUBD	ymmreg,ymmreg*,ymmrm256	AVX2
VPSUBQ	ymmreg,ymmreg*,ymmrm256	AVX2
VPSUBSB	ymmreg,ymmreg*,ymmrm256	AVX2
VPSUBSW	ymmreg,ymmreg*,ymmrm256	AVX2
VPSUBUSB	ymmreg,ymmreg*,ymmrm256	AVX2
VPSUBUSW	ymmreg,ymmreg*,ymmrm256	AVX2
VPUNPCKHBW	ymmreg,ymmreg*,ymmrm256	AVX2
VPUNPCKHWD	ymmreg,ymmreg*,ymmrm256	AVX2
VPUNPCKHQDQ	ymmreg,ymmreg*,ymmrm256	AVX2
VPUNPCKHQDQ	ymmreg,ymmreg*,ymmrm256	AVX2
VPUNPCKLBW	ymmreg,ymmreg*,ymmrm256	AVX2
VPUNPCKLWD	ymmreg,ymmreg*,ymmrm256	AVX2
VPUNPCKLDQ	ymmreg,ymmreg*,ymmrm256	AVX2
VPUNPCKLQDQ	ymmreg,ymmreg*,ymmrm256	AVX2
VPXOR	ymmreg,ymmreg*,ymmrm256	AVX2
VMOVNTDQA	ymmreg,mem256	AVX2
VBROADCASTSS	xmmreg,xmmreg	AVX2
VBROADCASTSS	ymmreg,xmmreg	AVX2
VBROADCASTSD	ymmreg,xmmreg	AVX2
VBROADCASTI128	ymmreg,mem128	AVX2
VPBLENDQ	xmmreg,xmmreg*,xmmrm128,imm8	AVX2
VPBLENDQ	ymmreg,ymmreg*,ymmrm256,imm8	AVX2
VPBROADCASTB	xmmreg,mem8	AVX2
VPBROADCASTB	xmmreg,xmmreg	AVX2
VPBROADCASTB	ymmreg,mem8	AVX2
VPBROADCASTB	ymmreg,xmmreg	AVX2
VPBROADCASTW	xmmreg,mem16	AVX2
VPBROADCASTW	xmmreg,xmmreg	AVX2
VPBROADCASTW	ymmreg,mem16	AVX2
VPBROADCASTW	ymmreg,xmmreg	AVX2
VPBROADCASTD	xmmreg,mem32	AVX2
VPBROADCASTD	xmmreg,xmmreg	AVX2
VPBROADCASTD	ymmreg,mem32	AVX2

VPBROADCASTD	ymmreg, xmmreg	AVX2
VPBROADCASTQ	xmmreg, mem64	AVX2
VPBROADCASTQ	xmmreg, xmmreg	AVX2
VPBROADCASTQ	ymmreg, mem64	AVX2
VPBROADCASTQ	ymmreg, xmmreg	AVX2
VPERMD	ymmreg, ymmreg*, ymmrm256	AVX2
VPERMPD	ymmreg, ymmrm256, imm8	AVX2
VPERMPS	ymmreg, ymmreg*, ymmrm256	AVX2
VPERMQ	ymmreg, ymmrm256, imm8	AVX2
VPERM2I128	ymmreg, ymmreg*, ymmrm256, imm8	AVX2
VEEXTRACTI128	xmmrm128, ymmreg, imm8	AVX2
VINSERTI128	ymmreg, ymmreg*, xmmrm128, imm8	AVX2
VPMASKMOVD	xmmreg, xmmreg*, mem128	AVX2
VPMASKMOVD	ymmreg, ymmreg*, mem256	AVX2
VPMASKMOVQ	xmmreg, xmmreg*, mem128	AVX2
VPMASKMOVQ	ymmreg, ymmreg*, mem256	AVX2
VPMASKMOVD	mem128, xmmreg*, xmmreg	AVX2
VPMASKMOVD	mem256, ymmreg*, ymmreg	AVX2
VPMASKMOVQ	mem128, xmmreg*, xmmreg	AVX2
VPMASKMOVQ	mem256, ymmreg*, ymmreg	AVX2
VPSLLVD	xmmreg, xmmreg*, xmmrm128	AVX2
VPSLLVQ	xmmreg, xmmreg*, xmmrm128	AVX2
VPSLLVD	ymmreg, ymmreg*, ymmrm256	AVX2
VPSLLVQ	ymmreg, ymmreg*, ymmrm256	AVX2
VPSRAVD	xmmreg, xmmreg*, xmmrm128	AVX2
VPSRAVD	ymmreg, ymmreg*, ymmrm256	AVX2
VPSRLVD	xmmreg, xmmreg*, xmmrm128	AVX2
VPSRLVQ	xmmreg, xmmreg*, xmmrm128	AVX2
VPSRLVD	ymmreg, ymmreg*, ymmrm256	AVX2
VPSRLVQ	ymmreg, ymmreg*, ymmrm256	AVX2
VGATHERDPD	xmmreg, xmem64, xmmreg	AVX2
VGATHERQPD	xmmreg, xmem64, xmmreg	AVX2
VGATHERDPD	ymmreg, xmem64, ymmreg	AVX2
VGATHERQPD	ymmreg, ymem64, ymmreg	AVX2
VGATHERDPS	xmmreg, xmem32, xmmreg	AVX2
VGATHERQPS	xmmreg, xmem32, xmmreg	AVX2
VGATHERDPS	ymmreg, ymem32, ymmreg	AVX2
VGATHERQPS	xmmreg, ymem32, xmmreg	AVX2
VPGATHERDD	xmmreg, xmem32, xmmreg	AVX2
VPGATHERQD	xmmreg, xmem32, xmmreg	AVX2
VPGATHERDD	ymmreg, ymem32, ymmreg	AVX2
VPGATHERQD	xmmreg, ymem32, xmmreg	AVX2
VPGATHERDQ	xmmreg, xmem64, xmmreg	AVX2
VPGATHERQQ	xmmreg, xmem64, xmmreg	AVX2
VPGATHERDQ	ymmreg, xmem64, ymmreg	AVX2
VPGATHERQQ	ymmreg, ymem64, ymmreg	AVX2

B.1.35 Intel Transactional Synchronization Extensions (TSX)

XABORT	imm	RTM
XABORT	imm8	RTM
XBEGIN	imm	RTM
XBEGIN	imm near	RTM, ND
XBEGIN	imm16	RTM, NOLONG

XBEGIN	imm16 near	RTM,NOLONG,ND
XBEGIN	imm32	RTM,NOLONG
XBEGIN	imm32 near	RTM,NOLONG,ND
XBEGIN	imm64	RTM, LONG
XBEGIN	imm64 near	RTM, LONG, ND
XEND		RTM
XTEST		HLE, RTM

B.1.36 Intel BMI1 and BMI2 instructions, AMD TBM instructions

ANDN	reg32, reg32, rm32	BMI1
ANDN	reg64, reg64, rm64	LONG, BMI1
BEXTR	reg32, rm32, reg32	BMI1
BEXTR	reg64, rm64, reg64	LONG, BMI1
BEXTR	reg32, rm32, imm32	TBM
BEXTR	reg64, rm64, imm32	LONG, TBM
BLCI	reg32, rm32	TBM
BLCI	reg64, rm64	LONG, TBM
BLCIC	reg32, rm32	TBM
BLCIC	reg64, rm64	LONG, TBM
BLSI	reg32, rm32	BMI1
BLSI	reg64, rm64	LONG, BMI1
BLSIC	reg32, rm32	TBM
BLSIC	reg64, rm64	LONG, TBM
BLCFILL	reg32, rm32	TBM
BLCFILL	reg64, rm64	LONG, TBM
BLSFILL	reg32, rm32	TBM
BLSFILL	reg64, rm64	LONG, TBM
BLCMSK	reg32, rm32	TBM
BLCMSK	reg64, rm64	LONG, TBM
BLSMSK	reg32, rm32	BMI1
BLSMSK	reg64, rm64	LONG, BMI1
BLSR	reg32, rm32	BMI1
BLSR	reg64, rm64	LONG, BMI1
BLCS	reg32, rm32	TBM
BLCS	reg64, rm64	LONG, TBM
BZHI	reg32, rm32, reg32	BMI2
BZHI	reg64, rm64, reg64	LONG, BMI2
MULX	reg32, reg32, rm32	BMI2
MULX	reg64, reg64, rm64	LONG, BMI2
PDEP	reg32, reg32, rm32	BMI2
PDEP	reg64, reg64, rm64	LONG, BMI2
PEXT	reg32, reg32, rm32	BMI2
PEXT	reg64, reg64, rm64	LONG, BMI2
RORX	reg32, rm32, imm8	BMI2
RORX	reg64, rm64, imm8	LONG, BMI2
SARX	reg32, rm32, reg32	BMI2
SARX	reg64, rm64, reg64	LONG, BMI2
SHLX	reg32, rm32, reg32	BMI2
SHLX	reg64, rm64, reg64	LONG, BMI2
SHRX	reg32, rm32, reg32	BMI2
SHRX	reg64, rm64, reg64	LONG, BMI2
TZCNT	reg16, rm16	BMI1
TZCNT	reg32, rm32	BMI1

TZCNT	reg64,rm64	LONG,BMI1
TZMSK	reg32,rm32	TBM
TZMSK	reg64,rm64	LONG,TBM
T1MSKC	reg32,rm32	TBM
T1MSKC	reg64,rm64	LONG,TBM
PREFETCHWT1	mem8	PREFETCHWT1

B.1.37 Intel Memory Protection Extensions (MPX)

BNDMK	bndreg,mem	MPX,MIB
BNDCL	bndreg,mem	MPX
BNDCL	bndreg,reg32	MPX,NOLONG
BNDCL	bndreg,reg64	MPX, LONG
BNDCU	bndreg,mem	MPX
BNDCU	bndreg,reg32	MPX,NOLONG
BNDCU	bndreg,reg64	MPX, LONG
BNDCN	bndreg,mem	MPX
BNDCN	bndreg,reg32	MPX,NOLONG
BNDCN	bndreg,reg64	MPX, LONG
BNDMOV	bndreg,bndreg	MPX
BNDMOV	bndreg,mem	MPX
BNDMOV	bndreg,bndreg	MPX
BNDMOV	mem,bndreg	MPX
BNDLDX	bndreg,mem	MPX,MIB
BNDLDX	bndreg,mem,reg32	MPX,MIB,NOLONG
BNDLDX	bndreg,mem,reg64	MPX,MIB, LONG
BNDSTX	mem,bndreg	MPX,MIB
BNDSTX	mem,reg32,bndreg	MPX,MIB,NOLONG
BNDSTX	mem,reg64,bndreg	MPX,MIB, LONG
BNDSTX	mem,bndreg,reg32	MPX,MIB,NOLONG
BNDSTX	mem,bndreg,reg64	MPX,MIB, LONG

B.1.38 Intel SHA acceleration instructions

SHA1MSG1	xmmreg,xmmrm128	SHA
SHA1MSG2	xmmreg,xmmrm128	SHA
SHA1NEXTE	xmmreg,xmmrm128	SHA
SHA1RND4	xmmreg,xmmrm128,imm8	SHA
SHA256MSG1	xmmreg,xmmrm128	SHA
SHA256MSG2	xmmreg,xmmrm128	SHA
SHA256RND2	xmmreg,xmmrm128,xmm0	SHA
SHA256RND2	xmmreg,xmmrm128	SHA

B.1.39 AVX-512 mask register instructions

KADDB	kreg,kreg,kreg
KADDD	kreg,kreg,kreg
KADDQ	kreg,kreg,kreg
KADDW	kreg,kreg,kreg
KANDB	kreg,kreg,kreg
KANDD	kreg,kreg,kreg
KANDNB	kreg,kreg,kreg
KANDND	kreg,kreg,kreg
KANDNQ	kreg,kreg,kreg
KANDNW	kreg,kreg,kreg
KANDQ	kreg,kreg,kreg

KANDW	kreg, kreg, kreg	
KMOVB	kreg, krm8	
KMOVB	mem8, kreg	
KMOVB	kreg, reg32	
KMOVB	kreg, reg8	ND
KMOVB	reg32, kreg	
KMOVD	kreg, krm32	
KMOVD	mem32, kreg	
KMOVD	kreg, reg32	
KMOVD	reg32, kreg	
KMOVQ	kreg, krm64	
KMOVQ	mem64, kreg	
KMOVQ	kreg, reg64	
KMOVQ	reg64, kreg	
KMOVW	kreg, krm16	
KMOVW	mem16, kreg	
KMOVW	kreg, reg32	
KMOVW	kreg, reg16	ND
KMOVW	reg32, kreg	
KNOTB	kreg, kreg	
KNOTD	kreg, kreg	
KNOTQ	kreg, kreg	
KNOTW	kreg, kreg	
KORB	kreg, kreg, kreg	
KORD	kreg, kreg, kreg	
KORQ	kreg, kreg, kreg	
KORW	kreg, kreg, kreg	
KORTESTB	kreg, kreg	
KORTESTD	kreg, kreg	
KORTESTQ	kreg, kreg	
KORTESTW	kreg, kreg	
KSHIFTLB	kreg, kreg, imm8	
KSHIFTLD	kreg, kreg, imm8	
KSHIFTLQ	kreg, kreg, imm8	
KSHIFTLW	kreg, kreg, imm8	
KSHIFTRB	kreg, kreg, imm8	
KSHIFTRD	kreg, kreg, imm8	
KSHIFTRQ	kreg, kreg, imm8	
KSHIFTRW	kreg, kreg, imm8	
KTESTB	kreg, kreg	
KTESTD	kreg, kreg	
KTESTQ	kreg, kreg	
KTESTW	kreg, kreg	
KUNPCKBW	kreg, kreg, kreg	
KUNPCKDQ	kreg, kreg, kreg	
KUNPCKWD	kreg, kreg, kreg	
KXNORB	kreg, kreg, kreg	
KXNORD	kreg, kreg, kreg	
KXNORQ	kreg, kreg, kreg	
KXNORW	kreg, kreg, kreg	
KXORB	kreg, kreg, kreg	
KXORD	kreg, kreg, kreg	
KXORQ	kreg, kreg, kreg	
KXORW	kreg, kreg, kreg	

B.1.40 AVX-512 mask register instructions (aliases requiring explicit size support)

KADD	kreg8, kreg, kreg	ND
KADD	kreg32, kreg, kreg	ND
KADD	kreg64, kreg, kreg	ND
KADD	kreg16, kreg, kreg	ND
KAND	kreg8, kreg, kreg	ND
KAND	kreg32, kreg, kreg	ND
KANDN	kreg64, kreg, kreg	ND
KANDN	kreg16, kreg, kreg	ND
KANDN	kreg8, kreg, kreg	ND
KANDN	kreg32, kreg, kreg	ND
KAND	kreg64, kreg, kreg	ND
KAND	kreg16, kreg, kreg	ND
KMOV	kreg8, krm8	ND
KMOV	mem8, kreg8	ND
KMOV	kreg8, reg32	ND, SX
KMOV	kreg8, reg8	ND
KMOV	reg32, kreg8	ND, SX
KMOV	kreg32, krm32	ND
KMOV	mem32, kreg32	ND
KMOV	kreg32, reg32	ND
KMOV	reg32, kreg32	ND
KMOV	kreg64, krm64	ND
KMOV	mem64, kreg64	ND
KMOV	kreg64, reg64	ND
KMOV	reg64, kreg64	ND
KMOV	kreg16, krm16	ND
KMOV	mem16, kreg16	ND
KMOV	kreg16, reg32	ND, SX
KMOV	reg32, kreg16	ND, SX
KMOV	kreg16, reg32	ND, SX
KMOV	kreg16, reg16	ND
KNOT	kreg8, kreg8	ND
KNOT	kreg32, kreg32	ND
KNOT	kreg64, kreg64	ND
KNOT	kreg16, kreg16	ND
KOR	kreg8, kreg, kreg	ND
KOR	kreg32, kreg, kreg	ND
KOR	kreg64, kreg, kreg	ND
KOR	kreg16, kreg, kreg	ND
KORTEST	kreg8, kreg	ND
KORTEST	kreg32, kreg	ND
KORTEST	kreg64, kreg	ND
KORTEST	kreg16, kreg	ND
KSHIFTL	kreg8, kreg, imm8	ND
KSHIFTL	kreg32, kreg, imm8	ND
KSHIFTL	kreg64, kreg, imm8	ND
KSHIFTL	kreg16, kreg, imm8	ND
KSHIFTR	kreg8, kreg, imm8	ND
KSHIFTR	kreg32, kreg, imm8	ND
KSHIFTR	kreg64, kreg, imm8	ND
KSHIFTR	kreg16, kreg, imm8	ND
KTEST	kreg8, kreg	ND

KTEST	kreg32, kreg	ND
KTEST	kreg64, kreg	ND
KTEST	kreg16, kreg	ND
KUNPCK	kreg16, kreg8, kreg8	ND
KUNPCK	kreg64, kreg32, kreg32	ND
KUNPCK	kreg32, kreg16, kreg16	ND
KXNOR	kreg8, kreg, kreg	ND
KXNOR	kreg32, kreg, kreg	ND
KXNOR	kreg64, kreg, kreg	ND
KXNOR	kreg16, kreg, kreg	ND
KXOR	kreg8, kreg, kreg	ND
KXOR	kreg32, kreg, kreg	ND
KXOR	kreg64, kreg, kreg	ND
KXOR	kreg16, kreg, kreg	ND

B.1.41 AVX-512 instructions

VADDPD	xmmreg mask z, xmmreg*, xmmrm128 b64	AVX512VL
VADDPD	yymmreg mask z, yymmreg*, ymmrm256 b64	AVX512VL
VADDPD	zmmreg mask z, zmmreg*, zmmrm512 b64 er	AVX512
VADDPD	xmmreg mask z, xmmreg*, xmmrm128 b32	AVX512VL
VADDPD	yymmreg mask z, yymmreg*, ymmrm256 b32	AVX512VL
VADDPD	zmmreg mask z, zmmreg*, zmmrm512 b32 er	AVX512
VADDS	xmmreg mask z, xmmreg*, xmmrm64 er	AVX512
VADDS	xmmreg mask z, xmmreg*, xmmrm32 er	AVX512
VALIGND	xmmreg mask z, xmmreg*, xmmrm128 b32, imm8	AVX512VL
VALIGND	yymmreg mask z, yymmreg*, ymmrm256 b32, imm8	AVX512VL
VALIGND	zmmreg mask z, zmmreg*, zmmrm512 b32, imm8	AVX512
VALIGNQ	xmmreg mask z, xmmreg*, xmmrm128 b64, imm8	AVX512VL
VALIGNQ	yymmreg mask z, yymmreg*, ymmrm256 b64, imm8	AVX512VL
VALIGNQ	zmmreg mask z, zmmreg*, zmmrm512 b64, imm8	AVX512
VANDNPD	xmmreg mask z, xmmreg*, xmmrm128 b64	AVX512VL/DQ
VANDNPD	yymmreg mask z, yymmreg*, ymmrm256 b64	AVX512VL/DQ
VANDNPD	zmmreg mask z, zmmreg*, zmmrm512 b64	AVX512DQ
VANDNPS	xmmreg mask z, xmmreg*, xmmrm128 b32	AVX512VL/DQ
VANDNPS	yymmreg mask z, yymmreg*, ymmrm256 b32	AVX512VL/DQ
VANDNPS	zmmreg mask z, zmmreg*, zmmrm512 b32	AVX512DQ
VANDPD	xmmreg mask z, xmmreg*, xmmrm128 b64	AVX512VL/DQ
VANDPD	yymmreg mask z, yymmreg*, ymmrm256 b64	AVX512VL/DQ
VANDPD	zmmreg mask z, zmmreg*, zmmrm512 b64	AVX512DQ
VANDPS	xmmreg mask z, xmmreg*, xmmrm128 b32	AVX512VL/DQ
VANDPS	yymmreg mask z, yymmreg*, ymmrm256 b32	AVX512VL/DQ
VANDPS	zmmreg mask z, zmmreg*, zmmrm512 b32	AVX512DQ
VBLENDMPD	xmmreg mask z, xmmreg, xmmrm128 b64	AVX512VL
VBLENDMPD	yymmreg mask z, yymmreg, ymmrm256 b64	AVX512VL
VBLENDMPD	zmmreg mask z, zmmreg, zmmrm512 b64	AVX512
VBLENDMPS	xmmreg mask z, xmmreg, xmmrm128 b32	AVX512VL
VBLENDMPS	yymmreg mask z, yymmreg, ymmrm256 b32	AVX512VL
VBLENDMPS	zmmreg mask z, zmmreg, zmmrm512 b32	AVX512
VBROADCASTF32X2	yymmreg mask z, xmmrm64	AVX512VL/DQ
VBROADCASTF32X2	zmmreg mask z, xmmrm64	AVX512DQ
VBROADCASTF32X4	yymmreg mask z, mem128	AVX512VL
VBROADCASTF32X4	zmmreg mask z, mem128	AVX512
VBROADCASTF32X8	zmmreg mask z, mem256	AVX512DQ

VBROADCASTF64X2	ymmreg mask z,mem128	AVX512VL/DQ
VBROADCASTF64X2	zmmreg mask z,mem128	AVX512DQ
VBROADCASTF64X4	zmmreg mask z,mem256	AVX512
VBROADCASTI32X2	xmmreg mask z,xmmrm64	AVX512VL/DQ
VBROADCASTI32X2	ymmreg mask z,xmmrm64	AVX512VL/DQ
VBROADCASTI32X2	zmmreg mask z,xmmrm64	AVX512DQ
VBROADCASTI32X4	ymmreg mask z,mem128	AVX512VL
VBROADCASTI32X4	zmmreg mask z,mem128	AVX512
VBROADCASTI32X8	zmmreg mask z,mem256	AVX512DQ
VBROADCASTI64X2	ymmreg mask z,mem128	AVX512VL/DQ
VBROADCASTI64X2	zmmreg mask z,mem128	AVX512DQ
VBROADCASTI64X4	zmmreg mask z,mem256	AVX512
VBROADCASTSD	ymmreg mask z,mem64	AVX512VL
VBROADCASTSD	zmmreg mask z,mem64	AVX512
VBROADCASTSD	ymmreg mask z,xmmreg	AVX512VL
VBROADCASTSD	zmmreg mask z,xmmreg	AVX512
VBROADCASTSS	xmmreg mask z,mem32	AVX512VL
VBROADCASTSS	ymmreg mask z,mem32	AVX512VL
VBROADCASTSS	zmmreg mask z,mem32	AVX512
VBROADCASTSS	xmmreg mask z,xmmreg	AVX512VL
VBROADCASTSS	ymmreg mask z,xmmreg	AVX512VL
VBROADCASTSS	zmmreg mask z,xmmreg	AVX512
VCMPEQPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPEQPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPEQPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPEQPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPEQPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPEQPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPEQSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPEQSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPEQ_QOPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPEQ_QOPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPEQ_QOPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPEQ_QOPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPEQ_QOPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPEQ_QOPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPEQ_QQSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPEQ_QQSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMLTPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMLTPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMLTPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMLTPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMLTPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMLTPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMLTSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMLTSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMLT_OSP	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMLT_OSP	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMLT_OSP	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMLT_OSPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMLT_OSPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMLT_OSPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMLT_OSSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMLT_OSSS	kreg mask,xmmreg,xmmrm32 sae	AVX512

VCMPLPDP	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPLPDP	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPLPDP	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPLPDS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPLPDS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPLPDS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPLPESD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPLPES	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPLP_OSPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPLP_OSPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPLP_OSPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPLP_OSPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPLP_OSPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPLP_OSPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPLP_OSSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPLP_OSSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPLPORDPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPLPORDPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPLPORDPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPLPORDPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPLPORDPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPLPORDPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPLPORDSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPLPORDSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPLPORD_QPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPLPORD_QPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPLPORD_QPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPLPORD_QPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPLPORD_QPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPLPORD_QPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPLPORD_QSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPLPORD_QSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPLPNEQPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPLPNEQPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPLPNEQPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPLPNEQPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPLPNEQPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPLPNEQPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPLPNEQSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPLPNEQSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPLPNEQ_UQPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPLPNEQ_UQPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPLPNEQ_UQPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPLPNEQ_UQPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPLPNEQ_UQPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPLPNEQ_UQPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPLPNEQ_UQSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPLPNEQ_UQSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPLNLTPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPLNLTPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPLNLTPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPLNLTPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPLNLTPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPLNLTPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512

VCMPLNTSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPLNTSS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPLNT_USPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPLNT_USPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPLNT_USPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPLNT_USPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPLNT_USPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPLNT_USPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPLNT_USSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPLNT_USSS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPLNLEPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPLNLEPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPLNLEPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPLNLEPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPLNLEPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPLNLEPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPLNLESD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPLNLESS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPLNLE_USPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPLNLE_USPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPLNLE_USPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPLNLE_USPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPLNLE_USPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPLNLE_USPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPLNLE_USSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPLNLE_USSS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPLORDPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPLORDPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPLORDPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPLORDPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPLORDPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPLORDPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPLORDSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPLORDSS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPLORD_QPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPLORD_QPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPLORD_QPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPLORD_QPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPLORD_QPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPLORD_QPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPLORD_QSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPLORD_QSS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPEQ_UQPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPEQ_UQPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPEQ_UQPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPEQ_UQPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPEQ_UQPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPEQ_UQPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPEQ_UQSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPEQ_UQSS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPLNGEPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPLNGEPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPLNGEPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPLNGEPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL

VCMPNGEPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPNGEPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPNGESD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPNGESS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPNGE_USPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPNGE_USPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPNGE_USPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPNGE_USPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPNGE_USPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPNGE_USPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPNGE_USSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPNGE_USSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPNGTPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPNGTPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPNGTPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPNGTPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPNGTPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPNGTPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPNGTSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPNGTSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPNGT_USPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPNGT_USPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPNGT_USPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPNGT_USPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPNGT_USPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPNGT_USPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPNGT_USSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPNGT_USSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPFALSEPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPFALSEPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPFALSEPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPFALSEPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPFALSEPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPFALSEPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPFALSESD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPFALSESS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPFALSE_QQPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPFALSE_QQPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPFALSE_QQPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPFALSE_QQPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPFALSE_QQPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPFALSE_QQPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPFALSE_QQSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPFALSE_QQSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPNEQ_QQPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPNEQ_QQPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPNEQ_QQPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPNEQ_QQPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPNEQ_QQPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPNEQ_QQPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPNEQ_QQSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPNEQ_QQSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPGEPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPGEPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL

VCMPGEPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPGEPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPGEPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPGEPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPGESD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPGESS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPGE_OSPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPGE_OSPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPGE_OSPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPGE_OSPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPGE_OSPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPGE_OSPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPGE_OSSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPGE_OSSS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPGTPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPGTPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPGTPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPGTSPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPGTSPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPGTSPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPGTSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPGTSS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPGT_OSPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPGT_OSPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPGT_OSPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPGT_OSPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPGT_OSPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPGT_OSPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPGT_OSSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPGT_OSSS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPTRUEPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPTRUEPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPTRUEPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPTRUEPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPTRUEPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPTRUEPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPTRUESD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPTRUESS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPTRUE_UQPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPTRUE_UQPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPTRUE_UQPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPTRUE_UQPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPTRUE_UQPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPTRUE_UQPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPTRUE_UQSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPTRUE_UQSS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPEQ_OSPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPEQ_OSPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPEQ_OSPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPEQ_OSPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPEQ_OSPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPEQ_OSPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPEQ_OSSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPEQ_OSSS	kreg mask,xmmreg,xmmrm32 sae AVX512

VCMPPLT_OQPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPPLT_OQPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPPLT_OQPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPPLT_OQPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPPLT_OQPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPPLT_OQPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPPLT_OQSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPPLT_OQSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPLE_OQPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPLE_OQPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPLE_OQPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPLE_OQPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPLE_OQPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPLE_OQPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPLE_OQSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPLE_OQSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPUNORD_SPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPUNORD_SPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPUNORD_SPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPUNORD_SPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPUNORD_SPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPUNORD_SPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPUNORD_SSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPUNORD_SSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPNEQ_USPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPNEQ_USPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPNEQ_USPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPNEQ_USPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPNEQ_USPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPNEQ_USPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPNEQ_USSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPNEQ_USSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPNLT_UQPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPNLT_UQPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPNLT_UQPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPNLT_UQPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPNLT_UQPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPNLT_UQPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPNLT_UQSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPNLT_UQSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPNLE_UQPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPNLE_UQPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPNLE_UQPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPNLE_UQPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPNLE_UQPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPNLE_UQPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPNLE_UQSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPNLE_UQSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPORD_SPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPORD_SPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPORD_SPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPORD_SPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPORD_SPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPORD_SPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512

VCMPORD_SSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPORD_SSS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPEQ_USPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPEQ_USPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPEQ_USPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPEQ_USPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPEQ_USPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPEQ_USPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPEQ_USSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPEQ_USSS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPNGE_UQPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPNGE_UQPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPNGE_UQPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPNGE_UQPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPNGE_UQPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPNGE_UQPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPNGE_UQSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPNGE_UQSS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPNGT_UQPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPNGT_UQPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPNGT_UQPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPNGT_UQPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPNGT_UQPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPNGT_UQPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPNGT_UQSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPNGT_UQSS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPPFALSE_OSPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPPFALSE_OSPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPPFALSE_OSPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPPFALSE_OSPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPPFALSE_OSPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPPFALSE_OSPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPPFALSE_OSSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPPFALSE_OSSS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPPNEQ_OSPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPPNEQ_OSPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPPNEQ_OSPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPPNEQ_OSPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPPNEQ_OSPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPPNEQ_OSPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPPNEQ_OSSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPPNEQ_OSSS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPPGE_OQPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPPGE_OQPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPPGE_OQPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPPGE_OQPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL
VCMPPGE_OQPS	kreg mask,ymmreg,ymmrm256 b32 AVX512VL
VCMPPGE_OQPS	kreg mask,zmmreg,zmmrm512 b32 sae AVX512
VCMPPGE_OQSD	kreg mask,xmmreg,xmmrm64 sae AVX512
VCMPPGE_OQSS	kreg mask,xmmreg,xmmrm32 sae AVX512
VCMPPGT_OQPD	kreg mask,xmmreg,xmmrm128 b64 AVX512VL
VCMPPGT_OQPD	kreg mask,ymmreg,ymmrm256 b64 AVX512VL
VCMPPGT_OQPD	kreg mask,zmmreg,zmmrm512 b64 sae AVX512
VCMPPGT_OQPS	kreg mask,xmmreg,xmmrm128 b32 AVX512VL

VCMPGT_OQPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPGT_OQPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPGT_OQSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPGT_OQSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPTRUE_USPD	kreg mask,xmmreg,xmmrm128 b64	AVX512VL
VCMPTRUE_USPD	kreg mask,ymmreg,ymmrm256 b64	AVX512VL
VCMPTRUE_USPD	kreg mask,zmmreg,zmmrm512 b64 sae	AVX512
VCMPTRUE_USPS	kreg mask,xmmreg,xmmrm128 b32	AVX512VL
VCMPTRUE_USPS	kreg mask,ymmreg,ymmrm256 b32	AVX512VL
VCMPTRUE_USPS	kreg mask,zmmreg,zmmrm512 b32 sae	AVX512
VCMPTRUE_USSD	kreg mask,xmmreg,xmmrm64 sae	AVX512
VCMPTRUE_USSS	kreg mask,xmmreg,xmmrm32 sae	AVX512
VCMPPD	kreg mask,xmmreg,xmmrm128 b64,imm8	AVX512VL
VCMPPD	kreg mask,ymmreg,ymmrm256 b64,imm8	AVX512VL
VCMPPD	kreg mask,zmmreg,zmmrm512 b64 sae,imm8	AVX512
VCMPPS	kreg mask,xmmreg,xmmrm128 b32,imm8	AVX512VL
VCMPPS	kreg mask,ymmreg,ymmrm256 b32,imm8	AVX512VL
VCMPPS	kreg mask,zmmreg,zmmrm512 b32 sae,imm8	AVX512
VCMPSD	kreg mask,xmmreg,xmmrm64 sae,imm8	AVX512
VCMPS	kreg mask,xmmreg,xmmrm32 sae,imm8	AVX512
VCOMISD	xmmreg,xmmrm64 sae	AVX512
VCOMISS	xmmreg,xmmrm32 sae	AVX512
VCOMPRESSPD	mem128 mask,xmmreg	AVX512VL
VCOMPRESSPD	mem256 mask,ymmreg	AVX512VL
VCOMPRESSPD	mem512 mask,zmmreg	AVX512
VCOMPRESSPD	xmmreg mask z,xmmreg	AVX512VL
VCOMPRESSPD	ymmreg mask z,ymmreg	AVX512VL
VCOMPRESSPD	zmmreg mask z,zmmreg	AVX512
VCOMPRESSPS	mem128 mask,xmmreg	AVX512VL
VCOMPRESSPS	mem256 mask,ymmreg	AVX512VL
VCOMPRESSPS	mem512 mask,zmmreg	AVX512
VCOMPRESSPS	xmmreg mask z,xmmreg	AVX512VL
VCOMPRESSPS	ymmreg mask z,ymmreg	AVX512VL
VCOMPRESSPS	zmmreg mask z,zmmreg	AVX512
VCVTDQ2PD	xmmreg mask z,xmmrm64 b32	AVX512VL
VCVTDQ2PD	ymmreg mask z,xmmrm128 b32	AVX512VL
VCVTDQ2PD	zmmreg mask z,ymmrm256 b32 er	AVX512
VCVTDQ2PS	xmmreg mask z,xmmrm128 b32	AVX512VL
VCVTDQ2PS	ymmreg mask z,ymmrm256 b32	AVX512VL
VCVTDQ2PS	zmmreg mask z,zmmrm512 b32 er	AVX512
VCVTPD2DQ	xmmreg mask z,xmmrm128 b64	AVX512VL
VCVTPD2DQ	xmmreg mask z,ymmrm256 b64	AVX512VL
VCVTPD2DQ	ymmreg mask z,zmmrm512 b64 er	AVX512
VCVTPD2PS	xmmreg mask z,xmmrm128 b64	AVX512VL
VCVTPD2PS	xmmreg mask z,ymmrm256 b64	AVX512VL
VCVTPD2PS	ymmreg mask z,zmmrm512 b64 er	AVX512
VCVTPD2QQ	xmmreg mask z,xmmrm128 b64	AVX512VL/DQ
VCVTPD2QQ	ymmreg mask z,ymmrm256 b64	AVX512VL/DQ
VCVTPD2QQ	zmmreg mask z,zmmrm512 b64 er	AVX512DQ
VCVTPD2UDQ	xmmreg mask z,xmmrm128 b64	AVX512VL
VCVTPD2UDQ	xmmreg mask z,ymmrm256 b64	AVX512VL
VCVTPD2UDQ	ymmreg mask z,zmmrm512 b64 er	AVX512
VCVTPD2UQQ	xmmreg mask z,xmmrm128 b64	AVX512VL/DQ
VCVTPD2UQQ	ymmreg mask z,ymmrm256 b64	AVX512VL/DQ

VCVTPD2UQQ	zmmreg mask z,zmmrm512 b64 er	AVX512DQ
VCVTPH2PS	xmmreg mask z,xmmrm64	AVX512VL
VCVTPH2PS	ymmreg mask z,xmmrm128	AVX512VL
VCVTPH2PS	zmmreg mask z,ymmrm256 sae	AVX512
VCVTPS2DQ	xmmreg mask z,xmmrm128 b32	AVX512VL
VCVTPS2DQ	ymmreg mask z,ymmrm256 b32	AVX512VL
VCVTPS2DQ	zmmreg mask z,zmmrm512 b32 er	AVX512
VCVTPS2PD	xmmreg mask z,xmmrm64 b32	AVX512VL
VCVTPS2PD	ymmreg mask z,xmmrm128 b32	AVX512VL
VCVTPS2PD	zmmreg mask z,ymmrm256 b32 sae	AVX512
VCVTPS2PH	xmmreg mask z,xmmreg,imm8	AVX512VL
VCVTPS2PH	xmmreg mask z,ymmreg,imm8	AVX512VL
VCVTPS2PH	ymmreg mask z,zmmreg sae,imm8	AVX512
VCVTPS2PH	mem64 mask,xmmreg,imm8	AVX512VL
VCVTPS2PH	mem128 mask,ymmreg,imm8	AVX512VL
VCVTPS2PH	mem256 mask,zmmreg sae,imm8	AVX512
VCVTPS2QQ	xmmreg mask z,xmmrm64 b32	AVX512VL/DQ
VCVTPS2QQ	ymmreg mask z,xmmrm128 b32	AVX512VL/DQ
VCVTPS2QQ	zmmreg mask z,ymmrm256 b32 er	AVX512DQ
VCVTPS2UDQ	xmmreg mask z,xmmrm128 b32	AVX512VL
VCVTPS2UDQ	ymmreg mask z,ymmrm256 b32	AVX512VL
VCVTPS2UDQ	zmmreg mask z,zmmrm512 b32 er	AVX512
VCVTPS2UQQ	xmmreg mask z,xmmrm64 b32	AVX512VL/DQ
VCVTPS2UQQ	ymmreg mask z,xmmrm128 b32	AVX512VL/DQ
VCVTPS2UQQ	zmmreg mask z,ymmrm256 b32 er	AVX512DQ
VCVTQQ2PD	xmmreg mask z,xmmrm128 b64	AVX512VL/DQ
VCVTQQ2PD	ymmreg mask z,ymmrm256 b64	AVX512VL/DQ
VCVTQQ2PD	zmmreg mask z,zmmrm512 b64 er	AVX512DQ
VCVTQQ2PS	xmmreg mask z,xmmrm128 b64	AVX512VL/DQ
VCVTQQ2PS	xmmreg mask z,ymmrm256 b64	AVX512VL/DQ
VCVTQQ2PS	ymmreg mask z,zmmrm512 b64 er	AVX512DQ
VCVTSD2SI	reg32,xmmrm64 er	AVX512
VCVTSD2SI	reg64,xmmrm64 er	AVX512
VCVTSD2SS	xmmreg mask z,xmmreg,xmmrm64 er	AVX512
VCVTSD2USI	reg32,xmmrm64 er	AVX512
VCVTSD2USI	reg64,xmmrm64 er	AVX512
VCVTSI2SD	xmmreg,xmmreg er,rm32	AVX512
VCVTSI2SD	xmmreg,xmmreg er,rm64	AVX512
VCVTSI2SS	xmmreg,xmmreg er,rm32	AVX512
VCVTSI2SS	xmmreg,xmmreg er,rm64	AVX512
VCVTSS2SD	xmmreg mask z,xmmreg,xmmrm32 sae	AVX512
VCVTSS2SI	reg32,xmmrm32 er	AVX512
VCVTSS2SI	reg64,xmmrm32 er	AVX512
VCVTSS2USI	reg32,xmmrm32 er	AVX512
VCVTSS2USI	reg64,xmmrm32 er	AVX512
VCVTTPD2DQ	xmmreg mask z,xmmrm128 b64	AVX512VL
VCVTTPD2DQ	xmmreg mask z,ymmrm256 b64	AVX512VL
VCVTTPD2DQ	ymmreg mask z,zmmrm512 b64 sae	AVX512
VCVTTPD2QQ	xmmreg mask z,xmmrm128 b64	AVX512VL/DQ
VCVTTPD2QQ	ymmreg mask z,ymmrm256 b64	AVX512VL/DQ
VCVTTPD2QQ	zmmreg mask z,zmmrm512 b64 sae	AVX512DQ
VCVTTPD2UDQ	xmmreg mask z,xmmrm128 b64	AVX512VL
VCVTTPD2UDQ	xmmreg mask z,ymmrm256 b64	AVX512VL
VCVTTPD2UDQ	ymmreg mask z,zmmrm512 b64 sae	AVX512

VCVTTPD2UQQ	xmmreg mask z,xmmrm128	b64	AVX512VL/DQ
VCVTTPD2UQQ	ymmreg mask z,ymmrm256	b64	AVX512VL/DQ
VCVTTPD2UQQ	zmmreg mask z,zmmrm512	b64	sae AVX512DQ
VCVTTPS2DQ	xmmreg mask z,xmmrm128	b32	AVX512VL
VCVTTPS2DQ	ymmreg mask z,ymmrm256	b32	AVX512VL
VCVTTPS2DQ	zmmreg mask z,zmmrm512	b32	sae AVX512
VCVTTPS2QQ	xmmreg mask z,xmmrm64	b32	AVX512VL/DQ
VCVTTPS2QQ	ymmreg mask z,xmmrm128	b32	AVX512VL/DQ
VCVTTPS2QQ	zmmreg mask z,ymmrm256	b32	sae AVX512DQ
VCVTTPS2UDQ	xmmreg mask z,xmmrm128	b32	AVX512VL
VCVTTPS2UDQ	ymmreg mask z,ymmrm256	b32	AVX512VL
VCVTTPS2UDQ	zmmreg mask z,zmmrm512	b32	sae AVX512
VCVTTPS2UQQ	xmmreg mask z,xmmrm64	b32	AVX512VL/DQ
VCVTTPS2UQQ	ymmreg mask z,xmmrm128	b32	AVX512VL/DQ
VCVTTPS2UQQ	zmmreg mask z,ymmrm256	b32	sae AVX512DQ
VCVTTSD2SI	reg32,xmmrm64	sae	AVX512
VCVTTSD2SI	reg64,xmmrm64	sae	AVX512
VCVTTSD2USI	reg32,xmmrm64	sae	AVX512
VCVTTSD2USI	reg64,xmmrm64	sae	AVX512
VCVTTSS2SI	reg32,xmmrm32	sae	AVX512
VCVTTSS2SI	reg64,xmmrm32	sae	AVX512
VCVTTSS2USI	reg32,xmmrm32	sae	AVX512
VCVTTSS2USI	reg64,xmmrm32	sae	AVX512
VCVTUDQ2PD	xmmreg mask z,xmmrm64	b32	AVX512VL
VCVTUDQ2PD	ymmreg mask z,xmmrm128	b32	AVX512VL
VCVTUDQ2PD	zmmreg mask z,ymmrm256	b32	er AVX512
VCVTUDQ2PS	xmmreg mask z,xmmrm128	b32	AVX512VL
VCVTUDQ2PS	ymmreg mask z,ymmrm256	b32	AVX512VL
VCVTUDQ2PS	zmmreg mask z,zmmrm512	b32	er AVX512
VCVTUQQ2PD	xmmreg mask z,xmmrm128	b64	AVX512VL/DQ
VCVTUQQ2PD	ymmreg mask z,ymmrm256	b64	AVX512VL/DQ
VCVTUQQ2PD	zmmreg mask z,zmmrm512	b64	er AVX512DQ
VCVTUQQ2PS	xmmreg mask z,xmmrm128	b64	AVX512VL/DQ
VCVTUQQ2PS	xmmreg mask z,ymmrm256	b64	AVX512VL/DQ
VCVTUQQ2PS	ymmreg mask z,zmmrm512	b64	er AVX512DQ
VCVTUSI2SD	xmmreg,xmmreg er,rm32		AVX512
VCVTUSI2SD	xmmreg,xmmreg er,rm64		AVX512
VCVTUSI2SS	xmmreg,xmmreg er,rm32		AVX512
VCVTUSI2SS	xmmreg,xmmreg er,rm64		AVX512
VDBPSADBW	xmmreg mask z,xmmreg*,xmmrm128,imm8		AVX512VL/BW
VDBPSADBW	ymmreg mask z,ymmreg*,ymmrm256,imm8		AVX512VL/BW
VDBPSADBW	zmmreg mask z,zmmreg*,zmmrm512,imm8		AVX512BW
VDIVPD	xmmreg mask z,xmmreg*,xmmrm128	b64	AVX512VL
VDIVPD	ymmreg mask z,ymmreg*,ymmrm256	b64	AVX512VL
VDIVPD	zmmreg mask z,zmmreg*,zmmrm512	b64	er AVX512
VDIVPS	xmmreg mask z,xmmreg*,xmmrm128	b32	AVX512VL
VDIVPS	ymmreg mask z,ymmreg*,ymmrm256	b32	AVX512VL
VDIVPS	zmmreg mask z,zmmreg*,zmmrm512	b32	er AVX512
VDIVSD	xmmreg mask z,xmmreg*,xmmrm64		er AVX512
VDIVSS	xmmreg mask z,xmmreg*,xmmrm32		er AVX512
VEXP2PD	zmmreg mask z,zmmrm512	b64	sae AVX512ER
VEXP2PS	zmmreg mask z,zmmrm512	b32	sae AVX512ER
VEXPANDPD	xmmreg mask z,mem128		AVX512VL
VEXPANDPD	ymmreg mask z,mem256		AVX512VL

VEXPANDPD	zmmreg	mask	z, mem512	AVX512
VEXPANDPD	xmmreg	mask	z, xmmreg	AVX512VL
VEXPANDPD	ymmreg	mask	z, ymmreg	AVX512VL
VEXPANDPD	zmmreg	mask	z, zmmreg	AVX512
VEXPANDPS	xmmreg	mask	z, mem128	AVX512VL
VEXPANDPS	ymmreg	mask	z, mem256	AVX512VL
VEXPANDPS	zmmreg	mask	z, mem512	AVX512
VEXPANDPS	xmmreg	mask	z, xmmreg	AVX512VL
VEXPANDPS	ymmreg	mask	z, ymmreg	AVX512VL
VEXPANDPS	zmmreg	mask	z, zmmreg	AVX512
VEXTRACTF32X4	xmmreg	mask	z, ymmreg, imm8	AVX512VL
VEXTRACTF32X4	xmmreg	mask	z, zmmreg, imm8	AVX512
VEXTRACTF32X4	mem128	mask	, ymmreg, imm8	AVX512VL
VEXTRACTF32X4	mem128	mask	, zmmreg, imm8	AVX512
VEXTRACTF32X8	ymmreg	mask	z, zmmreg, imm8	AVX512DQ
VEXTRACTF32X8	mem256	mask	, zmmreg, imm8	AVX512DQ
VEXTRACTF64X2	xmmreg	mask	z, ymmreg, imm8	AVX512VL/DQ
VEXTRACTF64X2	xmmreg	mask	z, zmmreg, imm8	AVX512DQ
VEXTRACTF64X2	mem128	mask	, ymmreg, imm8	AVX512VL/DQ
VEXTRACTF64X2	mem128	mask	, zmmreg, imm8	AVX512DQ
VEXTRACTF64X4	ymmreg	mask	z, zmmreg, imm8	AVX512
VEXTRACTF64X4	mem256	mask	, zmmreg, imm8	AVX512
VEXTRACTI32X4	xmmreg	mask	z, ymmreg, imm8	AVX512VL
VEXTRACTI32X4	xmmreg	mask	z, zmmreg, imm8	AVX512
VEXTRACTI32X4	mem128	mask	, ymmreg, imm8	AVX512VL
VEXTRACTI32X4	mem128	mask	, zmmreg, imm8	AVX512
VEXTRACTI32X8	ymmreg	mask	z, zmmreg, imm8	AVX512DQ
VEXTRACTI32X8	mem256	mask	, zmmreg, imm8	AVX512DQ
VEXTRACTI64X2	xmmreg	mask	z, ymmreg, imm8	AVX512VL/DQ
VEXTRACTI64X2	xmmreg	mask	z, zmmreg, imm8	AVX512DQ
VEXTRACTI64X2	mem128	mask	, ymmreg, imm8	AVX512VL/DQ
VEXTRACTI64X2	mem128	mask	, zmmreg, imm8	AVX512DQ
VEXTRACTI64X4	ymmreg	mask	z, zmmreg, imm8	AVX512
VEXTRACTI64X4	mem256	mask	, zmmreg, imm8	AVX512
VEXTRACTPS	reg32, xmmreg,	imm8		AVX512
VEXTRACTPS	reg64, xmmreg,	imm8		AVX512
VEXTRACTPS	mem32, xmmreg,	imm8		AVX512
VFIXUPIIMPD	xmmreg	mask	z, xmmreg*, xmrm128	b64, imm8 AVX512VL
VFIXUPIIMPD	ymmreg	mask	z, ymmreg*, ymrm256	b64, imm8 AVX512VL
VFIXUPIIMPD	zmmreg	mask	z, zmmreg*, zmrm512	b64 sae, imm8 AVX512
VFIXUPIIMPS	xmmreg	mask	z, xmmreg*, xmrm128	b32, imm8 AVX512VL
VFIXUPIIMPS	ymmreg	mask	z, ymmreg*, ymrm256	b32, imm8 AVX512VL
VFIXUPIIMPS	zmmreg	mask	z, zmmreg*, zmrm512	b32 sae, imm8 AVX512
VFIXUPIIMSD	xmmreg	mask	z, xmmreg*, xmrm64	sae, imm8 AVX512
VFIXUPIIMSS	xmmreg	mask	z, xmmreg*, xmrm32	sae, imm8 AVX512
VFMADD132PD	xmmreg	mask	z, xmmreg, xmrm128	b64 AVX512VL
VFMADD132PD	ymmreg	mask	z, ymmreg, ymrm256	b64 AVX512VL
VFMADD132PD	zmmreg	mask	z, zmmreg, zmrm512	b64 er AVX512
VFMADD132PS	xmmreg	mask	z, xmmreg, xmrm128	b32 AVX512VL
VFMADD132PS	ymmreg	mask	z, ymmreg, ymrm256	b32 AVX512VL
VFMADD132PS	zmmreg	mask	z, zmmreg, zmrm512	b32 er AVX512
VFMADD132SD	xmmreg	mask	z, xmmreg, xmrm64	er AVX512
VFMADD132SS	xmmreg	mask	z, xmmreg, xmrm32	er AVX512
VFMADD213PD	xmmreg	mask	z, xmmreg, xmrm128	b64 AVX512VL

VFMADD213PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFMADD213PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFMADD213PS	xmmreg	mask	z, xmmreg, xmmrm128	b32	AVX512VL
VFMADD213PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFMADD213PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFMADD213SD	xmmreg	mask	z, xmmreg, xmmrm64	er	AVX512
VFMADD213SS	xmmreg	mask	z, xmmreg, xmmrm32	er	AVX512
VFMADD231PD	xmmreg	mask	z, xmmreg, xmmrm128	b64	AVX512VL
VFMADD231PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFMADD231PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFMADD231PS	xmmreg	mask	z, xmmreg, xmmrm128	b32	AVX512VL
VFMADD231PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFMADD231PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFMADD231SD	xmmreg	mask	z, xmmreg, xmmrm64	er	AVX512
VFMADD231SS	xmmreg	mask	z, xmmreg, xmmrm32	er	AVX512
VFMADDSUB132PD	xmmreg	mask	z, xmmreg, xmmrm128	b64	AVX512VL
VFMADDSUB132PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFMADDSUB132PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFMADDSUB132PS	xmmreg	mask	z, xmmreg, xmmrm128	b32	AVX512VL
VFMADDSUB132PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFMADDSUB132PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFMADDSUB213PD	xmmreg	mask	z, xmmreg, xmmrm128	b64	AVX512VL
VFMADDSUB213PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFMADDSUB213PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFMADDSUB213PS	xmmreg	mask	z, xmmreg, xmmrm128	b32	AVX512VL
VFMADDSUB213PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFMADDSUB213PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFMADDSUB231PD	xmmreg	mask	z, xmmreg, xmmrm128	b64	AVX512VL
VFMADDSUB231PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFMADDSUB231PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFMADDSUB231PS	xmmreg	mask	z, xmmreg, xmmrm128	b32	AVX512VL
VFMADDSUB231PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFMADDSUB231PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFMASUB132PD	xmmreg	mask	z, xmmreg, xmmrm128	b64	AVX512VL
VFMASUB132PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFMASUB132PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFMASUB132PS	xmmreg	mask	z, xmmreg, xmmrm128	b32	AVX512VL
VFMASUB132PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFMASUB132PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFMASUB132SD	xmmreg	mask	z, xmmreg, xmmrm64	er	AVX512
VFMASUB132SS	xmmreg	mask	z, xmmreg, xmmrm32	er	AVX512
VFMASUB213PD	xmmreg	mask	z, xmmreg, xmmrm128	b64	AVX512VL
VFMASUB213PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFMASUB213PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFMASUB213PS	xmmreg	mask	z, xmmreg, xmmrm128	b32	AVX512VL
VFMASUB213PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFMASUB213PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFMASUB213SD	xmmreg	mask	z, xmmreg, xmmrm64	er	AVX512
VFMASUB213SS	xmmreg	mask	z, xmmreg, xmmrm32	er	AVX512
VFMASUB231PD	xmmreg	mask	z, xmmreg, xmmrm128	b64	AVX512VL
VFMASUB231PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFMASUB231PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFMASUB231PS	xmmreg	mask	z, xmmreg, xmmrm128	b32	AVX512VL
VFMASUB231PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL

VFMSUB231PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFMSUB231SD	xmmreg	mask	z, xmmreg, xmrm64		er AVX512
VFMSUB231SS	xmmreg	mask	z, xmmreg, xmrm32		er AVX512
VFMSUBADD132PD	xmmreg	mask	z, xmmreg, xmrm128	b64	AVX512VL
VFMSUBADD132PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFMSUBADD132PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFMSUBADD132PS	xmmreg	mask	z, xmmreg, xmrm128	b32	AVX512VL
VFMSUBADD132PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFMSUBADD132PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFMSUBADD213PD	xmmreg	mask	z, xmmreg, xmrm128	b64	AVX512VL
VFMSUBADD213PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFMSUBADD213PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFMSUBADD213PS	xmmreg	mask	z, xmmreg, xmrm128	b32	AVX512VL
VFMSUBADD213PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFMSUBADD213PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFMSUBADD231PD	xmmreg	mask	z, xmmreg, xmrm128	b64	AVX512VL
VFMSUBADD231PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFMSUBADD231PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFMSUBADD231PS	xmmreg	mask	z, xmmreg, xmrm128	b32	AVX512VL
VFMSUBADD231PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFMSUBADD231PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFNMADD132PD	xmmreg	mask	z, xmmreg, xmrm128	b64	AVX512VL
VFNMADD132PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFNMADD132PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFNMADD132PS	xmmreg	mask	z, xmmreg, xmrm128	b32	AVX512VL
VFNMADD132PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFNMADD132PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFNMADD132SD	xmmreg	mask	z, xmmreg, xmrm64		er AVX512
VFNMADD132SS	xmmreg	mask	z, xmmreg, xmrm32		er AVX512
VFNMADD213PD	xmmreg	mask	z, xmmreg, xmrm128	b64	AVX512VL
VFNMADD213PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFNMADD213PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFNMADD213PS	xmmreg	mask	z, xmmreg, xmrm128	b32	AVX512VL
VFNMADD213PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFNMADD213PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFNMADD213SD	xmmreg	mask	z, xmmreg, xmrm64		er AVX512
VFNMADD213SS	xmmreg	mask	z, xmmreg, xmrm32		er AVX512
VFNMADD231PD	xmmreg	mask	z, xmmreg, xmrm128	b64	AVX512VL
VFNMADD231PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFNMADD231PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFNMADD231PS	xmmreg	mask	z, xmmreg, xmrm128	b32	AVX512VL
VFNMADD231PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFNMADD231PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFNMADD231SD	xmmreg	mask	z, xmmreg, xmrm64		er AVX512
VFNMADD231SS	xmmreg	mask	z, xmmreg, xmrm32		er AVX512
VFNMSUB132PD	xmmreg	mask	z, xmmreg, xmrm128	b64	AVX512VL
VFNMSUB132PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFNMSUB132PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFNMSUB132PS	xmmreg	mask	z, xmmreg, xmrm128	b32	AVX512VL
VFNMSUB132PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFNMSUB132PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFNMSUB132SD	xmmreg	mask	z, xmmreg, xmrm64		er AVX512
VFNMSUB132SS	xmmreg	mask	z, xmmreg, xmrm32		er AVX512
VFNMSUB213PD	xmmreg	mask	z, xmmreg, xmrm128	b64	AVX512VL

VFNMSUB213PD	ymmreg mask z,ymmreg,ymmrm256 b64	AVX512VL
VFNMSUB213PD	zmmreg mask z,zmmreg,zmmrm512 b64 er	AVX512
VFNMSUB213PS	xmmreg mask z,xmmreg,xmmrm128 b32	AVX512VL
VFNMSUB213PS	ymmreg mask z,ymmreg,ymmrm256 b32	AVX512VL
VFNMSUB213PS	zmmreg mask z,zmmreg,zmmrm512 b32 er	AVX512
VFNMSUB213SD	xmmreg mask z,xmmreg,xmmrm64 er	AVX512
VFNMSUB213SS	xmmreg mask z,xmmreg,xmmrm32 er	AVX512
VFNMSUB231PD	xmmreg mask z,xmmreg,xmmrm128 b64	AVX512VL
VFNMSUB231PD	ymmreg mask z,ymmreg,ymmrm256 b64	AVX512VL
VFNMSUB231PD	zmmreg mask z,zmmreg,zmmrm512 b64 er	AVX512
VFNMSUB231PS	xmmreg mask z,xmmreg,xmmrm128 b32	AVX512VL
VFNMSUB231PS	ymmreg mask z,ymmreg,ymmrm256 b32	AVX512VL
VFNMSUB231PS	zmmreg mask z,zmmreg,zmmrm512 b32 er	AVX512
VFNMSUB231SD	xmmreg mask z,xmmreg,xmmrm64 er	AVX512
VFNMSUB231SS	xmmreg mask z,xmmreg,xmmrm32 er	AVX512
VFPCLASSPD	kreg mask,xmmrm128 b64,imm8	AVX512VL/DQ
VFPCLASSPD	kreg mask,ymmrm256 b64,imm8	AVX512VL/DQ
VFPCLASSPD	kreg mask,zmmrm512 b64,imm8	AVX512DQ
VFPCLASSPS	kreg mask,xmmrm128 b32,imm8	AVX512VL/DQ
VFPCLASSPS	kreg mask,ymmrm256 b32,imm8	AVX512VL/DQ
VFPCLASSPS	kreg mask,zmmrm512 b32,imm8	AVX512DQ
VFPCLASSSD	kreg mask,xmmrm64,imm8	AVX512DQ
VFPCLASSSS	kreg mask,xmmrm32,imm8	AVX512DQ
VGATHERDPD	xmmreg mask,xmem64	AVX512VL
VGATHERDPD	ymmreg mask,xmem64	AVX512VL
VGATHERDPD	zmmreg mask,ymem64	AVX512
VGATHERDPS	xmmreg mask,xmem32	AVX512VL
VGATHERDPS	ymmreg mask,ymem32	AVX512VL
VGATHERDPS	zmmreg mask,zmem32	AVX512
VGATHERPF0DPD	ymem64 mask	AVX512PF
VGATHERPF0DPS	zmem32 mask	AVX512PF
VGATHERPF0QPD	zmem64 mask	AVX512PF
VGATHERPF0QPS	zmem32 mask	AVX512PF
VGATHERPF1DPD	ymem64 mask	AVX512PF
VGATHERPF1DPS	zmem32 mask	AVX512PF
VGATHERPF1QPD	zmem64 mask	AVX512PF
VGATHERPF1QPS	zmem32 mask	AVX512PF
VGATHERQPD	xmmreg mask,xmem64	AVX512VL
VGATHERQPD	ymmreg mask,ymem64	AVX512VL
VGATHERQPD	zmmreg mask,zmem64	AVX512
VGATHERQPS	xmmreg mask,xmem32	AVX512VL
VGATHERQPS	xmmreg mask,ymem32	AVX512VL
VGATHERQPS	ymmreg mask,zmem32	AVX512
VGETEXPPD	xmmreg mask z,xmmrm128 b64	AVX512VL
VGETEXPPD	ymmreg mask z,ymmrm256 b64	AVX512VL
VGETEXPPD	zmmreg mask z,zmmrm512 b64 sae	AVX512
VGETEXPPS	xmmreg mask z,xmmrm128 b32	AVX512VL
VGETEXPPS	ymmreg mask z,ymmrm256 b32	AVX512VL
VGETEXPPS	zmmreg mask z,zmmrm512 b32 sae	AVX512
VGETEXPSD	xmmreg mask z,xmmreg,xmmrm64 sae	AVX512
VGETEXPSS	xmmreg mask z,xmmreg,xmmrm32 sae	AVX512
VGETMANTPD	xmmreg mask z,xmmrm128 b64,imm8	AVX512VL
VGETMANTPD	ymmreg mask z,ymmrm256 b64,imm8	AVX512VL
VGETMANTPD	zmmreg mask z,zmmrm512 b64 sae,imm8	AVX512

VGETMANTPS	xmmreg	mask	z, xmmrm128	b32, imm8	AVX512VL
VGETMANTPS	ymmreg	mask	z, ymmrm256	b32, imm8	AVX512VL
VGETMANTPS	zmmreg	mask	z, zmmrm512	b32 sae, imm8	AVX512
VGETMANTSD	xmmreg	mask	z, xmmreg, xmmrm64	sae, imm8	AVX512
VGETMANTSS	xmmreg	mask	z, xmmreg, xmmrm32	sae, imm8	AVX512
VINSERTF32X4	ymmreg	mask	z, ymmreg*, xmmrm128	imm8	AVX512VL
VINSERTF32X4	zmmreg	mask	z, zmmreg*, xmmrm128	imm8	AVX512
VINSERTF32X8	zmmreg	mask	z, zmmreg*, ymmrm256	imm8	AVX512DQ
VINSERTF64X2	ymmreg	mask	z, ymmreg*, xmmrm128	imm8	AVX512VL/DQ
VINSERTF64X2	zmmreg	mask	z, zmmreg*, xmmrm128	imm8	AVX512DQ
VINSERTF64X4	zmmreg	mask	z, zmmreg*, ymmrm256	imm8	AVX512
VINSERTI32X4	ymmreg	mask	z, ymmreg*, xmmrm128	imm8	AVX512VL
VINSERTI32X4	zmmreg	mask	z, zmmreg*, xmmrm128	imm8	AVX512
VINSERTI32X8	zmmreg	mask	z, zmmreg*, ymmrm256	imm8	AVX512DQ
VINSERTI64X2	ymmreg	mask	z, ymmreg*, xmmrm128	imm8	AVX512VL/DQ
VINSERTI64X2	zmmreg	mask	z, zmmreg*, xmmrm128	imm8	AVX512DQ
VINSERTI64X4	zmmreg	mask	z, zmmreg*, ymmrm256	imm8	AVX512
VINSERTPS	xmmreg, xmmreg*		xmmrm32	imm8	AVX512
VMAXPD	xmmreg	mask	z, xmmreg*, xmmrm128	b64	AVX512VL
VMAXPD	ymmreg	mask	z, ymmreg*, ymmrm256	b64	AVX512VL
VMAXPD	zmmreg	mask	z, zmmreg*, zmmrm512	b64 sae	AVX512
VMAXPS	xmmreg	mask	z, xmmreg*, xmmrm128	b32	AVX512VL
VMAXPS	ymmreg	mask	z, ymmreg*, ymmrm256	b32	AVX512VL
VMAXPS	zmmreg	mask	z, zmmreg*, zmmrm512	b32 sae	AVX512
VMAXSD	xmmreg	mask	z, xmmreg*, xmmrm64	sae	AVX512
VMAXSS	xmmreg	mask	z, xmmreg*, xmmrm32	sae	AVX512
VMINPD	xmmreg	mask	z, xmmreg*, xmmrm128	b64	AVX512VL
VMINPD	ymmreg	mask	z, ymmreg*, ymmrm256	b64	AVX512VL
VMINPD	zmmreg	mask	z, zmmreg*, zmmrm512	b64 sae	AVX512
VMINPS	xmmreg	mask	z, xmmreg*, xmmrm128	b32	AVX512VL
VMINPS	ymmreg	mask	z, ymmreg*, ymmrm256	b32	AVX512VL
VMINPS	zmmreg	mask	z, zmmreg*, zmmrm512	b32 sae	AVX512
VMINSD	xmmreg	mask	z, xmmreg*, xmmrm64	sae	AVX512
VMINSS	xmmreg	mask	z, xmmreg*, xmmrm32	sae	AVX512
VMOVAPD	xmmreg	mask	z, xmmrm128		AVX512VL
VMOVAPD	ymmreg	mask	z, ymmrm256		AVX512VL
VMOVAPD	zmmreg	mask	z, zmmrm512		AVX512
VMOVAPD	xmmreg	mask	z, xmmreg		AVX512VL
VMOVAPD	ymmreg	mask	z, ymmreg		AVX512VL
VMOVAPD	zmmreg	mask	z, zmmreg		AVX512
VMOVAPD	mem128	mask, xmmreg			AVX512VL
VMOVAPD	mem256	mask, ymmreg			AVX512VL
VMOVAPD	mem512	mask, zmmreg			AVX512
VMOVAPS	xmmreg	mask	z, xmmrm128		AVX512VL
VMOVAPS	ymmreg	mask	z, ymmrm256		AVX512VL
VMOVAPS	zmmreg	mask	z, zmmrm512		AVX512
VMOVAPS	xmmreg	mask	z, xmmreg		AVX512VL
VMOVAPS	ymmreg	mask	z, ymmreg		AVX512VL
VMOVAPS	zmmreg	mask	z, zmmreg		AVX512
VMOVAPS	mem128	mask, xmmreg			AVX512VL
VMOVAPS	mem256	mask, ymmreg			AVX512VL
VMOVAPS	mem512	mask, zmmreg			AVX512
VMOVD	xmmreg, rm32				AVX512
VMOVD	rm32, xmmreg				AVX512

VMOVDDUP	xmmreg mask z,xmmrm64	AVX512VL
VMOVDDUP	ymmreg mask z,ymmrm256	AVX512VL
VMOVDDUP	zmmreg mask z,zmmrm512	AVX512
VMOVDQA32	xmmreg mask z,xmmrm128	AVX512VL
VMOVDQA32	ymmreg mask z,ymmrm256	AVX512VL
VMOVDQA32	zmmreg mask z,zmmrm512	AVX512
VMOVDQA32	xmmrm128 mask z,xmmreg	AVX512VL
VMOVDQA32	ymmrm256 mask z,ymmreg	AVX512VL
VMOVDQA32	zmmrm512 mask z,zmmreg	AVX512
VMOVDQA64	xmmreg mask z,xmmrm128	AVX512VL
VMOVDQA64	ymmreg mask z,ymmrm256	AVX512VL
VMOVDQA64	zmmreg mask z,zmmrm512	AVX512
VMOVDQA64	xmmrm128 mask z,xmmreg	AVX512VL
VMOVDQA64	ymmrm256 mask z,ymmreg	AVX512VL
VMOVDQA64	zmmrm512 mask z,zmmreg	AVX512
VMOVDQU16	xmmreg mask z,xmmrm128	AVX512VL/BW
VMOVDQU16	ymmreg mask z,ymmrm256	AVX512VL/BW
VMOVDQU16	zmmreg mask z,zmmrm512	AVX512BW
VMOVDQU16	xmmrm128 mask z,xmmreg	AVX512VL/BW
VMOVDQU16	ymmrm256 mask z,ymmreg	AVX512VL/BW
VMOVDQU16	zmmrm512 mask z,zmmreg	AVX512BW
VMOVDQU32	xmmreg mask z,xmmrm128	AVX512VL
VMOVDQU32	ymmreg mask z,ymmrm256	AVX512VL
VMOVDQU32	zmmreg mask z,zmmrm512	AVX512
VMOVDQU32	xmmrm128 mask z,xmmreg	AVX512VL
VMOVDQU32	ymmrm256 mask z,ymmreg	AVX512VL
VMOVDQU32	zmmrm512 mask z,zmmreg	AVX512
VMOVDQU64	xmmreg mask z,xmmrm128	AVX512VL
VMOVDQU64	ymmreg mask z,ymmrm256	AVX512VL
VMOVDQU64	zmmreg mask z,zmmrm512	AVX512
VMOVDQU64	xmmrm128 mask z,xmmreg	AVX512VL
VMOVDQU64	ymmrm256 mask z,ymmreg	AVX512VL
VMOVDQU64	zmmrm512 mask z,zmmreg	AVX512
VMOVDQU8	xmmreg mask z,xmmrm128	AVX512VL/BW
VMOVDQU8	ymmreg mask z,ymmrm256	AVX512VL/BW
VMOVDQU8	zmmreg mask z,zmmrm512	AVX512BW
VMOVDQU8	xmmrm128 mask z,xmmreg	AVX512VL/BW
VMOVDQU8	ymmrm256 mask z,ymmreg	AVX512VL/BW
VMOVDQU8	zmmrm512 mask z,zmmreg	AVX512BW
VMOVHLP	xmmreg,xmmreg*,xmmreg	AVX512
VMOVHPD	xmmreg,xmmreg*,mem64	AVX512
VMOVHPD	mem64,xmmreg	AVX512
VMOVHPS	xmmreg,xmmreg*,mem64	AVX512
VMOVHPS	mem64,xmmreg	AVX512
VMOVLHPS	xmmreg,xmmreg*,xmmreg	AVX512
VMOVLPD	xmmreg,xmmreg*,mem64	AVX512
VMOVLPD	mem64,xmmreg	AVX512
VMOVLPS	xmmreg,xmmreg*,mem64	AVX512
VMOVLPS	mem64,xmmreg	AVX512
VMOVNTDQ	mem128,xmmreg	AVX512VL
VMOVNTDQ	mem256,ymmreg	AVX512VL
VMOVNTDQ	mem512,zmmreg	AVX512
VMOVNTDQA	xmmreg,mem128	AVX512VL
VMOVNTDQA	ymmreg,mem256	AVX512VL

VMOVNTDQA	zmmreg, mem512	AVX512
VMOVNTPD	mem128, xmmreg	AVX512VL
VMOVNTPD	mem256, ymmreg	AVX512VL
VMOVNTPD	mem512, zmmreg	AVX512
VMOVNTPS	mem128, xmmreg	AVX512VL
VMOVNTPS	mem256, ymmreg	AVX512VL
VMOVNTPS	mem512, zmmreg	AVX512
VMOVQ	xmmreg, rm64	AVX512
VMOVQ	rm64, xmmreg	AVX512
VMOVQ	xmmreg, xmmrm64	AVX512
VMOVQ	xmmrm64, xmmreg	AVX512
VMOVSD	xmmreg mask z, mem64	AVX512
VMOVSD	mem64 mask, xmmreg	AVX512
VMOVSD	xmmreg mask z, xmmreg*, xmmreg	AVX512
VMOVSD	xmmreg mask z, xmmreg*, xmmreg	AVX512
VMOVSHDUP	xmmreg mask z, xmmrm128	AVX512VL
VMOVSHDUP	ymmreg mask z, ymmrm256	AVX512VL
VMOVSHDUP	zmmreg mask z, zmmrm512	AVX512
VMOVSLDUP	xmmreg mask z, xmmrm128	AVX512VL
VMOVSLDUP	ymmreg mask z, ymmrm256	AVX512VL
VMOVSLDUP	zmmreg mask z, zmmrm512	AVX512
VMOVSS	xmmreg mask z, mem32	AVX512
VMOVSS	mem32 mask, xmmreg	AVX512
VMOVSS	xmmreg mask z, xmmreg*, xmmreg	AVX512
VMOVSS	xmmreg mask z, xmmreg*, xmmreg	AVX512
VMOVUPD	xmmreg mask z, xmmrm128	AVX512VL
VMOVUPD	ymmreg mask z, ymmrm256	AVX512VL
VMOVUPD	zmmreg mask z, zmmrm512	AVX512
VMOVUPD	xmmreg mask z, xmmreg	AVX512VL
VMOVUPD	ymmreg mask z, ymmreg	AVX512VL
VMOVUPD	zmmreg mask z, zmmreg	AVX512
VMOVUPD	mem128 mask, xmmreg	AVX512VL
VMOVUPD	mem256 mask, ymmreg	AVX512VL
VMOVUPD	mem512 mask, zmmreg	AVX512
VMOVUPS	xmmreg mask z, xmmrm128	AVX512VL
VMOVUPS	ymmreg mask z, ymmrm256	AVX512VL
VMOVUPS	zmmreg mask z, zmmrm512	AVX512
VMOVUPS	xmmreg mask z, xmmreg	AVX512VL
VMOVUPS	ymmreg mask z, ymmreg	AVX512VL
VMOVUPS	zmmreg mask z, zmmreg	AVX512
VMOVUPS	mem128 mask, xmmreg	AVX512VL
VMOVUPS	mem256 mask, ymmreg	AVX512VL
VMOVUPS	mem512 mask, zmmreg	AVX512
VMULPD	xmmreg mask z, xmmreg*, xmmrm128 b64	AVX512VL
VMULPD	ymmreg mask z, ymmreg*, ymmrm256 b64	AVX512VL
VMULPD	zmmreg mask z, zmmreg*, zmmrm512 b64 er	AVX512
VMULPS	xmmreg mask z, xmmreg*, xmmrm128 b32	AVX512VL
VMULPS	ymmreg mask z, ymmreg*, ymmrm256 b32	AVX512VL
VMULPS	zmmreg mask z, zmmreg*, zmmrm512 b32 er	AVX512
VMULSD	xmmreg mask z, xmmreg*, xmmrm64 er	AVX512
VMULSS	xmmreg mask z, xmmreg*, xmmrm32 er	AVX512
VORPD	xmmreg mask z, xmmreg*, xmmrm128 b64	AVX512VL/DQ
VORPD	ymmreg mask z, ymmreg*, ymmrm256 b64	AVX512VL/DQ
VORPD	zmmreg mask z, zmmreg*, zmmrm512 b64	AVX512DQ

VORPS	xmmreg	mask	z, xmmreg*, xmrm128	b32 AVX512VL/DQ
VORPS	ymmreg	mask	z, ymmreg*, ymrm256	b32 AVX512VL/DQ
VORPS	zmmreg	mask	z, zmmreg*, zmrm512	b32 AVX512DQ
VPABSB	xmmreg	mask	z, xmrm128	AVX512VL/BW
VPABSB	ymmreg	mask	z, ymrm256	AVX512VL/BW
VPABSB	zmmreg	mask	z, zmrm512	AVX512BW
VPABSD	xmmreg	mask	z, xmrm128	b32 AVX512VL
VPABSD	ymmreg	mask	z, ymrm256	b32 AVX512VL
VPABSD	zmmreg	mask	z, zmrm512	b32 AVX512
VPABSQ	xmmreg	mask	z, xmrm128	b64 AVX512VL
VPABSQ	ymmreg	mask	z, ymrm256	b64 AVX512VL
VPABSQ	zmmreg	mask	z, zmrm512	b64 AVX512
VPABSW	xmmreg	mask	z, xmrm128	AVX512VL/BW
VPABSW	ymmreg	mask	z, ymrm256	AVX512VL/BW
VPABSW	zmmreg	mask	z, zmrm512	AVX512BW
VPACKSSDW	xmmreg	mask	z, xmmreg*, xmrm128	b32 AVX512VL/BW
VPACKSSDW	ymmreg	mask	z, ymmreg*, ymrm256	b32 AVX512VL/BW
VPACKSSDW	zmmreg	mask	z, zmmreg*, zmrm512	b32 AVX512BW
VPACKSSWB	xmmreg	mask	z, xmmreg*, xmrm128	AVX512VL/BW
VPACKSSWB	ymmreg	mask	z, ymmreg*, ymrm256	AVX512VL/BW
VPACKSSWB	zmmreg	mask	z, zmmreg*, zmrm512	AVX512BW
VPACKUSDW	xmmreg	mask	z, xmmreg*, xmrm128	b32 AVX512VL/BW
VPACKUSDW	ymmreg	mask	z, ymmreg*, ymrm256	b32 AVX512VL/BW
VPACKUSDW	zmmreg	mask	z, zmmreg*, zmrm512	b32 AVX512BW
VPACKUSWB	xmmreg	mask	z, xmmreg*, xmrm128	AVX512VL/BW
VPACKUSWB	ymmreg	mask	z, ymmreg*, ymrm256	AVX512VL/BW
VPACKUSWB	zmmreg	mask	z, zmmreg*, zmrm512	AVX512BW
VPADDB	xmmreg	mask	z, xmmreg*, xmrm128	AVX512VL/BW
VPADDB	ymmreg	mask	z, ymmreg*, ymrm256	AVX512VL/BW
VPADDB	zmmreg	mask	z, zmmreg*, zmrm512	AVX512BW
VPADD	xmmreg	mask	z, xmmreg*, xmrm128	b32 AVX512VL
VPADD	ymmreg	mask	z, ymmreg*, ymrm256	b32 AVX512VL
VPADD	zmmreg	mask	z, zmmreg*, zmrm512	b32 AVX512
VPADDQ	xmmreg	mask	z, xmmreg*, xmrm128	b64 AVX512VL
VPADDQ	ymmreg	mask	z, ymmreg*, ymrm256	b64 AVX512VL
VPADDQ	zmmreg	mask	z, zmmreg*, zmrm512	b64 AVX512
VPADDSB	xmmreg	mask	z, xmmreg*, xmrm128	AVX512VL/BW
VPADDSB	ymmreg	mask	z, ymmreg*, ymrm256	AVX512VL/BW
VPADDSB	zmmreg	mask	z, zmmreg*, zmrm512	AVX512BW
VPADDSW	xmmreg	mask	z, xmmreg*, xmrm128	AVX512VL/BW
VPADDSW	ymmreg	mask	z, ymmreg*, ymrm256	AVX512VL/BW
VPADDSW	zmmreg	mask	z, zmmreg*, zmrm512	AVX512BW
VPADDUSB	xmmreg	mask	z, xmmreg*, xmrm128	AVX512VL/BW
VPADDUSB	ymmreg	mask	z, ymmreg*, ymrm256	AVX512VL/BW
VPADDUSB	zmmreg	mask	z, zmmreg*, zmrm512	AVX512BW
VPADDUSW	xmmreg	mask	z, xmmreg*, xmrm128	AVX512VL/BW
VPADDUSW	ymmreg	mask	z, ymmreg*, ymrm256	AVX512VL/BW
VPADDUSW	zmmreg	mask	z, zmmreg*, zmrm512	AVX512BW
VPADDW	xmmreg	mask	z, xmmreg*, xmrm128	AVX512VL/BW
VPADDW	ymmreg	mask	z, ymmreg*, ymrm256	AVX512VL/BW
VPADDW	zmmreg	mask	z, zmmreg*, zmrm512	AVX512BW
VPALIGNR	xmmreg	mask	z, xmmreg*, xmrm128, imm8	AVX512VL/BW
VPALIGNR	ymmreg	mask	z, ymmreg*, ymrm256, imm8	AVX512VL/BW
VPALIGNR	zmmreg	mask	z, zmmreg*, zmrm512, imm8	AVX512BW

VPANDD	xmmreg	mask	z, xmmreg*, xmrm128	b32	AVX512VL
VPANDD	ymmreg	mask	z, ymmreg*, ymrm256	b32	AVX512VL
VPANDD	zmmreg	mask	z, zmmreg*, zmrm512	b32	AVX512
VPANDND	xmmreg	mask	z, xmmreg*, xmrm128	b32	AVX512VL
VPANDND	ymmreg	mask	z, ymmreg*, ymrm256	b32	AVX512VL
VPANDND	zmmreg	mask	z, zmmreg*, zmrm512	b32	AVX512
VPANDNQ	xmmreg	mask	z, xmmreg*, xmrm128	b64	AVX512VL
VPANDNQ	ymmreg	mask	z, ymmreg*, ymrm256	b64	AVX512VL
VPANDNQ	zmmreg	mask	z, zmmreg*, zmrm512	b64	AVX512
VPANDQ	xmmreg	mask	z, xmmreg*, xmrm128	b64	AVX512VL
VPANDQ	ymmreg	mask	z, ymmreg*, ymrm256	b64	AVX512VL
VPANDQ	zmmreg	mask	z, zmmreg*, zmrm512	b64	AVX512
VPAVGB	xmmreg	mask	z, xmmreg*, xmrm128	AVX512VL/BW	
VPAVGB	ymmreg	mask	z, ymmreg*, ymrm256	AVX512VL/BW	
VPAVGB	zmmreg	mask	z, zmmreg*, zmrm512	AVX512BW	
VPAVGW	xmmreg	mask	z, xmmreg*, xmrm128	AVX512VL/BW	
VPAVGW	ymmreg	mask	z, ymmreg*, ymrm256	AVX512VL/BW	
VPAVGW	zmmreg	mask	z, zmmreg*, zmrm512	AVX512BW	
VPBLENDMB	xmmreg	mask	z, xmmreg, xmrm128	AVX512VL/BW	
VPBLENDMB	ymmreg	mask	z, ymmreg, ymrm256	AVX512VL/BW	
VPBLENDMB	zmmreg	mask	z, zmmreg, zmrm512	AVX512BW	
VPBLENDMD	xmmreg	mask	z, xmmreg, xmrm128	b32	AVX512VL
VPBLENDMD	ymmreg	mask	z, ymmreg, ymrm256	b32	AVX512VL
VPBLENDMD	zmmreg	mask	z, zmmreg, zmrm512	b32	AVX512
VPBLENDMQ	xmmreg	mask	z, xmmreg, xmrm128	b64	AVX512VL
VPBLENDMQ	ymmreg	mask	z, ymmreg, ymrm256	b64	AVX512VL
VPBLENDMQ	zmmreg	mask	z, zmmreg, zmrm512	b64	AVX512
VPBLENDMW	xmmreg	mask	z, xmmreg, xmrm128	AVX512VL/BW	
VPBLENDMW	ymmreg	mask	z, ymmreg, ymrm256	AVX512VL/BW	
VPBLENDMW	zmmreg	mask	z, zmmreg, zmrm512	AVX512BW	
VPBROADCASTB	xmmreg	mask	z, xmrm8	AVX512VL/BW	
VPBROADCASTB	ymmreg	mask	z, xmrm8	AVX512VL/BW	
VPBROADCASTB	zmmreg	mask	z, xmrm8	AVX512BW	
VPBROADCASTB	xmmreg	mask	z, reg8	AVX512VL/BW	
VPBROADCASTB	xmmreg	mask	z, reg16	AVX512VL/BW	
VPBROADCASTB	xmmreg	mask	z, reg32	AVX512VL/BW	
VPBROADCASTB	xmmreg	mask	z, reg64	AVX512VL/BW	
VPBROADCASTB	ymmreg	mask	z, reg8	AVX512VL/BW	
VPBROADCASTB	ymmreg	mask	z, reg16	AVX512VL/BW	
VPBROADCASTB	ymmreg	mask	z, reg32	AVX512VL/BW	
VPBROADCASTB	ymmreg	mask	z, reg64	AVX512VL/BW	
VPBROADCASTB	zmmreg	mask	z, reg8	AVX512BW	
VPBROADCASTB	zmmreg	mask	z, reg16	AVX512BW	
VPBROADCASTB	zmmreg	mask	z, reg32	AVX512BW	
VPBROADCASTB	zmmreg	mask	z, reg64	AVX512BW	
VPBROADCASTD	xmmreg	mask	z, mem32	AVX512VL	
VPBROADCASTD	ymmreg	mask	z, mem32	AVX512VL	
VPBROADCASTD	zmmreg	mask	z, mem32	AVX512	
VPBROADCASTD	xmmreg	mask	z, xmmreg	AVX512VL	
VPBROADCASTD	ymmreg	mask	z, xmmreg	AVX512VL	
VPBROADCASTD	zmmreg	mask	z, xmmreg	AVX512	
VPBROADCASTD	xmmreg	mask	z, reg32	AVX512VL	
VPBROADCASTD	ymmreg	mask	z, reg32	AVX512VL	
VPBROADCASTD	zmmreg	mask	z, reg32	AVX512	

VPBROADCASTMB2Q	xmmreg, kreg		AVX512VL/CD
VPBROADCASTMB2Q	ymmreg, kreg		AVX512VL/CD
VPBROADCASTMB2Q	zmmreg, kreg		AVX512CD
VPBROADCASTMW2D	xmmreg, kreg		AVX512VL/CD
VPBROADCASTMW2D	ymmreg, kreg		AVX512VL/CD
VPBROADCASTMW2D	zmmreg, kreg		AVX512CD
VPBROADCASTQ	xmmreg mask	z, mem64	AVX512VL
VPBROADCASTQ	ymmreg mask	z, mem64	AVX512VL
VPBROADCASTQ	zmmreg mask	z, mem64	AVX512
VPBROADCASTQ	xmmreg mask	z, xmmreg	AVX512VL
VPBROADCASTQ	ymmreg mask	z, xmmreg	AVX512VL
VPBROADCASTQ	zmmreg mask	z, xmmreg	AVX512
VPBROADCASTQ	xmmreg mask	z, reg64	AVX512VL
VPBROADCASTQ	ymmreg mask	z, reg64	AVX512VL
VPBROADCASTQ	zmmreg mask	z, reg64	AVX512
VPBROADCASTW	xmmreg mask	z, xmrm16	AVX512VL/BW
VPBROADCASTW	ymmreg mask	z, xmrm16	AVX512VL/BW
VPBROADCASTW	zmmreg mask	z, xmrm16	AVX512BW
VPBROADCASTW	xmmreg mask	z, reg16	AVX512VL/BW
VPBROADCASTW	xmmreg mask	z, reg32	AVX512VL/BW
VPBROADCASTW	xmmreg mask	z, reg64	AVX512VL/BW
VPBROADCASTW	ymmreg mask	z, reg16	AVX512VL/BW
VPBROADCASTW	ymmreg mask	z, reg32	AVX512VL/BW
VPBROADCASTW	ymmreg mask	z, reg64	AVX512VL/BW
VPBROADCASTW	zmmreg mask	z, reg16	AVX512BW
VPBROADCASTW	zmmreg mask	z, reg32	AVX512BW
VPBROADCASTW	zmmreg mask	z, reg64	AVX512BW
VPCPEQB	kreg mask, xmmreg, xmrm128		AVX512VL/BW
VPCPEQB	kreg mask, ymmreg, ymrm256		AVX512VL/BW
VPCPEQB	kreg mask, zmmreg, zmrm512		AVX512BW
VPCPEQD	kreg mask, xmmreg, xmrm128	b32	AVX512VL
VPCPEQD	kreg mask, ymmreg, ymrm256	b32	AVX512VL
VPCPEQD	kreg mask, zmmreg, zmrm512	b32	AVX512
VPCPEQQ	kreg mask, xmmreg, xmrm128	b64	AVX512VL
VPCPEQQ	kreg mask, ymmreg, ymrm256	b64	AVX512VL
VPCPEQQ	kreg mask, zmmreg, zmrm512	b64	AVX512
VPCPEQUB	kreg mask, xmmreg, xmrm128		AVX512VL/BW
VPCPEQUB	kreg mask, ymmreg, ymrm256		AVX512VL/BW
VPCPEQUB	kreg mask, zmmreg, zmrm512		AVX512BW
VPCPEQUD	kreg mask, xmmreg, xmrm128	b32	AVX512VL
VPCPEQUD	kreg mask, ymmreg, ymrm256	b32	AVX512VL
VPCPEQUD	kreg mask, zmmreg, zmrm512	b32	AVX512
VPCPEQUQ	kreg mask, xmmreg, xmrm128	b64	AVX512VL
VPCPEQUQ	kreg mask, ymmreg, ymrm256	b64	AVX512VL
VPCPEQUQ	kreg mask, zmmreg, zmrm512	b64	AVX512
VPCPEQUW	kreg mask, xmmreg, xmrm128		AVX512VL/BW
VPCPEQUW	kreg mask, ymmreg, ymrm256		AVX512VL/BW
VPCPEQUW	kreg mask, zmmreg, zmrm512		AVX512BW
VPCPEQW	kreg mask, xmmreg, xmrm128		AVX512VL/BW
VPCPEQW	kreg mask, ymmreg, ymrm256		AVX512VL/BW
VPCPEQW	kreg mask, zmmreg, zmrm512		AVX512BW
VPCMPGEB	kreg mask, xmmreg, xmrm128		AVX512VL/BW
VPCMPGEB	kreg mask, ymmreg, ymrm256		AVX512VL/BW
VPCMPGEB	kreg mask, zmmreg, zmrm512		AVX512BW

VPCMPGED	kreg	mask, xmmreg, xmrm128	b32	AVX512VL
VPCMPGED	kreg	mask, ymmreg, ymrm256	b32	AVX512VL
VPCMPGED	kreg	mask, zmmreg, zmrm512	b32	AVX512
VPCMPGEQ	kreg	mask, xmmreg, xmrm128	b64	AVX512VL
VPCMPGEQ	kreg	mask, ymmreg, ymrm256	b64	AVX512VL
VPCMPGEQ	kreg	mask, zmmreg, zmrm512	b64	AVX512
VPCMPGEUB	kreg	mask, xmmreg, xmrm128	AVX512VL/BW	
VPCMPGEUB	kreg	mask, ymmreg, ymrm256	AVX512VL/BW	
VPCMPGEUB	kreg	mask, zmmreg, zmrm512	AVX512BW	
VPCMPGEUD	kreg	mask, xmmreg, xmrm128	b32	AVX512VL
VPCMPGEUD	kreg	mask, ymmreg, ymrm256	b32	AVX512VL
VPCMPGEUD	kreg	mask, zmmreg, zmrm512	b32	AVX512
VPCMPGEUQ	kreg	mask, xmmreg, xmrm128	b64	AVX512VL
VPCMPGEUQ	kreg	mask, ymmreg, ymrm256	b64	AVX512VL
VPCMPGEUQ	kreg	mask, zmmreg, zmrm512	b64	AVX512
VPCMPGEUW	kreg	mask, xmmreg, xmrm128	AVX512VL/BW	
VPCMPGEUW	kreg	mask, ymmreg, ymrm256	AVX512VL/BW	
VPCMPGEUW	kreg	mask, zmmreg, zmrm512	AVX512BW	
VPCMPGEW	kreg	mask, xmmreg, xmrm128	AVX512VL/BW	
VPCMPGEW	kreg	mask, ymmreg, ymrm256	AVX512VL/BW	
VPCMPGEW	kreg	mask, zmmreg, zmrm512	AVX512BW	
VPCMPGTB	kreg	mask, xmmreg, xmrm128	AVX512VL/BW	
VPCMPGTB	kreg	mask, ymmreg, ymrm256	AVX512VL/BW	
VPCMPGTB	kreg	mask, zmmreg, zmrm512	AVX512BW	
VPCMPGTD	kreg	mask, xmmreg, xmrm128	b32	AVX512VL
VPCMPGTD	kreg	mask, ymmreg, ymrm256	b32	AVX512VL
VPCMPGTD	kreg	mask, zmmreg, zmrm512	b32	AVX512
VPCMPGTQ	kreg	mask, xmmreg, xmrm128	b64	AVX512VL
VPCMPGTQ	kreg	mask, ymmreg, ymrm256	b64	AVX512VL
VPCMPGTQ	kreg	mask, zmmreg, zmrm512	b64	AVX512
VPCMPGTUB	kreg	mask, xmmreg, xmrm128	AVX512VL/BW	
VPCMPGTUB	kreg	mask, ymmreg, ymrm256	AVX512VL/BW	
VPCMPGTUB	kreg	mask, zmmreg, zmrm512	AVX512BW	
VPCMPGTUD	kreg	mask, xmmreg, xmrm128	b32	AVX512VL
VPCMPGTUD	kreg	mask, ymmreg, ymrm256	b32	AVX512VL
VPCMPGTUD	kreg	mask, zmmreg, zmrm512	b32	AVX512
VPCMPGTUQ	kreg	mask, xmmreg, xmrm128	b64	AVX512VL
VPCMPGTUQ	kreg	mask, ymmreg, ymrm256	b64	AVX512VL
VPCMPGTUQ	kreg	mask, zmmreg, zmrm512	b64	AVX512
VPCMPGTUW	kreg	mask, xmmreg, xmrm128	AVX512VL/BW	
VPCMPGTUW	kreg	mask, ymmreg, ymrm256	AVX512VL/BW	
VPCMPGTUW	kreg	mask, zmmreg, zmrm512	AVX512BW	
VPCMPGTW	kreg	mask, xmmreg, xmrm128	AVX512VL/BW	
VPCMPGTW	kreg	mask, ymmreg, ymrm256	AVX512VL/BW	
VPCMPGTW	kreg	mask, zmmreg, zmrm512	AVX512BW	
VPCMPLEB	kreg	mask, xmmreg, xmrm128	AVX512VL/BW	
VPCMPLEB	kreg	mask, ymmreg, ymrm256	AVX512VL/BW	
VPCMPLEB	kreg	mask, zmmreg, zmrm512	AVX512BW	
VPCMPLED	kreg	mask, xmmreg, xmrm128	b32	AVX512VL
VPCMPLED	kreg	mask, ymmreg, ymrm256	b32	AVX512VL
VPCMPLED	kreg	mask, zmmreg, zmrm512	b32	AVX512
VPCMPLEQ	kreg	mask, xmmreg, xmrm128	b64	AVX512VL
VPCMPLEQ	kreg	mask, ymmreg, ymrm256	b64	AVX512VL
VPCMPLEQ	kreg	mask, zmmreg, zmrm512	b64	AVX512

VPCMPLEUB	kreg	mask, xmmreg, xmrm128	AVX512VL/BW
VPCMPLEUB	kreg	mask, ymmreg, ymrm256	AVX512VL/BW
VPCMPLEUB	kreg	mask, zmmreg, zmrm512	AVX512BW
VPCMPLEUD	kreg	mask, xmmreg, xmrm128	b32 AVX512VL
VPCMPLEUD	kreg	mask, ymmreg, ymrm256	b32 AVX512VL
VPCMPLEUD	kreg	mask, zmmreg, zmrm512	b32 AVX512
VPCMPLEUQ	kreg	mask, xmmreg, xmrm128	b64 AVX512VL
VPCMPLEUQ	kreg	mask, ymmreg, ymrm256	b64 AVX512VL
VPCMPLEUQ	kreg	mask, zmmreg, zmrm512	b64 AVX512
VPCMPLEUW	kreg	mask, xmmreg, xmrm128	AVX512VL/BW
VPCMPLEUW	kreg	mask, ymmreg, ymrm256	AVX512VL/BW
VPCMPLEUW	kreg	mask, zmmreg, zmrm512	AVX512BW
VPCMPLEW	kreg	mask, xmmreg, xmrm128	AVX512VL/BW
VPCMPLEW	kreg	mask, ymmreg, ymrm256	AVX512VL/BW
VPCMPLEW	kreg	mask, zmmreg, zmrm512	AVX512BW
VPCMPLTB	kreg	mask, xmmreg, xmrm128	AVX512VL/BW
VPCMPLTB	kreg	mask, ymmreg, ymrm256	AVX512VL/BW
VPCMPLTB	kreg	mask, zmmreg, zmrm512	AVX512BW
VPCMPLTD	kreg	mask, xmmreg, xmrm128	b32 AVX512VL
VPCMPLTD	kreg	mask, ymmreg, ymrm256	b32 AVX512VL
VPCMPLTD	kreg	mask, zmmreg, zmrm512	b32 AVX512
VPCMPLTQ	kreg	mask, xmmreg, xmrm128	b64 AVX512VL
VPCMPLTQ	kreg	mask, ymmreg, ymrm256	b64 AVX512VL
VPCMPLTQ	kreg	mask, zmmreg, zmrm512	b64 AVX512
VPCMPLTUB	kreg	mask, xmmreg, xmrm128	AVX512VL/BW
VPCMPLTUB	kreg	mask, ymmreg, ymrm256	AVX512VL/BW
VPCMPLTUB	kreg	mask, zmmreg, zmrm512	AVX512BW
VPCMPLTUD	kreg	mask, xmmreg, xmrm128	b32 AVX512VL
VPCMPLTUD	kreg	mask, ymmreg, ymrm256	b32 AVX512VL
VPCMPLTUD	kreg	mask, zmmreg, zmrm512	b32 AVX512
VPCMPLTUQ	kreg	mask, xmmreg, xmrm128	b64 AVX512VL
VPCMPLTUQ	kreg	mask, ymmreg, ymrm256	b64 AVX512VL
VPCMPLTUQ	kreg	mask, zmmreg, zmrm512	b64 AVX512
VPCMPLTUW	kreg	mask, xmmreg, xmrm128	AVX512VL/BW
VPCMPLTUW	kreg	mask, ymmreg, ymrm256	AVX512VL/BW
VPCMPLTUW	kreg	mask, zmmreg, zmrm512	AVX512BW
VPCMPLTW	kreg	mask, xmmreg, xmrm128	AVX512VL/BW
VPCMPLTW	kreg	mask, ymmreg, ymrm256	AVX512VL/BW
VPCMPLTW	kreg	mask, zmmreg, zmrm512	AVX512BW
VPCMPNEQB	kreg	mask, xmmreg, xmrm128	AVX512VL/BW
VPCMPNEQB	kreg	mask, ymmreg, ymrm256	AVX512VL/BW
VPCMPNEQB	kreg	mask, zmmreg, zmrm512	AVX512BW
VPCMPNEQD	kreg	mask, xmmreg, xmrm128	b32 AVX512VL
VPCMPNEQD	kreg	mask, ymmreg, ymrm256	b32 AVX512VL
VPCMPNEQD	kreg	mask, zmmreg, zmrm512	b32 AVX512
VPCMPNEQQ	kreg	mask, xmmreg, xmrm128	b64 AVX512VL
VPCMPNEQQ	kreg	mask, ymmreg, ymrm256	b64 AVX512VL
VPCMPNEQQ	kreg	mask, zmmreg, zmrm512	b64 AVX512
VPCMPNEQUB	kreg	mask, xmmreg, xmrm128	AVX512VL/BW
VPCMPNEQUB	kreg	mask, ymmreg, ymrm256	AVX512VL/BW
VPCMPNEQUB	kreg	mask, zmmreg, zmrm512	AVX512BW
VPCMPNEQUD	kreg	mask, xmmreg, xmrm128	b32 AVX512VL
VPCMPNEQUD	kreg	mask, ymmreg, ymrm256	b32 AVX512VL
VPCMPNEQUD	kreg	mask, zmmreg, zmrm512	b32 AVX512

VPCMPNEQUQ	kreg mask,xmmreg,xmmrm128	b64 AVX512VL
VPCMPNEQUQ	kreg mask,ymmreg,ymmrm256	b64 AVX512VL
VPCMPNEQUQ	kreg mask,zmmreg,zmmrm512	b64 AVX512
VPCMPNEQUW	kreg mask,xmmreg,xmmrm128	AVX512VL/BW
VPCMPNEQUW	kreg mask,ymmreg,ymmrm256	AVX512VL/BW
VPCMPNEQUW	kreg mask,zmmreg,zmmrm512	AVX512BW
VPCMPNEQW	kreg mask,xmmreg,xmmrm128	AVX512VL/BW
VPCMPNEQW	kreg mask,ymmreg,ymmrm256	AVX512VL/BW
VPCMPNEQW	kreg mask,zmmreg,zmmrm512	AVX512BW
VPCMPNGTB	kreg mask,xmmreg,xmmrm128	AVX512VL/BW
VPCMPNGTB	kreg mask,ymmreg,ymmrm256	AVX512VL/BW
VPCMPNGTB	kreg mask,zmmreg,zmmrm512	AVX512BW
VPCMPNGTD	kreg mask,xmmreg,xmmrm128	b32 AVX512VL
VPCMPNGTD	kreg mask,ymmreg,ymmrm256	b32 AVX512VL
VPCMPNGTD	kreg mask,zmmreg,zmmrm512	b32 AVX512
VPCMPNGTQ	kreg mask,xmmreg,xmmrm128	b64 AVX512VL
VPCMPNGTQ	kreg mask,ymmreg,ymmrm256	b64 AVX512VL
VPCMPNGTQ	kreg mask,zmmreg,zmmrm512	b64 AVX512
VPCMPNGTUB	kreg mask,xmmreg,xmmrm128	AVX512VL/BW
VPCMPNGTUB	kreg mask,ymmreg,ymmrm256	AVX512VL/BW
VPCMPNGTUB	kreg mask,zmmreg,zmmrm512	AVX512BW
VPCMPNGTUD	kreg mask,xmmreg,xmmrm128	b32 AVX512VL
VPCMPNGTUD	kreg mask,ymmreg,ymmrm256	b32 AVX512VL
VPCMPNGTUD	kreg mask,zmmreg,zmmrm512	b32 AVX512
VPCMPNGTUQ	kreg mask,xmmreg,xmmrm128	b64 AVX512VL
VPCMPNGTUQ	kreg mask,ymmreg,ymmrm256	b64 AVX512VL
VPCMPNGTUQ	kreg mask,zmmreg,zmmrm512	b64 AVX512
VPCMPNGTUW	kreg mask,xmmreg,xmmrm128	AVX512VL/BW
VPCMPNGTUW	kreg mask,ymmreg,ymmrm256	AVX512VL/BW
VPCMPNGTUW	kreg mask,zmmreg,zmmrm512	AVX512BW
VPCMPNGTW	kreg mask,xmmreg,xmmrm128	AVX512VL/BW
VPCMPNGTW	kreg mask,ymmreg,ymmrm256	AVX512VL/BW
VPCMPNGTW	kreg mask,zmmreg,zmmrm512	AVX512BW
VPCMPNLEB	kreg mask,xmmreg,xmmrm128	AVX512VL/BW
VPCMPNLEB	kreg mask,ymmreg,ymmrm256	AVX512VL/BW
VPCMPNLEB	kreg mask,zmmreg,zmmrm512	AVX512BW
VPCMPNLED	kreg mask,xmmreg,xmmrm128	b32 AVX512VL
VPCMPNLED	kreg mask,ymmreg,ymmrm256	b32 AVX512VL
VPCMPNLED	kreg mask,zmmreg,zmmrm512	b32 AVX512
VPCMPNLEQ	kreg mask,xmmreg,xmmrm128	b64 AVX512VL
VPCMPNLEQ	kreg mask,ymmreg,ymmrm256	b64 AVX512VL
VPCMPNLEQ	kreg mask,zmmreg,zmmrm512	b64 AVX512
VPCMPNLEUB	kreg mask,xmmreg,xmmrm128	AVX512VL/BW
VPCMPNLEUB	kreg mask,ymmreg,ymmrm256	AVX512VL/BW
VPCMPNLEUB	kreg mask,zmmreg,zmmrm512	AVX512BW
VPCMPNLEUD	kreg mask,xmmreg,xmmrm128	b32 AVX512VL
VPCMPNLEUD	kreg mask,ymmreg,ymmrm256	b32 AVX512VL
VPCMPNLEUD	kreg mask,zmmreg,zmmrm512	b32 AVX512
VPCMPNLEUQ	kreg mask,xmmreg,xmmrm128	b64 AVX512VL
VPCMPNLEUQ	kreg mask,ymmreg,ymmrm256	b64 AVX512VL
VPCMPNLEUQ	kreg mask,zmmreg,zmmrm512	b64 AVX512
VPCMPNLEUW	kreg mask,xmmreg,xmmrm128	AVX512VL/BW
VPCMPNLEUW	kreg mask,ymmreg,ymmrm256	AVX512VL/BW
VPCMPNLEUW	kreg mask,zmmreg,zmmrm512	AVX512BW

VPCMPNLEW	kreg mask,xmmreg,xmmrm128	AVX512VL/BW
VPCMPNLEW	kreg mask,ymmreg,ymmrm256	AVX512VL/BW
VPCMPNLEW	kreg mask,zmmreg,zmmrm512	AVX512BW
VPCMPNLTB	kreg mask,xmmreg,xmmrm128	AVX512VL/BW
VPCMPNLTB	kreg mask,ymmreg,ymmrm256	AVX512VL/BW
VPCMPNLTB	kreg mask,zmmreg,zmmrm512	AVX512BW
VPCMPNLTD	kreg mask,xmmreg,xmmrm128	b32 AVX512VL
VPCMPNLTD	kreg mask,ymmreg,ymmrm256	b32 AVX512VL
VPCMPNLTD	kreg mask,zmmreg,zmmrm512	b32 AVX512
VPCMPNLTD	kreg mask,xmmreg,xmmrm128	b64 AVX512VL
VPCMPNLTD	kreg mask,ymmreg,ymmrm256	b64 AVX512VL
VPCMPNLTD	kreg mask,zmmreg,zmmrm512	b64 AVX512
VPCMPNLTD	kreg mask,xmmreg,xmmrm128	AVX512VL/BW
VPCMPNLTD	kreg mask,ymmreg,ymmrm256	AVX512VL/BW
VPCMPNLTD	kreg mask,zmmreg,zmmrm512	AVX512BW
VPCMPNLTD	kreg mask,xmmreg,xmmrm128	b32 AVX512VL
VPCMPNLTD	kreg mask,ymmreg,ymmrm256	b32 AVX512VL
VPCMPNLTD	kreg mask,zmmreg,zmmrm512	b32 AVX512
VPCMPNLTD	kreg mask,xmmreg,xmmrm128	b64 AVX512VL
VPCMPNLTD	kreg mask,ymmreg,ymmrm256	b64 AVX512VL
VPCMPNLTD	kreg mask,zmmreg,zmmrm512	b64 AVX512
VPCMPNLTD	kreg mask,xmmreg,xmmrm128	AVX512VL/BW
VPCMPNLTD	kreg mask,ymmreg,ymmrm256	AVX512VL/BW
VPCMPNLTD	kreg mask,zmmreg,zmmrm512	AVX512BW
VPCMPNLTD	kreg mask,xmmreg,xmmrm128	AVX512VL/BW
VPCMPNLTD	kreg mask,ymmreg,ymmrm256	AVX512VL/BW
VPCMPNLTD	kreg mask,zmmreg,zmmrm512	AVX512BW
VPCMPNB	kreg mask,xmmreg,xmmrm128,imm8	AVX512VL/BW
VPCMPNB	kreg mask,ymmreg,ymmrm256,imm8	AVX512VL/BW
VPCMPNB	kreg mask,zmmreg,zmmrm512,imm8	AVX512BW
VPCMPD	kreg mask,xmmreg,xmmrm128	b32,imm8 AVX512VL
VPCMPD	kreg mask,ymmreg,ymmrm256	b32,imm8 AVX512VL
VPCMPD	kreg mask,zmmreg,zmmrm512	b32,imm8 AVX512
VPCMPQ	kreg mask,xmmreg,xmmrm128	b64,imm8 AVX512VL
VPCMPQ	kreg mask,ymmreg,ymmrm256	b64,imm8 AVX512VL
VPCMPQ	kreg mask,zmmreg,zmmrm512	b64,imm8 AVX512
VPCMPUB	kreg mask,xmmreg,xmmrm128,imm8	AVX512VL/BW
VPCMPUB	kreg mask,ymmreg,ymmrm256,imm8	AVX512VL/BW
VPCMPUB	kreg mask,zmmreg,zmmrm512,imm8	AVX512BW
VPCMPUD	kreg mask,xmmreg,xmmrm128	b32,imm8 AVX512VL
VPCMPUD	kreg mask,ymmreg,ymmrm256	b32,imm8 AVX512VL
VPCMPUD	kreg mask,zmmreg,zmmrm512	b32,imm8 AVX512
VPCMPUQ	kreg mask,xmmreg,xmmrm128	b64,imm8 AVX512VL
VPCMPUQ	kreg mask,ymmreg,ymmrm256	b64,imm8 AVX512VL
VPCMPUQ	kreg mask,zmmreg,zmmrm512	b64,imm8 AVX512
VPCMPUW	kreg mask,xmmreg,xmmrm128,imm8	AVX512VL/BW
VPCMPUW	kreg mask,ymmreg,ymmrm256,imm8	AVX512VL/BW
VPCMPUW	kreg mask,zmmreg,zmmrm512,imm8	AVX512BW
VPCMPW	kreg mask,xmmreg,xmmrm128,imm8	AVX512VL/BW
VPCMPW	kreg mask,ymmreg,ymmrm256,imm8	AVX512VL/BW
VPCMPW	kreg mask,zmmreg,zmmrm512,imm8	AVX512BW
VPCOMPRESSD	mem128 mask,xmmreg	AVX512VL
VPCOMPRESSD	mem256 mask,ymmreg	AVX512VL
VPCOMPRESSD	mem512 mask,zmmreg	AVX512

VPCOMPRESSD	xmmreg	mask	z, xmmreg	AVX512VL
VPCOMPRESSD	yymmreg	mask	z, yymmreg	AVX512VL
VPCOMPRESSD	zmmreg	mask	z, zmmreg	AVX512
VPCOMPRESSQ	mem128	mask, xmmreg		AVX512VL
VPCOMPRESSQ	mem256	mask, yymmreg		AVX512VL
VPCOMPRESSQ	mem512	mask, zmmreg		AVX512
VPCOMPRESSQ	xmmreg	mask	z, xmmreg	AVX512VL
VPCOMPRESSQ	yymmreg	mask	z, yymmreg	AVX512VL
VPCOMPRESSQ	zmmreg	mask	z, zmmreg	AVX512
VPCONFLICTD	xmmreg	mask	z, xmrm128	b32 AVX512VL/CD
VPCONFLICTD	yymmreg	mask	z, yymrm256	b32 AVX512VL/CD
VPCONFLICTD	zmmreg	mask	z, zmrm512	b32 AVX512CD
VPCONFLICTQ	xmmreg	mask	z, xmrm128	b64 AVX512VL/CD
VPCONFLICTQ	yymmreg	mask	z, yymrm256	b64 AVX512VL/CD
VPCONFLICTQ	zmmreg	mask	z, zmrm512	b64 AVX512CD
VPERMB	xmmreg	mask	z, xmmreg*, xmrm128	AVX512VL/VBMI
VPERMB	yymmreg	mask	z, yymmreg*, yymrm256	AVX512VL/VBMI
VPERMB	zmmreg	mask	z, zmmreg*, zmrm512	AVX512VBMI
VPERMD	yymmreg	mask	z, yymmreg*, yymrm256	b32 AVX512VL
VPERMD	zmmreg	mask	z, zmmreg*, zmrm512	b32 AVX512
VPERMI2B	xmmreg	mask	z, xmmreg*, xmrm128	AVX512VL/VBMI
VPERMI2B	yymmreg	mask	z, yymmreg*, yymrm256	AVX512VL/VBMI
VPERMI2B	zmmreg	mask	z, zmmreg*, zmrm512	AVX512VBMI
VPERMI2D	xmmreg	mask	z, xmmreg*, xmrm128	b32 AVX512VL
VPERMI2D	yymmreg	mask	z, yymmreg*, yymrm256	b32 AVX512VL
VPERMI2D	zmmreg	mask	z, zmmreg*, zmrm512	b32 AVX512
VPERMI2PD	xmmreg	mask	z, xmmreg*, xmrm128	b64 AVX512VL
VPERMI2PD	yymmreg	mask	z, yymmreg*, yymrm256	b64 AVX512VL
VPERMI2PD	zmmreg	mask	z, zmmreg*, zmrm512	b64 AVX512
VPERMI2PS	xmmreg	mask	z, xmmreg*, xmrm128	b32 AVX512VL
VPERMI2PS	yymmreg	mask	z, yymmreg*, yymrm256	b32 AVX512VL
VPERMI2PS	zmmreg	mask	z, zmmreg*, zmrm512	b32 AVX512
VPERMI2Q	xmmreg	mask	z, xmmreg*, xmrm128	b64 AVX512VL
VPERMI2Q	yymmreg	mask	z, yymmreg*, yymrm256	b64 AVX512VL
VPERMI2Q	zmmreg	mask	z, zmmreg*, zmrm512	b64 AVX512
VPERMI2W	xmmreg	mask	z, xmmreg*, xmrm128	AVX512VL/BW
VPERMI2W	yymmreg	mask	z, yymmreg*, yymrm256	AVX512VL/BW
VPERMI2W	zmmreg	mask	z, zmmreg*, zmrm512	AVX512BW
VPERMILPD	xmmreg	mask	z, xmrm128	b64, imm8 AVX512VL
VPERMILPD	yymmreg	mask	z, yymrm256	b64, imm8 AVX512VL
VPERMILPD	zmmreg	mask	z, zmrm512	b64, imm8 AVX512
VPERMILPD	xmmreg	mask	z, xmmreg*, xmrm128	b64 AVX512VL
VPERMILPD	yymmreg	mask	z, yymmreg*, yymrm256	b64 AVX512VL
VPERMILPD	zmmreg	mask	z, zmmreg*, zmrm512	b64 AVX512
VPERMILPS	xmmreg	mask	z, xmrm128	b32, imm8 AVX512VL
VPERMILPS	yymmreg	mask	z, yymrm256	b32, imm8 AVX512VL
VPERMILPS	zmmreg	mask	z, zmrm512	b32, imm8 AVX512
VPERMILPS	xmmreg	mask	z, xmmreg*, xmrm128	b32 AVX512VL
VPERMILPS	yymmreg	mask	z, yymmreg*, yymrm256	b32 AVX512VL
VPERMILPS	zmmreg	mask	z, zmmreg*, zmrm512	b32 AVX512
VPERMPD	yymmreg	mask	z, yymrm256	b64, imm8 AVX512VL
VPERMPD	zmmreg	mask	z, zmrm512	b64, imm8 AVX512
VPERMPD	yymmreg	mask	z, yymmreg*, yymrm256	b64 AVX512VL
VPERMPD	zmmreg	mask	z, zmmreg*, zmrm512	b64 AVX512

VPERMPS	ymmreg mask z,ymmreg*,ymmrm256 b32	AVX512VL
VPERMPS	zmmreg mask z,zmmreg*,zmmrm512 b32	AVX512
VPERMQ	ymmreg mask z,ymmrm256 b64,imm8	AVX512VL
VPERMQ	zmmreg mask z,zmmrm512 b64,imm8	AVX512
VPERMQ	ymmreg mask z,ymmreg*,ymmrm256 b64	AVX512VL
VPERMQ	zmmreg mask z,zmmreg*,zmmrm512 b64	AVX512
VPERMT2B	xmmreg mask z,xmmreg,xmmrm128	AVX512VL/VBMI
VPERMT2B	ymmreg mask z,ymmreg,ymmrm256	AVX512VL/VBMI
VPERMT2B	zmmreg mask z,zmmreg,zmmrm512	AVX512VBMI
VPERMT2D	xmmreg mask z,xmmreg,xmmrm128 b32	AVX512VL
VPERMT2D	ymmreg mask z,ymmreg,ymmrm256 b32	AVX512VL
VPERMT2D	zmmreg mask z,zmmreg,zmmrm512 b32	AVX512
VPERMT2PD	xmmreg mask z,xmmreg,xmmrm128 b64	AVX512VL
VPERMT2PD	ymmreg mask z,ymmreg,ymmrm256 b64	AVX512VL
VPERMT2PD	zmmreg mask z,zmmreg,zmmrm512 b64	AVX512
VPERMT2PS	xmmreg mask z,xmmreg,xmmrm128 b32	AVX512VL
VPERMT2PS	ymmreg mask z,ymmreg,ymmrm256 b32	AVX512VL
VPERMT2PS	zmmreg mask z,zmmreg,zmmrm512 b32	AVX512
VPERMT2Q	xmmreg mask z,xmmreg,xmmrm128 b64	AVX512VL
VPERMT2Q	ymmreg mask z,ymmreg,ymmrm256 b64	AVX512VL
VPERMT2Q	zmmreg mask z,zmmreg,zmmrm512 b64	AVX512
VPERMT2W	xmmreg mask z,xmmreg,xmmrm128	AVX512VL/BW
VPERMT2W	ymmreg mask z,ymmreg,ymmrm256	AVX512VL/BW
VPERMT2W	zmmreg mask z,zmmreg,zmmrm512	AVX512BW
VPERMW	xmmreg mask z,xmmreg*,xmmrm128	AVX512VL/BW
VPERMW	ymmreg mask z,ymmreg*,ymmrm256	AVX512VL/BW
VPERMW	zmmreg mask z,zmmreg*,zmmrm512	AVX512BW
VEXPANDD	xmmreg mask z,mem128	AVX512VL
VEXPANDD	ymmreg mask z,mem256	AVX512VL
VEXPANDD	zmmreg mask z,mem512	AVX512
VEXPANDD	xmmreg mask z,xmmreg	AVX512VL
VEXPANDD	ymmreg mask z,ymmreg	AVX512VL
VEXPANDD	zmmreg mask z,zmmreg	AVX512
VEXPANDQ	xmmreg mask z,mem128	AVX512VL
VEXPANDQ	ymmreg mask z,mem256	AVX512VL
VEXPANDQ	zmmreg mask z,mem512	AVX512
VEXPANDQ	xmmreg mask z,xmmreg	AVX512VL
VEXPANDQ	ymmreg mask z,ymmreg	AVX512VL
VEXPANDQ	zmmreg mask z,zmmreg	AVX512
VPEXTRB	reg8,xmmreg,imm8	AVX512BW
VPEXTRB	reg16,xmmreg,imm8	AVX512BW
VPEXTRB	reg32,xmmreg,imm8	AVX512BW
VPEXTRB	reg64,xmmreg,imm8	AVX512BW
VPEXTRB	mem8,xmmreg,imm8	AVX512BW
VPEXTRD	rm32,xmmreg,imm8	AVX512DQ
VPEXTRQ	rm64,xmmreg,imm8	AVX512DQ
VPEXTRW	reg16,xmmreg,imm8	AVX512BW
VPEXTRW	reg32,xmmreg,imm8	AVX512BW
VPEXTRW	reg64,xmmreg,imm8	AVX512BW
VPEXTRW	mem16,xmmreg,imm8	AVX512BW
VPEXTRW	reg16,xmmreg,imm8	AVX512BW
VPEXTRW	reg32,xmmreg,imm8	AVX512BW
VPEXTRW	reg64,xmmreg,imm8	AVX512BW
VPGATHERDD	xmmreg mask,xmem32	AVX512VL

VPGATHERDD	ymmreg	mask,ymem32		AVX512VL
VPGATHERDD	zmmreg	mask,zmem32		AVX512
VPGATHERDQ	xmmreg	mask,xmem64		AVX512VL
VPGATHERDQ	ymmreg	mask,xmem64		AVX512VL
VPGATHERDQ	zmmreg	mask,ymem64		AVX512
VPGATHERQD	xmmreg	mask,xmem32		AVX512VL
VPGATHERQD	xmmreg	mask,ymem32		AVX512VL
VPGATHERQD	ymmreg	mask,zmem32		AVX512
VPGATHERQQ	xmmreg	mask,xmem64		AVX512VL
VPGATHERQQ	ymmreg	mask,ymem64		AVX512VL
VPGATHERQQ	zmmreg	mask,zmem64		AVX512
VPINSRB	xmmreg	xmmreg*,reg32,imm8		AVX512BW
VPINSRB	xmmreg	xmmreg*,mem8,imm8		AVX512BW
VPINSRD	xmmreg	xmmreg*,rm32,imm8		AVX512DQ
VPINSRQ	xmmreg	xmmreg*,rm64,imm8		AVX512DQ
VPINSRW	xmmreg	xmmreg*,reg32,imm8		AVX512BW
VPINSRW	xmmreg	xmmreg*,mem16,imm8		AVX512BW
VPLZCNTD	xmmreg	mask z,xmmrm128	b32	AVX512VL/CD
VPLZCNTD	ymmreg	mask z,ymmrm256	b32	AVX512VL/CD
VPLZCNTD	zmmreg	mask z,zmmrm512	b32	AVX512CD
VPLZCNTQ	xmmreg	mask z,xmmrm128	b64	AVX512VL/CD
VPLZCNTQ	ymmreg	mask z,ymmrm256	b64	AVX512VL/CD
VPLZCNTQ	zmmreg	mask z,zmmrm512	b64	AVX512CD
VPMADD52HUQ	xmmreg	mask z,xmmreg,xmmrm128	b64	AVX512VL/IFMA
VPMADD52HUQ	ymmreg	mask z,ymmreg,ymmrm256	b64	AVX512VL/IFMA
VPMADD52HUQ	zmmreg	mask z,zmmreg,zmmrm512	b64	AVX512IFMA
VPMADD52LUQ	xmmreg	mask z,xmmreg,xmmrm128	b64	AVX512VL/IFMA
VPMADD52LUQ	ymmreg	mask z,ymmreg,ymmrm256	b64	AVX512VL/IFMA
VPMADD52LUQ	zmmreg	mask z,zmmreg,zmmrm512	b64	AVX512IFMA
VPMADDUBSW	xmmreg	mask z,xmmreg*,xmmrm128		AVX512VL/BW
VPMADDUBSW	ymmreg	mask z,ymmreg*,ymmrm256		AVX512VL/BW
VPMADDUBSW	zmmreg	mask z,zmmreg*,zmmrm512		AVX512BW
VPMADDWD	xmmreg	mask z,xmmreg*,xmmrm128		AVX512VL/BW
VPMADDWD	ymmreg	mask z,ymmreg*,ymmrm256		AVX512VL/BW
VPMADDWD	zmmreg	mask z,zmmreg*,zmmrm512		AVX512BW
VPMAXSB	xmmreg	mask z,xmmreg*,xmmrm128		AVX512VL/BW
VPMAXSB	ymmreg	mask z,ymmreg*,ymmrm256		AVX512VL/BW
VPMAXSB	zmmreg	mask z,zmmreg*,zmmrm512		AVX512BW
VPMAXSD	xmmreg	mask z,xmmreg*,xmmrm128	b32	AVX512VL
VPMAXSD	ymmreg	mask z,ymmreg*,ymmrm256	b32	AVX512VL
VPMAXSD	zmmreg	mask z,zmmreg*,zmmrm512	b32	AVX512
VPMAXSQ	xmmreg	mask z,xmmreg*,xmmrm128	b64	AVX512VL
VPMAXSQ	ymmreg	mask z,ymmreg*,ymmrm256	b64	AVX512VL
VPMAXSQ	zmmreg	mask z,zmmreg*,zmmrm512	b64	AVX512
VPMAXSW	xmmreg	mask z,xmmreg*,xmmrm128		AVX512VL/BW
VPMAXSW	ymmreg	mask z,ymmreg*,ymmrm256		AVX512VL/BW
VPMAXSW	zmmreg	mask z,zmmreg*,zmmrm512		AVX512BW
VPMAXUB	xmmreg	mask z,xmmreg*,xmmrm128		AVX512VL/BW
VPMAXUB	ymmreg	mask z,ymmreg*,ymmrm256		AVX512VL/BW
VPMAXUB	zmmreg	mask z,zmmreg*,zmmrm512		AVX512BW
VPMAXUD	xmmreg	mask z,xmmreg*,xmmrm128	b32	AVX512VL
VPMAXUD	ymmreg	mask z,ymmreg*,ymmrm256	b32	AVX512VL
VPMAXUD	zmmreg	mask z,zmmreg*,zmmrm512	b32	AVX512
VPMAXUQ	xmmreg	mask z,xmmreg*,xmmrm128	b64	AVX512VL

VPMAXUQ	ymmreg	mask	z, ymmreg*	, ymmrm256	b64	AVX512VL
VPMAXUQ	zmmreg	mask	z, zmmreg*	, zmmrm512	b64	AVX512
VPMAXUW	xmmreg	mask	z, xmmreg*	, xmmrm128		AVX512VL/BW
VPMAXUW	ymmreg	mask	z, ymmreg*	, ymmrm256		AVX512VL/BW
VPMAXUW	zmmreg	mask	z, zmmreg*	, zmmrm512		AVX512BW
VPMINSB	xmmreg	mask	z, xmmreg*	, xmmrm128		AVX512VL/BW
VPMINSB	ymmreg	mask	z, ymmreg*	, ymmrm256		AVX512VL/BW
VPMINSB	zmmreg	mask	z, zmmreg*	, zmmrm512		AVX512BW
VPMINSD	xmmreg	mask	z, xmmreg*	, xmmrm128	b32	AVX512VL
VPMINSD	ymmreg	mask	z, ymmreg*	, ymmrm256	b32	AVX512VL
VPMINSD	zmmreg	mask	z, zmmreg*	, zmmrm512	b32	AVX512
VPMINSQ	xmmreg	mask	z, xmmreg*	, xmmrm128	b64	AVX512VL
VPMINSQ	ymmreg	mask	z, ymmreg*	, ymmrm256	b64	AVX512VL
VPMINSQ	zmmreg	mask	z, zmmreg*	, zmmrm512	b64	AVX512
VPMINSW	xmmreg	mask	z, xmmreg*	, xmmrm128		AVX512VL/BW
VPMINSW	ymmreg	mask	z, ymmreg*	, ymmrm256		AVX512VL/BW
VPMINSW	zmmreg	mask	z, zmmreg*	, zmmrm512		AVX512BW
VPMINUB	xmmreg	mask	z, xmmreg*	, xmmrm128		AVX512VL/BW
VPMINUB	ymmreg	mask	z, ymmreg*	, ymmrm256		AVX512VL/BW
VPMINUB	zmmreg	mask	z, zmmreg*	, zmmrm512		AVX512BW
VPMINUD	xmmreg	mask	z, xmmreg*	, xmmrm128	b32	AVX512VL
VPMINUD	ymmreg	mask	z, ymmreg*	, ymmrm256	b32	AVX512VL
VPMINUD	zmmreg	mask	z, zmmreg*	, zmmrm512	b32	AVX512
VPMINUQ	xmmreg	mask	z, xmmreg*	, xmmrm128	b64	AVX512VL
VPMINUQ	ymmreg	mask	z, ymmreg*	, ymmrm256	b64	AVX512VL
VPMINUQ	zmmreg	mask	z, zmmreg*	, zmmrm512	b64	AVX512
VPMINUW	xmmreg	mask	z, xmmreg*	, xmmrm128		AVX512VL/BW
VPMINUW	ymmreg	mask	z, ymmreg*	, ymmrm256		AVX512VL/BW
VPMINUW	zmmreg	mask	z, zmmreg*	, zmmrm512		AVX512BW
VPMOVB2M	kreg, xmmreg					AVX512VL/BW
VPMOVB2M	kreg, ymmreg					AVX512VL/BW
VPMOVB2M	kreg, zmmreg					AVX512BW
VPMOVD2M	kreg, xmmreg					AVX512VL/DQ
VPMOVD2M	kreg, ymmreg					AVX512VL/DQ
VPMOVD2M	kreg, zmmreg					AVX512DQ
VPMOVDDB	xmmreg	mask	z, xmmreg			AVX512VL
VPMOVDDB	xmmreg	mask	z, ymmreg			AVX512VL
VPMOVDDB	xmmreg	mask	z, zmmreg			AVX512
VPMOVDDB	mem32	mask, xmmreg				AVX512VL
VPMOVDDB	mem64	mask, ymmreg				AVX512VL
VPMOVDDB	mem128	mask, zmmreg				AVX512
VPMOVDW	xmmreg	mask	z, xmmreg			AVX512VL
VPMOVDW	xmmreg	mask	z, ymmreg			AVX512VL
VPMOVDW	ymmreg	mask	z, zmmreg			AVX512
VPMOVDW	mem64	mask, xmmreg				AVX512VL
VPMOVDW	mem128	mask, ymmreg				AVX512VL
VPMOVDW	mem256	mask, zmmreg				AVX512
VPMOVM2B	xmmreg, kreg					AVX512VL/BW
VPMOVM2B	ymmreg, kreg					AVX512VL/BW
VPMOVM2B	zmmreg, kreg					AVX512BW
VPMOVM2D	xmmreg, kreg					AVX512VL/DQ
VPMOVM2D	ymmreg, kreg					AVX512VL/DQ
VPMOVM2D	zmmreg, kreg					AVX512DQ
VPMOVM2Q	xmmreg, kreg					AVX512VL/DQ

VPMOVM2Q	ymmreg, kreg	AVX512VL/DQ
VPMOVM2Q	zmmreg, kreg	AVX512DQ
VPMOVM2W	xmmreg, kreg	AVX512VL/BW
VPMOVM2W	ymmreg, kreg	AVX512VL/BW
VPMOVM2W	zmmreg, kreg	AVX512BW
VPMOVQ2M	kreg, xmmreg	AVX512VL/DQ
VPMOVQ2M	kreg, ymmreg	AVX512VL/DQ
VPMOVQ2M	kreg, zmmreg	AVX512DQ
VPMOVQB	xmmreg mask z, xmmreg	AVX512VL
VPMOVQB	xmmreg mask z, ymmreg	AVX512VL
VPMOVQB	xmmreg mask z, zmmreg	AVX512
VPMOVQB	mem16 mask, xmmreg	AVX512VL
VPMOVQB	mem32 mask, ymmreg	AVX512VL
VPMOVQB	mem64 mask, zmmreg	AVX512
VPMOVQD	xmmreg mask z, xmmreg	AVX512VL
VPMOVQD	xmmreg mask z, ymmreg	AVX512VL
VPMOVQD	ymmreg mask z, zmmreg	AVX512
VPMOVQD	mem64 mask, xmmreg	AVX512VL
VPMOVQD	mem128 mask, ymmreg	AVX512VL
VPMOVQD	mem256 mask, zmmreg	AVX512
VPMOVQW	xmmreg mask z, xmmreg	AVX512VL
VPMOVQW	xmmreg mask z, ymmreg	AVX512VL
VPMOVQW	xmmreg mask z, zmmreg	AVX512
VPMOVQW	mem32 mask, xmmreg	AVX512VL
VPMOVQW	mem64 mask, ymmreg	AVX512VL
VPMOVQW	mem128 mask, zmmreg	AVX512
VPMOVSDB	xmmreg mask z, xmmreg	AVX512VL
VPMOVSDB	xmmreg mask z, ymmreg	AVX512VL
VPMOVSDB	xmmreg mask z, zmmreg	AVX512
VPMOVSDB	mem32 mask, xmmreg	AVX512VL
VPMOVSDB	mem64 mask, ymmreg	AVX512VL
VPMOVSDB	mem128 mask, zmmreg	AVX512
VPMOVSDW	xmmreg mask z, xmmreg	AVX512VL
VPMOVSDW	xmmreg mask z, ymmreg	AVX512VL
VPMOVSDW	ymmreg mask z, zmmreg	AVX512
VPMOVSDW	mem64 mask, xmmreg	AVX512VL
VPMOVSDW	mem128 mask, ymmreg	AVX512VL
VPMOVSDW	mem256 mask, zmmreg	AVX512
VPMOVSQB	xmmreg mask z, xmmreg	AVX512VL
VPMOVSQB	xmmreg mask z, ymmreg	AVX512VL
VPMOVSQB	xmmreg mask z, zmmreg	AVX512
VPMOVSQB	mem16 mask, xmmreg	AVX512VL
VPMOVSQB	mem32 mask, ymmreg	AVX512VL
VPMOVSQB	mem64 mask, zmmreg	AVX512
VPMOVSQD	xmmreg mask z, xmmreg	AVX512VL
VPMOVSQD	xmmreg mask z, ymmreg	AVX512VL
VPMOVSQD	ymmreg mask z, zmmreg	AVX512
VPMOVSQD	mem64 mask, xmmreg	AVX512VL
VPMOVSQD	mem128 mask, ymmreg	AVX512VL
VPMOVSQD	mem256 mask, zmmreg	AVX512
VPMOVSQW	xmmreg mask z, xmmreg	AVX512VL
VPMOVSQW	xmmreg mask z, ymmreg	AVX512VL
VPMOVSQW	xmmreg mask z, zmmreg	AVX512
VPMOVSQW	mem32 mask, xmmreg	AVX512VL

VPMOVSQW	mem64	mask,ymmreg	AVX512VL
VPMOVSQW	mem128	mask,zmmreg	AVX512
VPMOVSWB	xmmreg	mask z,xmmreg	AVX512VL/BW
VPMOVSWB	xmmreg	mask z,ymmreg	AVX512VL/BW
VPMOVSWB	ymmreg	mask z,zmmreg	AVX512BW
VPMOVSWB	mem64	mask,xmmreg	AVX512VL/BW
VPMOVSWB	mem128	mask,ymmreg	AVX512VL/BW
VPMOVSWB	mem256	mask,zmmreg	AVX512BW
VPMOVXBD	xmmreg	mask z,xmmrm32	AVX512VL
VPMOVXBD	ymmreg	mask z,xmmrm64	AVX512VL
VPMOVXBD	zmmreg	mask z,xmmrm128	AVX512
VPMOVXBD	xmmreg	mask z,xmmrm16	AVX512VL
VPMOVXBD	ymmreg	mask z,xmmrm32	AVX512VL
VPMOVXBD	zmmreg	mask z,xmmrm64	AVX512
VPMOVXBD	xmmreg	mask z,xmmrm64	AVX512VL/BW
VPMOVXBD	ymmreg	mask z,xmmrm128	AVX512VL/BW
VPMOVXBD	zmmreg	mask z,ymmrm256	AVX512BW
VPMOVXBD	xmmreg	mask z,xmmrm64	AVX512VL
VPMOVXBD	ymmreg	mask z,xmmrm128	AVX512VL
VPMOVXBD	zmmreg	mask z,ymmrm256	AVX512
VPMOVXBD	xmmreg	mask z,xmmrm64	AVX512VL
VPMOVXBD	ymmreg	mask z,xmmrm128	AVX512VL
VPMOVXBD	zmmreg	mask z,ymmrm256	AVX512
VPMOVXBD	xmmreg	mask z,xmmrm32	AVX512VL
VPMOVXBD	ymmreg	mask z,xmmrm64	AVX512VL
VPMOVXBD	zmmreg	mask z,xmmrm128	AVX512
VPMOVUSDB	xmmreg	mask z,xmmreg	AVX512VL
VPMOVUSDB	xmmreg	mask z,ymmreg	AVX512VL
VPMOVUSDB	xmmreg	mask z,zmmreg	AVX512
VPMOVUSDB	mem32	mask,xmmreg	AVX512VL
VPMOVUSDB	mem64	mask,ymmreg	AVX512VL
VPMOVUSDB	mem128	mask,zmmreg	AVX512
VPMOVUSDB	xmmreg	mask z,xmmreg	AVX512VL
VPMOVUSDB	xmmreg	mask z,ymmreg	AVX512VL
VPMOVUSDB	ymmreg	mask z,zmmreg	AVX512
VPMOVUSDB	mem64	mask,xmmreg	AVX512VL
VPMOVUSDB	mem128	mask,ymmreg	AVX512VL
VPMOVUSDB	mem256	mask,zmmreg	AVX512
VPMOVUSDB	xmmreg	mask z,xmmreg	AVX512VL
VPMOVUSDB	xmmreg	mask z,ymmreg	AVX512VL
VPMOVUSDB	xmmreg	mask z,zmmreg	AVX512
VPMOVUSDB	mem16	mask,xmmreg	AVX512VL
VPMOVUSDB	mem32	mask,ymmreg	AVX512VL
VPMOVUSDB	mem64	mask,zmmreg	AVX512
VPMOVUSDB	xmmreg	mask z,xmmreg	AVX512VL
VPMOVUSDB	xmmreg	mask z,ymmreg	AVX512VL
VPMOVUSDB	ymmreg	mask z,zmmreg	AVX512
VPMOVUSDB	mem64	mask,xmmreg	AVX512VL
VPMOVUSDB	mem128	mask,ymmreg	AVX512VL
VPMOVUSDB	mem256	mask,zmmreg	AVX512
VPMOVUSDB	xmmreg	mask z,xmmreg	AVX512VL
VPMOVUSDB	xmmreg	mask z,ymmreg	AVX512VL
VPMOVUSDB	xmmreg	mask z,zmmreg	AVX512
VPMOVUSDB	mem32	mask,xmmreg	AVX512VL

VPMOVUSQW	mem64	mask,ymmreg		AVX512VL
VPMOVUSQW	mem128	mask,zmmreg		AVX512
VPMOVUSWB	xmmreg	mask z,xmmreg		AVX512VL/BW
VPMOVUSWB	xmmreg	mask z,ymmreg		AVX512VL/BW
VPMOVUSWB	ymmreg	mask z,zmmreg		AVX512BW
VPMOVUSWB	mem64	mask,xmmreg		AVX512VL/BW
VPMOVUSWB	mem128	mask,ymmreg		AVX512VL/BW
VPMOVUSWB	mem256	mask,zmmreg		AVX512BW
VPMOVW2M	kreg,xmmreg			AVX512VL/BW
VPMOVW2M	kreg,ymmreg			AVX512VL/BW
VPMOVW2M	kreg,zmmreg			AVX512BW
VPMOVWB	xmmreg	mask z,xmmreg		AVX512VL/BW
VPMOVWB	xmmreg	mask z,ymmreg		AVX512VL/BW
VPMOVWB	ymmreg	mask z,zmmreg		AVX512BW
VPMOVWB	mem64	mask,xmmreg		AVX512VL/BW
VPMOVWB	mem128	mask,ymmreg		AVX512VL/BW
VPMOVWB	mem256	mask,zmmreg		AVX512BW
VPMOVZXBD	xmmreg	mask z,xmmrm32		AVX512VL
VPMOVZXBD	ymmreg	mask z,xmmrm64		AVX512VL
VPMOVZXBD	zmmreg	mask z,xmmrm128		AVX512
VPMOVZXBQ	xmmreg	mask z,xmmrm16		AVX512VL
VPMOVZXBQ	ymmreg	mask z,xmmrm32		AVX512VL
VPMOVZXBQ	zmmreg	mask z,xmmrm64		AVX512
VPMOVZXBW	xmmreg	mask z,xmmrm64		AVX512VL/BW
VPMOVZXBW	ymmreg	mask z,xmmrm128		AVX512VL/BW
VPMOVZXBW	zmmreg	mask z,ymmrm256		AVX512BW
VPMOVZXDQ	xmmreg	mask z,xmmrm64		AVX512VL
VPMOVZXDQ	ymmreg	mask z,xmmrm128		AVX512VL
VPMOVZXDQ	zmmreg	mask z,ymmrm256		AVX512
VPMOVZXWD	xmmreg	mask z,xmmrm64		AVX512VL
VPMOVZXWD	ymmreg	mask z,xmmrm128		AVX512VL
VPMOVZXWD	zmmreg	mask z,ymmrm256		AVX512
VPMOVZXWQ	xmmreg	mask z,xmmrm32		AVX512VL
VPMOVZXWQ	ymmreg	mask z,xmmrm64		AVX512VL
VPMOVZXWQ	zmmreg	mask z,xmmrm128		AVX512
VPMULDQ	xmmreg	mask z,xmmreg*,xmmrm128	b64	AVX512VL
VPMULDQ	ymmreg	mask z,ymmreg*,ymmrm256	b64	AVX512VL
VPMULDQ	zmmreg	mask z,zmmreg*,zmmrm512	b64	AVX512
VPMULHRSW	xmmreg	mask z,xmmreg*,xmmrm128		AVX512VL/BW
VPMULHRSW	ymmreg	mask z,ymmreg*,ymmrm256		AVX512VL/BW
VPMULHRSW	zmmreg	mask z,zmmreg*,zmmrm512		AVX512BW
VPMULHUW	xmmreg	mask z,xmmreg*,xmmrm128		AVX512VL/BW
VPMULHUW	ymmreg	mask z,ymmreg*,ymmrm256		AVX512VL/BW
VPMULHUW	zmmreg	mask z,zmmreg*,zmmrm512		AVX512BW
VPMULHW	xmmreg	mask z,xmmreg*,xmmrm128		AVX512VL/BW
VPMULHW	ymmreg	mask z,ymmreg*,ymmrm256		AVX512VL/BW
VPMULHW	zmmreg	mask z,zmmreg*,zmmrm512		AVX512BW
VPMULLD	xmmreg	mask z,xmmreg*,xmmrm128	b32	AVX512VL
VPMULLD	ymmreg	mask z,ymmreg*,ymmrm256	b32	AVX512VL
VPMULLD	zmmreg	mask z,zmmreg*,zmmrm512	b32	AVX512
VPMULLQ	xmmreg	mask z,xmmreg*,xmmrm128	b64	AVX512VL/DQ
VPMULLQ	ymmreg	mask z,ymmreg*,ymmrm256	b64	AVX512VL/DQ
VPMULLQ	zmmreg	mask z,zmmreg*,zmmrm512	b64	AVX512DQ
VPMULLW	xmmreg	mask z,xmmreg*,xmmrm128		AVX512VL/BW

VPMULLW	ymmreg	mask	z, ymmreg*	ymmrm256	AVX512VL/BW
VPMULLW	zmmreg	mask	z, zmmreg*	zmmrm512	AVX512BW
VPMULTISHIFTQB	xmmreg	mask	z, xmmreg*	xmmrm128	b64 AVX512VL/VBMI
VPMULTISHIFTQB	ymmreg	mask	z, ymmreg*	ymmrm256	b64 AVX512VL/VBMI
VPMULTISHIFTQB	zmmreg	mask	z, zmmreg*	zmmrm512	b64 AVX512VBMI
VPMULUDQ	xmmreg	mask	z, xmmreg*	xmmrm128	b64 AVX512VL
VPMULUDQ	ymmreg	mask	z, ymmreg*	ymmrm256	b64 AVX512VL
VPMULUDQ	zmmreg	mask	z, zmmreg*	zmmrm512	b64 AVX512
VPORD	xmmreg	mask	z, xmmreg*	xmmrm128	b32 AVX512VL
VPORD	ymmreg	mask	z, ymmreg*	ymmrm256	b32 AVX512VL
VPORD	zmmreg	mask	z, zmmreg*	zmmrm512	b32 AVX512
VPORQ	xmmreg	mask	z, xmmreg*	xmmrm128	b64 AVX512VL
VPORQ	ymmreg	mask	z, ymmreg*	ymmrm256	b64 AVX512VL
VPORQ	zmmreg	mask	z, zmmreg*	zmmrm512	b64 AVX512
VPROLD	xmmreg	mask	z, xmmrm128	b32*, imm8	AVX512VL
VPROLD	ymmreg	mask	z, ymmrm256	b32*, imm8	AVX512VL
VPROLD	zmmreg	mask	z, zmmrm512	b32*, imm8	AVX512
VPROLQ	xmmreg	mask	z, xmmrm128	b64*, imm8	AVX512VL
VPROLQ	ymmreg	mask	z, ymmrm256	b64*, imm8	AVX512VL
VPROLQ	zmmreg	mask	z, zmmrm512	b64*, imm8	AVX512
VPROLVD	xmmreg	mask	z, xmmreg*	xmmrm128	b32 AVX512VL
VPROLVD	ymmreg	mask	z, ymmreg*	ymmrm256	b32 AVX512VL
VPROLVD	zmmreg	mask	z, zmmreg*	zmmrm512	b32 AVX512
VPROLVQ	xmmreg	mask	z, xmmreg*	xmmrm128	b64 AVX512VL
VPROLVQ	ymmreg	mask	z, ymmreg*	ymmrm256	b64 AVX512VL
VPROLVQ	zmmreg	mask	z, zmmreg*	zmmrm512	b64 AVX512
VPRORD	xmmreg	mask	z, xmmrm128	b32*, imm8	AVX512VL
VPRORD	ymmreg	mask	z, ymmrm256	b32*, imm8	AVX512VL
VPRORD	zmmreg	mask	z, zmmrm512	b32*, imm8	AVX512
VPRORQ	xmmreg	mask	z, xmmrm128	b64*, imm8	AVX512VL
VPRORQ	ymmreg	mask	z, ymmrm256	b64*, imm8	AVX512VL
VPRORQ	zmmreg	mask	z, zmmrm512	b64*, imm8	AVX512
VPRORVD	xmmreg	mask	z, xmmreg*	xmmrm128	b32 AVX512VL
VPRORVD	ymmreg	mask	z, ymmreg*	ymmrm256	b32 AVX512VL
VPRORVD	zmmreg	mask	z, zmmreg*	zmmrm512	b32 AVX512
VPRORVQ	xmmreg	mask	z, xmmreg*	xmmrm128	b64 AVX512VL
VPRORVQ	ymmreg	mask	z, ymmreg*	ymmrm256	b64 AVX512VL
VPRORVQ	zmmreg	mask	z, zmmreg*	zmmrm512	b64 AVX512
VPSADBW	xmmreg, xmmreg*		xmmrm128		AVX512VL/BW
VPSADBW	ymmreg, ymmreg*		ymmrm256		AVX512VL/BW
VPSADBW	zmmreg, zmmreg*		zmmrm512		AVX512BW
VPSCATTERDD	xmem32	mask, xmmreg			AVX512VL
VPSCATTERDD	yem32	mask, ymmreg			AVX512VL
VPSCATTERDD	zmem32	mask, zmmreg			AVX512
VPSCATTERDQ	xmem64	mask, xmmreg			AVX512VL
VPSCATTERDQ	xmem64	mask, ymmreg			AVX512VL
VPSCATTERDQ	yem64	mask, zmmreg			AVX512
VPSCATTERQD	xmem32	mask, xmmreg			AVX512VL
VPSCATTERQD	yem32	mask, xmmreg			AVX512VL
VPSCATTERQD	zmem32	mask, ymmreg			AVX512
VPSCATTERQQ	xmem64	mask, xmmreg			AVX512VL
VPSCATTERQQ	yem64	mask, ymmreg			AVX512VL
VPSCATTERQQ	zmem64	mask, zmmreg			AVX512
VPSHUFB	xmmreg	mask	z, xmmreg*	xmmrm128	AVX512VL/BW

VPSHUFB	ymmreg mask z,ymmreg*,ymmrm256	AVX512VL/BW
VPSHUFB	zmmreg mask z,zmmreg*,zmmrm512	AVX512BW
VPSHUFD	xmmreg mask z,xmmrm128 b32,imm8	AVX512VL
VPSHUFD	ymmreg mask z,ymmrm256 b32,imm8	AVX512VL
VPSHUFD	zmmreg mask z,zmmrm512 b32,imm8	AVX512
VPSHUFHW	xmmreg mask z,xmmrm128,imm8	AVX512VL/BW
VPSHUFHW	ymmreg mask z,ymmrm256,imm8	AVX512VL/BW
VPSHUFHW	zmmreg mask z,zmmrm512,imm8	AVX512BW
VPSHUFLW	xmmreg mask z,xmmrm128,imm8	AVX512VL/BW
VPSHUFLW	ymmreg mask z,ymmrm256,imm8	AVX512VL/BW
VPSHUFLW	zmmreg mask z,zmmrm512,imm8	AVX512BW
VPSLLD	xmmreg mask z,xmmreg*,xmmrm128	AVX512VL
VPSLLD	ymmreg mask z,ymmreg*,ymmrm256	AVX512VL
VPSLLD	zmmreg mask z,zmmreg*,zmmrm512	AVX512
VPSLLD	xmmreg mask z,xmmrm128 b32*,imm8	AVX512VL
VPSLLD	ymmreg mask z,ymmrm256 b32*,imm8	AVX512VL
VPSLLD	zmmreg mask z,zmmrm512 b32*,imm8	AVX512
VPSLLDQ	xmmreg,xmmrm128*,imm8	AVX512VL/BW
VPSLLDQ	ymmreg,ymmrm256*,imm8	AVX512VL/BW
VPSLLDQ	zmmreg,zmmrm512*,imm8	AVX512BW
VPSLLQ	xmmreg mask z,xmmreg*,xmmrm128	AVX512VL
VPSLLQ	ymmreg mask z,ymmreg*,ymmrm256	AVX512VL
VPSLLQ	zmmreg mask z,zmmreg*,zmmrm512	AVX512
VPSLLQ	xmmreg mask z,xmmrm128 b64*,imm8	AVX512VL
VPSLLQ	ymmreg mask z,ymmrm256 b64*,imm8	AVX512VL
VPSLLQ	zmmreg mask z,zmmrm512 b64*,imm8	AVX512
VPSLLVD	xmmreg mask z,xmmreg*,xmmrm128 b32	AVX512VL
VPSLLVD	ymmreg mask z,ymmreg*,ymmrm256 b32	AVX512VL
VPSLLVD	zmmreg mask z,zmmreg*,zmmrm512 b32	AVX512
VPSLLVQ	xmmreg mask z,xmmreg*,xmmrm128 b64	AVX512VL
VPSLLVQ	ymmreg mask z,ymmreg*,ymmrm256 b64	AVX512VL
VPSLLVQ	zmmreg mask z,zmmreg*,zmmrm512 b64	AVX512
VPSLLVW	xmmreg mask z,xmmreg*,xmmrm128	AVX512VL/BW
VPSLLVW	ymmreg mask z,ymmreg*,ymmrm256	AVX512VL/BW
VPSLLVW	zmmreg mask z,zmmreg*,zmmrm512	AVX512BW
VPSLLW	xmmreg mask z,xmmreg*,xmmrm128	AVX512VL/BW
VPSLLW	ymmreg mask z,ymmreg*,ymmrm256	AVX512VL/BW
VPSLLW	zmmreg mask z,zmmreg*,zmmrm512	AVX512BW
VPSLLW	xmmreg mask z,xmmrm128*,imm8	AVX512VL/BW
VPSLLW	ymmreg mask z,ymmrm256*,imm8	AVX512VL/BW
VPSLLW	zmmreg mask z,zmmrm512*,imm8	AVX512BW
VPSRAD	xmmreg mask z,xmmreg*,xmmrm128	AVX512VL
VPSRAD	ymmreg mask z,ymmreg*,ymmrm256	AVX512VL
VPSRAD	zmmreg mask z,zmmreg*,zmmrm512	AVX512
VPSRAD	xmmreg mask z,xmmrm128 b32*,imm8	AVX512VL
VPSRAD	ymmreg mask z,ymmrm256 b32*,imm8	AVX512VL
VPSRAD	zmmreg mask z,zmmrm512 b32*,imm8	AVX512
VPSRAQ	xmmreg mask z,xmmreg*,xmmrm128	AVX512VL
VPSRAQ	ymmreg mask z,ymmreg*,ymmrm256	AVX512VL
VPSRAQ	zmmreg mask z,zmmreg*,zmmrm512	AVX512
VPSRAQ	xmmreg mask z,xmmrm128 b64*,imm8	AVX512VL
VPSRAQ	ymmreg mask z,ymmrm256 b64*,imm8	AVX512VL
VPSRAQ	zmmreg mask z,zmmrm512 b64*,imm8	AVX512
VPSRAVD	xmmreg mask z,xmmreg*,xmmrm128 b32	AVX512VL

VPSRAVD	ymmreg	mask	z, ymmreg*, ymmrm256	b32	AVX512VL
VPSRAVD	zmmreg	mask	z, zmmreg*, zmmrm512	b32	AVX512
VPSRAVQ	xmmreg	mask	z, xmmreg*, xmmrm128	b64	AVX512VL
VPSRAVQ	ymmreg	mask	z, ymmreg*, ymmrm256	b64	AVX512VL
VPSRAVQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64	AVX512
VPSRAVW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW	
VPSRAVW	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW	
VPSRAVW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW	
VPSRAW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW	
VPSRAW	ymmreg	mask	z, ymmreg*, xmmrm128	AVX512VL/BW	
VPSRAW	zmmreg	mask	z, zmmreg*, xmmrm128	AVX512BW	
VPSRAW	xmmreg	mask	z, xmmrm128*, imm8	AVX512VL/BW	
VPSRAW	ymmreg	mask	z, ymmrm256*, imm8	AVX512VL/BW	
VPSRAW	zmmreg	mask	z, zmmrm512*, imm8	AVX512BW	
VPSRLD	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL	
VPSRLD	ymmreg	mask	z, ymmreg*, xmmrm128	AVX512VL	
VPSRLD	zmmreg	mask	z, zmmreg*, xmmrm128	AVX512	
VPSRLD	xmmreg	mask	z, xmmrm128	b32*, imm8	AVX512VL
VPSRLD	ymmreg	mask	z, ymmrm256	b32*, imm8	AVX512VL
VPSRLD	zmmreg	mask	z, zmmrm512	b32*, imm8	AVX512
VPSRLDQ	xmmreg, xmmrm128*	imm8		AVX512VL/BW	
VPSRLDQ	ymmreg, ymmrm256*	imm8		AVX512VL/BW	
VPSRLDQ	zmmreg, zmmrm512*	imm8		AVX512BW	
VPSRLQ	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL	
VPSRLQ	ymmreg	mask	z, ymmreg*, xmmrm128	AVX512VL	
VPSRLQ	zmmreg	mask	z, zmmreg*, xmmrm128	AVX512	
VPSRLQ	xmmreg	mask	z, xmmrm128	b64*, imm8	AVX512VL
VPSRLQ	ymmreg	mask	z, ymmrm256	b64*, imm8	AVX512VL
VPSRLQ	zmmreg	mask	z, zmmrm512	b64*, imm8	AVX512
VPSRLVD	xmmreg	mask	z, xmmreg*, xmmrm128	b32	AVX512VL
VPSRLVD	ymmreg	mask	z, ymmreg*, ymmrm256	b32	AVX512VL
VPSRLVD	zmmreg	mask	z, zmmreg*, zmmrm512	b32	AVX512
VPSRLVQ	xmmreg	mask	z, xmmreg*, xmmrm128	b64	AVX512VL
VPSRLVQ	ymmreg	mask	z, ymmreg*, ymmrm256	b64	AVX512VL
VPSRLVQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64	AVX512
VPSRLVW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW	
VPSRLVW	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW	
VPSRLVW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW	
VPSRLW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW	
VPSRLW	ymmreg	mask	z, ymmreg*, xmmrm128	AVX512VL/BW	
VPSRLW	zmmreg	mask	z, zmmreg*, xmmrm128	AVX512BW	
VPSRLW	xmmreg	mask	z, xmmrm128*, imm8	AVX512VL/BW	
VPSRLW	ymmreg	mask	z, ymmrm256*, imm8	AVX512VL/BW	
VPSRLW	zmmreg	mask	z, zmmrm512*, imm8	AVX512BW	
VPSUBB	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW	
VPSUBB	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW	
VPSUBB	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW	
VPSUBD	xmmreg	mask	z, xmmreg*, xmmrm128	b32	AVX512VL
VPSUBD	ymmreg	mask	z, ymmreg*, ymmrm256	b32	AVX512VL
VPSUBD	zmmreg	mask	z, zmmreg*, zmmrm512	b32	AVX512
VPSUBQ	xmmreg	mask	z, xmmreg*, xmmrm128	b64	AVX512VL
VPSUBQ	ymmreg	mask	z, ymmreg*, ymmrm256	b64	AVX512VL
VPSUBQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64	AVX512
VPSUBSB	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW	

VPSUBSB	ymmreg	mask	z, ymmreg*	ymmrm256	AVX512VL/BW
VPSUBSB	zmmreg	mask	z, zmmreg*	zmmrm512	AVX512BW
VPSUBSW	xmmreg	mask	z, xmmreg*	xmmrm128	AVX512VL/BW
VPSUBSW	ymmreg	mask	z, ymmreg*	ymmrm256	AVX512VL/BW
VPSUBSW	zmmreg	mask	z, zmmreg*	zmmrm512	AVX512BW
VPSUBUSB	xmmreg	mask	z, xmmreg*	xmmrm128	AVX512VL/BW
VPSUBUSB	ymmreg	mask	z, ymmreg*	ymmrm256	AVX512VL/BW
VPSUBUSB	zmmreg	mask	z, zmmreg*	zmmrm512	AVX512BW
VPSUBUSW	xmmreg	mask	z, xmmreg*	xmmrm128	AVX512VL/BW
VPSUBUSW	ymmreg	mask	z, ymmreg*	ymmrm256	AVX512VL/BW
VPSUBUSW	zmmreg	mask	z, zmmreg*	zmmrm512	AVX512BW
VPSUBW	xmmreg	mask	z, xmmreg*	xmmrm128	AVX512VL/BW
VPSUBW	ymmreg	mask	z, ymmreg*	ymmrm256	AVX512VL/BW
VPSUBW	zmmreg	mask	z, zmmreg*	zmmrm512	AVX512BW
VPTERNLOGD	xmmreg	mask	z, xmmreg, xmmrm128	b32, imm8	AVX512VL
VPTERNLOGD	ymmreg	mask	z, ymmreg, ymmrm256	b32, imm8	AVX512VL
VPTERNLOGD	zmmreg	mask	z, zmmreg, zmmrm512	b32, imm8	AVX512
VPTERNLOGQ	xmmreg	mask	z, xmmreg, xmmrm128	b64, imm8	AVX512VL
VPTERNLOGQ	ymmreg	mask	z, ymmreg, ymmrm256	b64, imm8	AVX512VL
VPTERNLOGQ	zmmreg	mask	z, zmmreg, zmmrm512	b64, imm8	AVX512
VPTESTMB	kreg	mask, xmmreg, xmmrm128			AVX512VL/BW
VPTESTMB	kreg	mask, ymmreg, ymmrm256			AVX512VL/BW
VPTESTMB	kreg	mask, zmmreg, zmmrm512			AVX512BW
VPTESTMD	kreg	mask, xmmreg, xmmrm128	b32		AVX512VL
VPTESTMD	kreg	mask, ymmreg, ymmrm256	b32		AVX512VL
VPTESTMD	kreg	mask, zmmreg, zmmrm512	b32		AVX512
VPTESTMQ	kreg	mask, xmmreg, xmmrm128	b64		AVX512VL
VPTESTMQ	kreg	mask, ymmreg, ymmrm256	b64		AVX512VL
VPTESTMQ	kreg	mask, zmmreg, zmmrm512	b64		AVX512
VPTESTMW	kreg	mask, xmmreg, xmmrm128			AVX512VL/BW
VPTESTMW	kreg	mask, ymmreg, ymmrm256			AVX512VL/BW
VPTESTMW	kreg	mask, zmmreg, zmmrm512			AVX512BW
VPTESTNMB	kreg	mask, xmmreg, xmmrm128			AVX512VL/BW
VPTESTNMB	kreg	mask, ymmreg, ymmrm256			AVX512VL/BW
VPTESTNMB	kreg	mask, zmmreg, zmmrm512			AVX512BW
VPTESTNMD	kreg	mask, xmmreg, xmmrm128	b32		AVX512VL
VPTESTNMD	kreg	mask, ymmreg, ymmrm256	b32		AVX512VL
VPTESTNMD	kreg	mask, zmmreg, zmmrm512	b32		AVX512
VPTESTNMQ	kreg	mask, xmmreg, xmmrm128	b64		AVX512VL
VPTESTNMQ	kreg	mask, ymmreg, ymmrm256	b64		AVX512VL
VPTESTNMQ	kreg	mask, zmmreg, zmmrm512	b64		AVX512
VPTESTNMW	kreg	mask, xmmreg, xmmrm128			AVX512VL/BW
VPTESTNMW	kreg	mask, ymmreg, ymmrm256			AVX512VL/BW
VPTESTNMW	kreg	mask, zmmreg, zmmrm512			AVX512BW
VPUNPCKHBW	xmmreg	mask	z, xmmreg*	xmmrm128	AVX512VL/BW
VPUNPCKHBW	ymmreg	mask	z, ymmreg*	ymmrm256	AVX512VL/BW
VPUNPCKHBW	zmmreg	mask	z, zmmreg*	zmmrm512	AVX512BW
VPUNPCKHDQ	xmmreg	mask	z, xmmreg*	xmmrm128	b32 AVX512VL
VPUNPCKHDQ	ymmreg	mask	z, ymmreg*	ymmrm256	b32 AVX512VL
VPUNPCKHDQ	zmmreg	mask	z, zmmreg*	zmmrm512	b32 AVX512
VPUNPCKHQDQ	xmmreg	mask	z, xmmreg*	xmmrm128	b64 AVX512VL
VPUNPCKHQDQ	ymmreg	mask	z, ymmreg*	ymmrm256	b64 AVX512VL
VPUNPCKHQDQ	zmmreg	mask	z, zmmreg*	zmmrm512	b64 AVX512
VPUNPCKHWD	xmmreg	mask	z, xmmreg*	xmmrm128	AVX512VL/BW

VPUNPCKHWD	ymmreg	mask	z, ymmreg*	ymmrm256	AVX512VL/BW
VPUNPCKHWD	zmmreg	mask	z, zmmreg*	zmmrm512	AVX512BW
VPUNPCKLBW	xmmreg	mask	z, xmmreg*	xmmrm128	AVX512VL/BW
VPUNPCKLBW	ymmreg	mask	z, ymmreg*	ymmrm256	AVX512VL/BW
VPUNPCKLBW	zmmreg	mask	z, zmmreg*	zmmrm512	AVX512BW
VPUNPCKLDQ	xmmreg	mask	z, xmmreg*	xmmrm128	b32 AVX512VL
VPUNPCKLDQ	ymmreg	mask	z, ymmreg*	ymmrm256	b32 AVX512VL
VPUNPCKLDQ	zmmreg	mask	z, zmmreg*	zmmrm512	b32 AVX512
VPUNPCKLQDQ	xmmreg	mask	z, xmmreg*	xmmrm128	b64 AVX512VL
VPUNPCKLQDQ	ymmreg	mask	z, ymmreg*	ymmrm256	b64 AVX512VL
VPUNPCKLQDQ	zmmreg	mask	z, zmmreg*	zmmrm512	b64 AVX512
VPUNPCKLWD	xmmreg	mask	z, xmmreg*	xmmrm128	AVX512VL/BW
VPUNPCKLWD	ymmreg	mask	z, ymmreg*	ymmrm256	AVX512VL/BW
VPUNPCKLWD	zmmreg	mask	z, zmmreg*	zmmrm512	AVX512BW
VPXORD	xmmreg	mask	z, xmmreg*	xmmrm128	b32 AVX512VL
VPXORD	ymmreg	mask	z, ymmreg*	ymmrm256	b32 AVX512VL
VPXORD	zmmreg	mask	z, zmmreg*	zmmrm512	b32 AVX512
VPXORQ	xmmreg	mask	z, xmmreg*	xmmrm128	b64 AVX512VL
VPXORQ	ymmreg	mask	z, ymmreg*	ymmrm256	b64 AVX512VL
VPXORQ	zmmreg	mask	z, zmmreg*	zmmrm512	b64 AVX512
VRANGEPD	xmmreg	mask	z, xmmreg*	xmmrm128	b64, imm8 AVX512VL/DQ
VRANGEPD	ymmreg	mask	z, ymmreg*	ymmrm256	b64, imm8 AVX512VL/DQ
VRANGEPD	zmmreg	mask	z, zmmreg*	zmmrm512	b64 sae, imm8 AVX512DQ
VRANGEPS	xmmreg	mask	z, xmmreg*	xmmrm128	b32, imm8 AVX512VL/DQ
VRANGEPS	ymmreg	mask	z, ymmreg*	ymmrm256	b32, imm8 AVX512VL/DQ
VRANGEPS	zmmreg	mask	z, zmmreg*	zmmrm512	b32 sae, imm8 AVX512DQ
VRANGESD	xmmreg	mask	z, xmmreg*	xmmrm64	sae, imm8 AVX512DQ
VRANGESS	xmmreg	mask	z, xmmreg*	xmmrm32	sae, imm8 AVX512DQ
VRCP14PD	xmmreg	mask	z, xmmrm128	b64	AVX512VL
VRCP14PD	ymmreg	mask	z, ymmrm256	b64	AVX512VL
VRCP14PD	zmmreg	mask	z, zmmrm512	b64	AVX512
VRCP14PS	xmmreg	mask	z, xmmrm128	b32	AVX512VL
VRCP14PS	ymmreg	mask	z, ymmrm256	b32	AVX512VL
VRCP14PS	zmmreg	mask	z, zmmrm512	b32	AVX512
VRCP14SD	xmmreg	mask	z, xmmreg*	xmmrm64	AVX512
VRCP14SS	xmmreg	mask	z, xmmreg*	xmmrm32	AVX512
VRCP28PD	zmmreg	mask	z, zmmrm512	b64 sae	AVX512ER
VRCP28PS	zmmreg	mask	z, zmmrm512	b32 sae	AVX512ER
VRCP28SD	xmmreg	mask	z, xmmreg*	xmmrm64	sae AVX512ER
VRCP28SS	xmmreg	mask	z, xmmreg*	xmmrm32	sae AVX512ER
VREDUCEPD	xmmreg	mask	z, xmmrm128	b64, imm8	AVX512VL/DQ
VREDUCEPD	ymmreg	mask	z, ymmrm256	b64, imm8	AVX512VL/DQ
VREDUCEPD	zmmreg	mask	z, zmmrm512	b64 sae, imm8	AVX512DQ
VREDUCEPS	xmmreg	mask	z, xmmrm128	b32, imm8	AVX512VL/DQ
VREDUCEPS	ymmreg	mask	z, ymmrm256	b32, imm8	AVX512VL/DQ
VREDUCEPS	zmmreg	mask	z, zmmrm512	b32 sae, imm8	AVX512DQ
VREDUCESD	xmmreg	mask	z, xmmreg*	xmmrm64	sae, imm8 AVX512DQ
VREDUCESD	xmmreg	mask	z, xmmreg*	xmmrm32	sae, imm8 AVX512DQ
VRNDSCALEPD	xmmreg	mask	z, xmmrm128	b64, imm8	AVX512VL
VRNDSCALEPD	ymmreg	mask	z, ymmrm256	b64, imm8	AVX512VL
VRNDSCALEPD	zmmreg	mask	z, zmmrm512	b64 sae, imm8	AVX512
VRNDSCALEPS	xmmreg	mask	z, xmmrm128	b32, imm8	AVX512VL
VRNDSCALEPS	ymmreg	mask	z, ymmrm256	b32, imm8	AVX512VL
VRNDSCALEPS	zmmreg	mask	z, zmmrm512	b32 sae, imm8	AVX512

VRNDSCALESD	xmmreg	mask	z,xmmreg*,xmrm64	sae,imm8	AVX512
VRNDSCALESS	xmmreg	mask	z,xmmreg*,xmrm32	sae,imm8	AVX512
VRSQRT14PD	xmmreg	mask	z,xmrm128	b64	AVX512VL
VRSQRT14PD	ymmreg	mask	z,ymrm256	b64	AVX512VL
VRSQRT14PD	zmmreg	mask	z,zmrm512	b64	AVX512
VRSQRT14PS	xmmreg	mask	z,xmrm128	b32	AVX512VL
VRSQRT14PS	ymmreg	mask	z,ymrm256	b32	AVX512VL
VRSQRT14PS	zmmreg	mask	z,zmrm512	b32	AVX512
VRSQRT14SD	xmmreg	mask	z,xmmreg*,xmrm64		AVX512
VRSQRT14SS	xmmreg	mask	z,xmmreg*,xmrm32		AVX512
VRSQRT28PD	zmmreg	mask	z,zmrm512	b64	sae AVX512ER
VRSQRT28PS	zmmreg	mask	z,zmrm512	b32	sae AVX512ER
VRSQRT28SD	xmmreg	mask	z,xmmreg*,xmrm64	sae	AVX512ER
VRSQRT28SS	xmmreg	mask	z,xmmreg*,xmrm32	sae	AVX512ER
VSCALEFPD	xmmreg	mask	z,xmmreg*,xmrm128	b64	AVX512VL
VSCALEFPD	ymmreg	mask	z,ymmreg*,ymrm256	b64	AVX512VL
VSCALEFPD	zmmreg	mask	z,zmmreg*,zmrm512	b64	er AVX512
VSCALEFPS	xmmreg	mask	z,xmmreg*,xmrm128	b32	AVX512VL
VSCALEFPS	ymmreg	mask	z,ymmreg*,ymrm256	b32	AVX512VL
VSCALEFPS	zmmreg	mask	z,zmmreg*,zmrm512	b32	er AVX512
VSCALEFSD	xmmreg	mask	z,xmmreg*,xmrm64	er	AVX512
VSCALEFSS	xmmreg	mask	z,xmmreg*,xmrm32	er	AVX512
VSCATTERDPD	xmem64	mask,xmmreg			AVX512VL
VSCATTERDPD	xmem64	mask,ymmreg			AVX512VL
VSCATTERDPD	ymem64	mask,zmmreg			AVX512
VSCATTERDPS	xmem32	mask,xmmreg			AVX512VL
VSCATTERDPS	ymem32	mask,ymmreg			AVX512VL
VSCATTERDPS	zmem32	mask,zmmreg			AVX512
VSCATTERPF0DPD	ymem64	mask			AVX512PF
VSCATTERPF0DPS	zmem32	mask			AVX512PF
VSCATTERPF0QPD	zmem64	mask			AVX512PF
VSCATTERPF0QPS	zmem32	mask			AVX512PF
VSCATTERPF1DPD	ymem64	mask			AVX512PF
VSCATTERPF1DPS	zmem32	mask			AVX512PF
VSCATTERPF1QPD	zmem64	mask			AVX512PF
VSCATTERPF1QPS	zmem32	mask			AVX512PF
VSCATTERQPD	xmem64	mask,xmmreg			AVX512VL
VSCATTERQPD	ymem64	mask,ymmreg			AVX512VL
VSCATTERQPD	zmem64	mask,zmmreg			AVX512
VSCATTERQPS	xmem32	mask,xmmreg			AVX512VL
VSCATTERQPS	ymem32	mask,xmmreg			AVX512VL
VSCATTERQPS	zmem32	mask,ymmreg			AVX512
VSHUFF32X4	ymmreg	mask	z,ymmreg*,ymrm256	b32,imm8	AVX512VL
VSHUFF32X4	zmmreg	mask	z,zmmreg*,zmrm512	b32,imm8	AVX512
VSHUFF64X2	ymmreg	mask	z,ymmreg*,ymrm256	b64,imm8	AVX512VL
VSHUFF64X2	zmmreg	mask	z,zmmreg*,zmrm512	b64,imm8	AVX512
VSHUFI32X4	ymmreg	mask	z,ymmreg*,ymrm256	b32,imm8	AVX512VL
VSHUFI32X4	zmmreg	mask	z,zmmreg*,zmrm512	b32,imm8	AVX512
VSHUFI64X2	ymmreg	mask	z,ymmreg*,ymrm256	b64,imm8	AVX512VL
VSHUFI64X2	zmmreg	mask	z,zmmreg*,zmrm512	b64,imm8	AVX512
VSHUFPD	xmmreg	mask	z,xmmreg*,xmrm128	b64,imm8	AVX512VL
VSHUFPD	ymmreg	mask	z,ymmreg*,ymrm256	b64,imm8	AVX512VL
VSHUFPD	zmmreg	mask	z,zmmreg*,zmrm512	b64,imm8	AVX512
VSHUFPS	xmmreg	mask	z,xmmreg*,xmrm128	b32,imm8	AVX512VL

VSHUFPS	ymmreg	mask	z, ymmreg*	ymmrm256	b32, imm8	AVX512VL
VSHUFPS	zmmreg	mask	z, zmmreg*	zmmrm512	b32, imm8	AVX512
VSQRTPD	xmmreg	mask	z, xmmrm128	b64		AVX512VL
VSQRTPD	ymmreg	mask	z, ymmrm256	b64		AVX512VL
VSQRTPD	zmmreg	mask	z, zmmrm512	b64	er	AVX512
VSQRTPS	xmmreg	mask	z, xmmrm128	b32		AVX512VL
VSQRTPS	ymmreg	mask	z, ymmrm256	b32		AVX512VL
VSQRTPS	zmmreg	mask	z, zmmrm512	b32	er	AVX512
VSQRTSD	xmmreg	mask	z, xmmreg*	xmmrm64	er	AVX512
VSQRTSS	xmmreg	mask	z, xmmreg*	xmmrm32	er	AVX512
VSUBPD	xmmreg	mask	z, xmmreg*	xmmrm128	b64	AVX512VL
VSUBPD	ymmreg	mask	z, ymmreg*	ymmrm256	b64	AVX512VL
VSUBPD	zmmreg	mask	z, zmmreg*	zmmrm512	b64	er AVX512
VSUBPS	xmmreg	mask	z, xmmreg*	xmmrm128	b32	AVX512VL
VSUBPS	ymmreg	mask	z, ymmreg*	ymmrm256	b32	AVX512VL
VSUBPS	zmmreg	mask	z, zmmreg*	zmmrm512	b32	er AVX512
VSUBSD	xmmreg	mask	z, xmmreg*	xmmrm64	er	AVX512
VSUBSS	xmmreg	mask	z, xmmreg*	xmmrm32	er	AVX512
VUCOMISD	xmmreg, xmmrm64		sae			AVX512
VUCOMISS	xmmreg, xmmrm32		sae			AVX512
VUNPCKHPD	xmmreg	mask	z, xmmreg*	xmmrm128	b64	AVX512VL
VUNPCKHPD	ymmreg	mask	z, ymmreg*	ymmrm256	b64	AVX512VL
VUNPCKHPD	zmmreg	mask	z, zmmreg*	zmmrm512	b64	AVX512
VUNPCKHPS	xmmreg	mask	z, xmmreg*	xmmrm128	b32	AVX512VL
VUNPCKHPS	ymmreg	mask	z, ymmreg*	ymmrm256	b32	AVX512VL
VUNPCKHPS	zmmreg	mask	z, zmmreg*	zmmrm512	b32	AVX512
VUNPCKLPD	xmmreg	mask	z, xmmreg*	xmmrm128	b64	AVX512VL
VUNPCKLPD	ymmreg	mask	z, ymmreg*	ymmrm256	b64	AVX512VL
VUNPCKLPD	zmmreg	mask	z, zmmreg*	zmmrm512	b64	AVX512
VUNPCKLPS	xmmreg	mask	z, xmmreg*	xmmrm128	b32	AVX512VL
VUNPCKLPS	ymmreg	mask	z, ymmreg*	ymmrm256	b32	AVX512VL
VUNPCKLPS	zmmreg	mask	z, zmmreg*	zmmrm512	b32	AVX512
VXORPD	xmmreg	mask	z, xmmreg*	xmmrm128	b64	AVX512VL/DQ
VXORPD	ymmreg	mask	z, ymmreg*	ymmrm256	b64	AVX512VL/DQ
VXORPD	zmmreg	mask	z, zmmreg*	zmmrm512	b64	AVX512DQ
VXORPS	xmmreg	mask	z, xmmreg*	xmmrm128	b32	AVX512VL/DQ
VXORPS	ymmreg	mask	z, ymmreg*	ymmrm256	b32	AVX512VL/DQ
VXORPS	zmmreg	mask	z, zmmreg*	zmmrm512	b32	AVX512DQ

B.1.42 Intel memory protection keys for userspace (PKU aka PKEYs)

RDPKRU		X64
WRPKRU		X64

B.1.43 Read Processor ID

RDPID	reg32	NOLONG
RDPID	reg64	X64
RDPID	reg32	X64, UNDOC

B.1.44 New memory instructions

CLFLUSHOPT	mem	
CLWB	mem	
PCOMMIT		NEVER, NOP
CLZERO		AMD

CLZERO	reg_ax	AMD,ND,NOLONG
CLZERO	reg_eax	AMD,ND
CLZERO	reg_rax	AMD,ND,X64

B.1.45 Processor trace write

PTWRITE	rm32	
PTWRITE	rm64	X64

B.1.46 Instructions from the Intel Instruction Set Extensions,

B.1.47 doc 319433–034 May 2018

CLDEMOT	mem	
MOVDIRI	mem32,reg32	SD
MOVDIRI	mem64,reg64	X64
MOVDIR64B	reg16,mem512	NOLONG
MOVDIR64B	reg32,mem512	
MOVDIR64B	reg64,mem512	X64
PCONFIG		
TPAUSE	reg32	
TPAUSE	reg32,reg_edx,reg_eax	ND
UMONITOR	reg16	NOLONG
UMONITOR	reg32	
UMONITOR	reg64	X64
UMWAIT	reg32	
UMWAIT	reg32,reg_edx,reg_eax	ND
WBNOINVD		

B.1.48 Galois field operations (GFNI)

GF2P8AFFINEINVQB	xmmreg,xmmrm128,imm8	GFNI,SSE
VGF2P8AFFINEINVQB	xmmreg,xmmreg*,xmmrm128,imm8	GFNI,AVX
VGF2P8AFFINEINVQB	ymmreg,yymmreg*,ymmrm256,imm8	GFNI,AVX
VGF2P8AFFINEINVQB	xmmreg mask z,xmmreg*,xmmrm128 b64,imm8	AVX512VL,GFNI
VGF2P8AFFINEINVQB	ymmreg mask z,yymmreg*,ymmrm256 b64,imm8	AVX512VL,GFNI
VGF2P8AFFINEINVQB	zmmreg mask z,zmmreg*,zmmrm512 b64,imm8	AVX512,GFNI
GF2P8AFFINEQB	xmmreg,xmmrm128,imm8	GFNI,SSE
VGF2P8AFFINEQB	xmmreg,xmmreg*,xmmrm128,imm8	GFNI,AVX
VGF2P8AFFINEQB	ymmreg,yymmreg*,ymmrm256,imm8	GFNI,AVX
VGF2P8AFFINEQB	xmmreg mask z,xmmreg*,xmmrm128 b64,imm8	AVX512VL,GFNI
VGF2P8AFFINEQB	ymmreg mask z,yymmreg*,ymmrm256 b64,imm8	AVX512VL,GFNI
VGF2P8AFFINEQB	zmmreg mask z,zmmreg*,zmmrm512 b64,imm8	AVX512,GFNI
GF2P8MULB	xmmreg,xmmrm128	GFNI,SSE
VGF2P8MULB	xmmreg,xmmreg*,xmmrm128	GFNI,AVX
VGF2P8MULB	ymmreg,yymmreg*,ymmrm256	GFNI,AVX
VGF2P8MULB	xmmreg mask z,xmmreg*,xmmrm128	AVX512VL,GFNI
VGF2P8MULB	ymmreg mask z,yymmreg*,ymmrm256	AVX512VL,GFNI
VGF2P8MULB	zmmreg mask z,zmmreg*,zmmrm512	AVX512,GFNI

B.1.49 AVX512 Vector Bit Manipulation Instructions 2

VPCOMPRESSB	mem128 mask,xmmreg	AVX512VBMI2/VL
VPCOMPRESSB	mem256 mask,yymmreg	AVX512VBMI2/VL
VPCOMPRESSB	mem512 mask,zmmreg	AVX512VBMI2
VPCOMPRESSB	xmmreg mask z,xmmreg	AVX512VBMI2/VL
VPCOMPRESSB	yymmreg mask z,yymmreg	AVX512VBMI2/VL

VPCOMPRESSB	zmmreg	mask	z, zmmreg	AVX512VBMI2
VPCOMPRESSW	mem128	mask	xmmreg	AVX512VBMI2/VL
VPCOMPRESSW	mem256	mask	yymmreg	AVX512VBMI2/VL
VPCOMPRESSW	mem512	mask	zmmreg	AVX512VBMI2
VPCOMPRESSW	xmmreg	mask	z, xmmreg	AVX512VBMI2/VL
VPCOMPRESSW	yymmreg	mask	z, yymmreg	AVX512VBMI2/VL
VPCOMPRESSW	zmmreg	mask	z, zmmreg	AVX512VBMI2
VPEXPANDB	mem128	mask	xmmreg	AVX512VBMI2/VL
VPEXPANDB	mem256	mask	yymmreg	AVX512VBMI2/VL
VPEXPANDB	mem512	mask	zmmreg	AVX512VBMI2
VPEXPANDB	xmmreg	mask	z, xmmreg	AVX512VBMI2/VL
VPEXPANDB	yymmreg	mask	z, yymmreg	AVX512VBMI2/VL
VPEXPANDB	zmmreg	mask	z, zmmreg	AVX512VBMI2
VPEXPANDW	mem128	mask	xmmreg	AVX512VBMI2/VL
VPEXPANDW	mem256	mask	yymmreg	AVX512VBMI2/VL
VPEXPANDW	mem512	mask	zmmreg	AVX512VBMI2
VPEXPANDW	xmmreg	mask	z, xmmreg	AVX512VBMI2/VL
VPEXPANDW	yymmreg	mask	z, yymmreg	AVX512VBMI2/VL
VPEXPANDW	zmmreg	mask	z, zmmreg	AVX512VBMI2
VPSHLDW	xmmreg	mask	z, xmmreg*, xmrm128, imm8	AVX512VBMI2/VL
VPSHLDW	yymmreg	mask	z, yymmreg*, yymmrm256, imm8	AVX512VBMI2/VL
VPSHLDW	zmmreg	mask	z, zmmreg*, zmmrm512, imm8	AVX512VBMI2
VPSHLDD	xmmreg	mask	z, xmmreg*, xmrm128	b32, imm8 AVX512VBMI2/VL
VPSHLDD	yymmreg	mask	z, yymmreg*, yymmrm256	b32, imm8 AVX512VBMI2/VL
VPSHLDD	zmmreg	mask	z, zmmreg*, zmmrm512	b32, imm8 AVX512VBMI2
VPSHLDQ	xmmreg	mask	z, xmmreg*, xmrm128	b64, imm8 AVX512VBMI2/VL
VPSHLDQ	yymmreg	mask	z, yymmreg*, yymmrm256	b64, imm8 AVX512VBMI2/VL
VPSHLDQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64, imm8 AVX512VBMI2
VPSHLDVW	xmmreg	mask	z, xmmreg*, xmrm128	AVX512VBMI2/VL
VPSHLDVW	yymmreg	mask	z, yymmreg*, yymmrm256	AVX512VBMI2/VL
VPSHLDVW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512VBMI2
VPSHLDVD	xmmreg	mask	z, xmmreg*, xmrm128	b32 AVX512VBMI2/VL
VPSHLDVD	yymmreg	mask	z, yymmreg*, yymmrm256	b32 AVX512VBMI2/VL
VPSHLDVD	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512VBMI2
VPSHLDVQ	xmmreg	mask	z, xmmreg*, xmrm128	b64 AVX512VBMI2/VL
VPSHLDVQ	yymmreg	mask	z, yymmreg*, yymmrm256	b64 AVX512VBMI2/VL
VPSHLDVQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64 AVX512VBMI2
VPSHRDW	xmmreg	mask	z, xmmreg*, xmrm128, imm8	AVX512VBMI2/VL
VPSHRDW	yymmreg	mask	z, yymmreg*, yymmrm256, imm8	AVX512VBMI2/VL
VPSHRDW	zmmreg	mask	z, zmmreg*, zmmrm512, imm8	AVX512VBMI2
VPSHRDD	xmmreg	mask	z, xmmreg*, xmrm128	b32, imm8 AVX512VBMI2/VL
VPSHRDD	yymmreg	mask	z, yymmreg*, yymmrm256	b32, imm8 AVX512VBMI2/VL
VPSHRDD	zmmreg	mask	z, zmmreg*, zmmrm512	b32, imm8 AVX512VBMI2
VPSHRDQ	xmmreg	mask	z, xmmreg*, xmrm128	b64, imm8 AVX512VBMI2/VL
VPSHRDQ	yymmreg	mask	z, yymmreg*, yymmrm256	b64, imm8 AVX512VBMI2/VL
VPSHRDQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64, imm8 AVX512VBMI2
VPSHRDVW	xmmreg	mask	z, xmmreg*, xmrm128	AVX512VBMI2/VL
VPSHRDVW	yymmreg	mask	z, yymmreg*, yymmrm256	AVX512VBMI2/VL
VPSHRDVW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512VBMI2
VPSHRDVD	xmmreg	mask	z, xmmreg*, xmrm128	b32 AVX512VBMI2/VL
VPSHRDVD	yymmreg	mask	z, yymmreg*, yymmrm256	b32 AVX512VBMI2/VL
VPSHRDVD	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512VBMI2
VPSHRDVQ	xmmreg	mask	z, xmmreg*, xmrm128	b64 AVX512VBMI2/VL

VPSHRDVQ	ymmreg mask z,yymmreg*,ymmrm256 b64	AVX512VBMI2/VL
VPSHRDVQ	zmmreg mask z,zmmreg*,zmmrm512 b64	AVX512VBMI2

B.1.50 AVX512 VNNI

VPDPBUSD	xmmreg mask z,xmmreg*,xmrm128 b32	AVX512VNNI/VL
VPDPBUSD	ymmreg mask z,yymmreg*,ymmrm256 b32	AVX512VNNI/VL
VPDPBUSD	zmmreg mask z,zmmreg*,zmmrm512 b32	AVX512VNNI
VPDPBUSDS	xmmreg mask z,xmmreg*,xmrm128 b32	AVX512VNNI/VL
VPDPBUSDS	ymmreg mask z,yymmreg*,ymmrm256 b32	AVX512VNNI/VL
VPDPBUSDS	zmmreg mask z,zmmreg*,zmmrm512 b32	AVX512VNNI
VPDPWSSD	xmmreg mask z,xmmreg*,xmrm128 b32	AVX512VNNI/VL
VPDPWSSD	ymmreg mask z,yymmreg*,ymmrm256 b32	AVX512VNNI/VL
VPDPWSSD	zmmreg mask z,zmmreg*,zmmrm512 b32	AVX512VNNI
VPDPWSSDS	xmmreg mask z,xmmreg*,xmrm128 b32	AVX512VNNI/VL
VPDPWSSDS	ymmreg mask z,yymmreg*,ymmrm256 b32	AVX512VNNI/VL
VPDPWSSDS	zmmreg mask z,zmmreg*,zmmrm512 b32	AVX512VNNI

B.1.51 AVX512 Bit Algorithms

VPOPCNTB	xmmreg mask z,xmrm128	AVX512BITALG/VL
VPOPCNTB	ymmreg mask z,ymmrm256	AVX512BITALG/VL
VPOPCNTB	zmmreg mask z,zmmrm512	AVX512BITALG
VPOPCNTW	xmmreg mask z,xmrm128	AVX512BITALG/VL
VPOPCNTW	ymmreg mask z,ymmrm256	AVX512BITALG/VL
VPOPCNTW	zmmreg mask z,zmmrm512	AVX512BITALG
VPOPCNTD	xmmreg mask z,xmrm128	AVX512VPOPCNTDQ/VL
VPOPCNTD	ymmreg mask z,ymmrm256	AVX512VPOPCNTDQ/VL
VPOPCNTD	zmmreg mask z,zmmrm512	AVX512VPOPCNTDQ
VPOPCNTQ	xmmreg mask z,xmrm128	AVX512VPOPCNTDQ/VL
VPOPCNTQ	ymmreg mask z,ymmrm256	AVX512VPOPCNTDQ/VL
VPOPCNTQ	zmmreg mask z,zmmrm512	AVX512VPOPCNTDQ
VPSHUFBITQMB	kreg mask,xmmreg,xmrm128	AVX512BITALG/VL
VPSHUFBITQMB	kreg mask,yymmreg,ymmrm256	AVX512BITALG/VL
VPSHUFBITQMB	kreg mask,zmmreg,zmmrm512	AVX512BITALG

B.1.52 AVX512 4-iteration Multiply-Add

V4FMADDPS	zmmreg mask z,zmmreg rs4,mem	AVX512FMAPS,S0
V4FMADDPS	zmmreg mask z,zmmreg rs4,mem	AVX512FMAPS,S0
V4FMADDSS	zmmreg mask z,zmmreg rs4,mem	AVX512FMAPS,S0
V4FMADDSS	zmmreg mask z,zmmreg rs4,mem	AVX512FMAPS,S0

B.1.53 AVX512 4-iteration Dot Product

V4DPWSSDS	zmmreg mask z,zmmreg rs4,mem	AVX512VNNIW,S0
V4DPWSSD	zmmreg mask z,zmmreg rs4,mem	AVX512VNNIW,S0

B.1.54 Intel Software Guard Extensions (SGX)

ENCLS	SGX
ENCLU	SGX
ENCLV	SGX

B.1.55 Systematic names for the hinting nop instructions

HINT_NOP0	rm16	P6,UNDOC
HINT_NOP0	rm32	P6,UNDOC

HINT_NOP0	rm64	X64,UNDOC
HINT_NOP1	rm16	P6,UNDOC
HINT_NOP1	rm32	P6,UNDOC
HINT_NOP1	rm64	X64,UNDOC
HINT_NOP2	rm16	P6,UNDOC
HINT_NOP2	rm32	P6,UNDOC
HINT_NOP2	rm64	X64,UNDOC
HINT_NOP3	rm16	P6,UNDOC
HINT_NOP3	rm32	P6,UNDOC
HINT_NOP3	rm64	X64,UNDOC
HINT_NOP4	rm16	P6,UNDOC
HINT_NOP4	rm32	P6,UNDOC
HINT_NOP4	rm64	X64,UNDOC
HINT_NOP5	rm16	P6,UNDOC
HINT_NOP5	rm32	P6,UNDOC
HINT_NOP5	rm64	X64,UNDOC
HINT_NOP6	rm16	P6,UNDOC
HINT_NOP6	rm32	P6,UNDOC
HINT_NOP6	rm64	X64,UNDOC
HINT_NOP7	rm16	P6,UNDOC
HINT_NOP7	rm32	P6,UNDOC
HINT_NOP7	rm64	X64,UNDOC
HINT_NOP8	rm16	P6,UNDOC
HINT_NOP8	rm32	P6,UNDOC
HINT_NOP8	rm64	X64,UNDOC
HINT_NOP9	rm16	P6,UNDOC
HINT_NOP9	rm32	P6,UNDOC
HINT_NOP9	rm64	X64,UNDOC
HINT_NOP10	rm16	P6,UNDOC
HINT_NOP10	rm32	P6,UNDOC
HINT_NOP10	rm64	X64,UNDOC
HINT_NOP11	rm16	P6,UNDOC
HINT_NOP11	rm32	P6,UNDOC
HINT_NOP11	rm64	X64,UNDOC
HINT_NOP12	rm16	P6,UNDOC
HINT_NOP12	rm32	P6,UNDOC
HINT_NOP12	rm64	X64,UNDOC
HINT_NOP13	rm16	P6,UNDOC
HINT_NOP13	rm32	P6,UNDOC
HINT_NOP13	rm64	X64,UNDOC
HINT_NOP14	rm16	P6,UNDOC
HINT_NOP14	rm32	P6,UNDOC
HINT_NOP14	rm64	X64,UNDOC
HINT_NOP15	rm16	P6,UNDOC
HINT_NOP15	rm32	P6,UNDOC
HINT_NOP15	rm64	X64,UNDOC
HINT_NOP16	rm16	P6,UNDOC
HINT_NOP16	rm32	P6,UNDOC
HINT_NOP16	rm64	X64,UNDOC
HINT_NOP17	rm16	P6,UNDOC
HINT_NOP17	rm32	P6,UNDOC
HINT_NOP17	rm64	X64,UNDOC
HINT_NOP18	rm16	P6,UNDOC
HINT_NOP18	rm32	P6,UNDOC

HINT_NOP18	rm64	X64,UNDOC
HINT_NOP19	rm16	P6,UNDOC
HINT_NOP19	rm32	P6,UNDOC
HINT_NOP19	rm64	X64,UNDOC
HINT_NOP20	rm16	P6,UNDOC
HINT_NOP20	rm32	P6,UNDOC
HINT_NOP20	rm64	X64,UNDOC
HINT_NOP21	rm16	P6,UNDOC
HINT_NOP21	rm32	P6,UNDOC
HINT_NOP21	rm64	X64,UNDOC
HINT_NOP22	rm16	P6,UNDOC
HINT_NOP22	rm32	P6,UNDOC
HINT_NOP22	rm64	X64,UNDOC
HINT_NOP23	rm16	P6,UNDOC
HINT_NOP23	rm32	P6,UNDOC
HINT_NOP23	rm64	X64,UNDOC
HINT_NOP24	rm16	P6,UNDOC
HINT_NOP24	rm32	P6,UNDOC
HINT_NOP24	rm64	X64,UNDOC
HINT_NOP25	rm16	P6,UNDOC
HINT_NOP25	rm32	P6,UNDOC
HINT_NOP25	rm64	X64,UNDOC
HINT_NOP26	rm16	P6,UNDOC
HINT_NOP26	rm32	P6,UNDOC
HINT_NOP26	rm64	X64,UNDOC
HINT_NOP27	rm16	P6,UNDOC
HINT_NOP27	rm32	P6,UNDOC
HINT_NOP27	rm64	X64,UNDOC
HINT_NOP28	rm16	P6,UNDOC
HINT_NOP28	rm32	P6,UNDOC
HINT_NOP28	rm64	X64,UNDOC
HINT_NOP29	rm16	P6,UNDOC
HINT_NOP29	rm32	P6,UNDOC
HINT_NOP29	rm64	X64,UNDOC
HINT_NOP30	rm16	P6,UNDOC
HINT_NOP30	rm32	P6,UNDOC
HINT_NOP30	rm64	X64,UNDOC
HINT_NOP31	rm16	P6,UNDOC
HINT_NOP31	rm32	P6,UNDOC
HINT_NOP31	rm64	X64,UNDOC
HINT_NOP32	rm16	P6,UNDOC
HINT_NOP32	rm32	P6,UNDOC
HINT_NOP32	rm64	X64,UNDOC
HINT_NOP33	rm16	P6,UNDOC
HINT_NOP33	rm32	P6,UNDOC
HINT_NOP33	rm64	X64,UNDOC
HINT_NOP34	rm16	P6,UNDOC
HINT_NOP34	rm32	P6,UNDOC
HINT_NOP34	rm64	X64,UNDOC
HINT_NOP35	rm16	P6,UNDOC
HINT_NOP35	rm32	P6,UNDOC
HINT_NOP35	rm64	X64,UNDOC
HINT_NOP36	rm16	P6,UNDOC
HINT_NOP36	rm32	P6,UNDOC

HINT_NOP36	rm64	X64,UNDOC
HINT_NOP37	rm16	P6,UNDOC
HINT_NOP37	rm32	P6,UNDOC
HINT_NOP37	rm64	X64,UNDOC
HINT_NOP38	rm16	P6,UNDOC
HINT_NOP38	rm32	P6,UNDOC
HINT_NOP38	rm64	X64,UNDOC
HINT_NOP39	rm16	P6,UNDOC
HINT_NOP39	rm32	P6,UNDOC
HINT_NOP39	rm64	X64,UNDOC
HINT_NOP40	rm16	P6,UNDOC
HINT_NOP40	rm32	P6,UNDOC
HINT_NOP40	rm64	X64,UNDOC
HINT_NOP41	rm16	P6,UNDOC
HINT_NOP41	rm32	P6,UNDOC
HINT_NOP41	rm64	X64,UNDOC
HINT_NOP42	rm16	P6,UNDOC
HINT_NOP42	rm32	P6,UNDOC
HINT_NOP42	rm64	X64,UNDOC
HINT_NOP43	rm16	P6,UNDOC
HINT_NOP43	rm32	P6,UNDOC
HINT_NOP43	rm64	X64,UNDOC
HINT_NOP44	rm16	P6,UNDOC
HINT_NOP44	rm32	P6,UNDOC
HINT_NOP44	rm64	X64,UNDOC
HINT_NOP45	rm16	P6,UNDOC
HINT_NOP45	rm32	P6,UNDOC
HINT_NOP45	rm64	X64,UNDOC
HINT_NOP46	rm16	P6,UNDOC
HINT_NOP46	rm32	P6,UNDOC
HINT_NOP46	rm64	X64,UNDOC
HINT_NOP47	rm16	P6,UNDOC
HINT_NOP47	rm32	P6,UNDOC
HINT_NOP47	rm64	X64,UNDOC
HINT_NOP48	rm16	P6,UNDOC
HINT_NOP48	rm32	P6,UNDOC
HINT_NOP48	rm64	X64,UNDOC
HINT_NOP49	rm16	P6,UNDOC
HINT_NOP49	rm32	P6,UNDOC
HINT_NOP49	rm64	X64,UNDOC
HINT_NOP50	rm16	P6,UNDOC
HINT_NOP50	rm32	P6,UNDOC
HINT_NOP50	rm64	X64,UNDOC
HINT_NOP51	rm16	P6,UNDOC
HINT_NOP51	rm32	P6,UNDOC
HINT_NOP51	rm64	X64,UNDOC
HINT_NOP52	rm16	P6,UNDOC
HINT_NOP52	rm32	P6,UNDOC
HINT_NOP52	rm64	X64,UNDOC
HINT_NOP53	rm16	P6,UNDOC
HINT_NOP53	rm32	P6,UNDOC
HINT_NOP53	rm64	X64,UNDOC
HINT_NOP54	rm16	P6,UNDOC
HINT_NOP54	rm32	P6,UNDOC

HINT_NOP54	rm64	X64,UNDOC
HINT_NOP55	rm16	P6,UNDOC
HINT_NOP55	rm32	P6,UNDOC
HINT_NOP55	rm64	X64,UNDOC
HINT_NOP56	rm16	P6,UNDOC
HINT_NOP56	rm32	P6,UNDOC
HINT_NOP56	rm64	X64,UNDOC
HINT_NOP57	rm16	P6,UNDOC
HINT_NOP57	rm32	P6,UNDOC
HINT_NOP57	rm64	X64,UNDOC
HINT_NOP58	rm16	P6,UNDOC
HINT_NOP58	rm32	P6,UNDOC
HINT_NOP58	rm64	X64,UNDOC
HINT_NOP59	rm16	P6,UNDOC
HINT_NOP59	rm32	P6,UNDOC
HINT_NOP59	rm64	X64,UNDOC
HINT_NOP60	rm16	P6,UNDOC
HINT_NOP60	rm32	P6,UNDOC
HINT_NOP60	rm64	X64,UNDOC
HINT_NOP61	rm16	P6,UNDOC
HINT_NOP61	rm32	P6,UNDOC
HINT_NOP61	rm64	X64,UNDOC
HINT_NOP62	rm16	P6,UNDOC
HINT_NOP62	rm32	P6,UNDOC
HINT_NOP62	rm64	X64,UNDOC
HINT_NOP63	rm16	P6,UNDOC
HINT_NOP63	rm32	P6,UNDOC
HINT_NOP63	rm64	X64,UNDOC

Appendix C: NASM Version History

C.1 NASM 2 Series

The NASM 2 series supports x86-64, and is the production version of NASM since 2007.

C.1.1 Version 2.15

- Warn for strange legacy behavior regarding empty arguments in multi-line macro expansion, but try to match legacy behavior in most cases. Legacy behavior can be disabled with the directive `%pragma preproc sane_empty_expansion`, see section 4.3 and section 4.10.1.
- A much more sensible limit to expression evaluation depth. The previously defined limit would rarely trigger before NASM died with a stack overrun error on most systems. See section 2.1.31.
- The state of warnings can now be saved and restored via the `[WARNING PUSH]` and `[WARNING POP]` directives. See section 7.13.
- The `sectalign on|off` switch does not affect an explicit directive. See section 5.10.2.
- Added `configure` option to enable building with profiling (`--enable-profiling`).
- Attempt to support of long path names, up to 32767 of UTF-16 characters, on Windows.
- Fixed 'mismatch in operand sizes' error in the `MOVDDUP`, `CMPXCHG8B` and `CMPXCHG16B` instructions.
- Improved error messages in the string transformation routine.
- Removed obsolete `gnu-elf-extensions` warning about 8- and 16-bit relocation generation. See section 8.9.8
- Added group aliases for all prefixed warnings. See section 2.1.26.
- Allowed building with MSVC versions older than 1700.
- Added implicitly sized versions of the `K...` instructions, which allows the `K...` instructions to be specified without a size suffix as long as the operands are sized.
- Added `-L` option for additional listing information. See section 2.1.4.
- Added some warnings for obsolete instructions for a specified CPU.
- Deprecated `-hf` and `-y` options. Use `-h` instead.
- Made DWARF as the default debug format for ELF.
- Added `%pragma list options...` to set or clear listing options (see `opt-L`).
- Allowed immediate syntax for `LEA` instruction (ignore operand size completely).
- Added limited functionality MASM compatibility package. See section 6.5.
- Add single-line macros aliases using `%defalias` or `%idefalias`. These behave like a kind of "symbolic links" for single-line macros. See section 4.1.10 and `clear`.
- Added support for `stringify`, `nostrip`, evaluating, and greedy single-line macro arguments. See section 4.1.1.
- Unused single-line macro arguments no longer need to have a specified name. See section 4.1.1.
- Added conditional comma operator `%, .`. See section 4.1.11.

- Changed private namespace from `__foo__` to `__?foo?__`, so a user namespace starting from underscore is now clean from symbols. For backwards compatibility, the previous names are defined as aliases; see section 4.1.10, section 4.11.3 and chapter 5.
- Added support of ELF weak symbols and external references. See section 8.9.5.
- Changed the behavior of the EXTERN keyword and introduced REQUIRED keyword. See section 7.6.
- Added `%ifusable` and `%ifusing` directives. See chapter 6.
- Made various performance improvements and stability fixes in macro preprocessor engine.
- Improved NASM error handling and cleaned up error messages.
- Many, many bug fixes.

C.1.2 Version 2.14.03

- Suppress nuisance "label changed during code generation" messages after a real error.
- Add support for the merge and strings attributes on ELF sections. See section 8.9.2.
- Add support for the note, preinit_array, init_array, and fini_array sections type in ELF. See section 8.9.2.
- Handle more than 32,633 sections in ELF.

C.1.3 Version 2.14.02

- Fix crash due to multiple errors or warnings during the code generation pass if a list file is specified.

C.1.4 Version 2.14.01

- Create all system-defined macros before processing command-line given preprocessing directives (`-p`, `-d`, `-u`, `--pragma`, `--before`).
- If debugging is enabled, define a `__DEBUG_FORMAT__` predefined macro. See section 5.5.
- Fix an assert for the case in the obj format when a SEG operator refers to an EXTERN symbol declared further down in the code.
- Fix a corner case in the floating-point code where a binary, octal or hexadecimal floating-point having at least 32, 11, or 8 mantissa digits could produce slightly incorrect results under very specific conditions.
- Support `-MD` without a filename, for gcc compatibility. `-MF` can be used to set the dependencies output filename. See section 2.1.8.
- Fix `-E` in combination with `-MD`. See section 2.1.22.
- Fix missing errors on redefined labels; would cause convergence failure instead which is very slow and not easy to debug.
- Duplicate definitions of the same label *with the same value* is now explicitly permitted (2.14 would allow it in some circumstances.)
- Add the option `--no-line` to ignore `%line` directives in the source. See section 2.1.33 and section 4.11.1.

C.1.5 Version 2.14

- Changed `-I` option semantics by adding a trailing path separator unconditionally.
- Fixed null dereference in corrupted invalid single line macros.
- Fixed division by zero which may happen if source code is malformed.

- Fixed out of bound access in processing of malformed segment override.
- Fixed out of bound access in certain EQU parsing.
- Fixed buffer underflow in float parsing.
- Added SGX (Intel Software Guard Extensions) instructions.
- Added +n syntax for multiple contiguous registers.
- Fixed subsections_via_symbols for macho object format.
- Added the --gprefix, --gpostfix, --lprefix, and --lpostfix command line options, to allow command line base symbol renaming. See section 2.1.28.
- Allow label renaming to be specified by %pragma in addition to from the command line. See section 7.10.
- Supported generic %pragma namespaces, output and debug. See section 4.10.
- Added the --pragma command line option to inject a %pragma directive. See section 2.1.29.
- Added the --before command line option to accept preprocess statement before input. See section 2.1.30.
- Added AVX512 VBMI2 (Additional Bit Manipulation), VNNI (Vector Neural Network), BITALG (Bit Algorithm), and GFNI (Galois Field New Instruction) instructions.
- Added the STATIC directive for local symbols that should be renamed using global-symbol rules. See section 7.9.
- Allow a symbol to be defined as EXTERN and then later overridden as GLOBAL or COMMON. Furthermore, a symbol declared EXTERN and then defined will be treated as GLOBAL. See section 7.5.
- The GLOBAL directive no longer is required to precede the definition of the symbol.
- Support private_extern as macho specific extension to the GLOBAL directive. See section 8.8.5.
- Updated UD0 encoding to match with the specification
- Added the --limit-X command line option to set execution limits. See section 2.1.31.
- Updated the Codeview version number to be aligned with MASM.
- Added the --keep-all command line option to preserve output files. See section 2.1.32.
- Added the --include command line option, an alias to -P (section 2.1.19).
- Added the --help command line option as an alias to -h (section 3.1).
- Added -W, -D, and -Q suffix aliases for RET instructions so the operand sizes of these instructions can be encoded without using o16, o32 or o64.

C.1.6 Version 2.13.03

- Added AVX and AVX512 VAES* and VPCLMULQDQ instructions.
- Fixed missing dwarf record in x32 ELF output format.

C.1.7 Version 2.13.02

- Fix false positive in testing of numeric overflows.
- Fix generation of PEXTRW instruction.
- Fix smartalign package which could trigger an error during optimization if the alignment code expanded too much due to optimization of the previous code.

- Fix a case where negative value in TIMES directive causes panic instead of an error.
- Always finalize `.debug_abbrev` section with a null in dwarf output format.
- Support debug flag in section attributes for macho output format. See section 8.8.1.
- Support up to 16 characters in section names for macho output format.
- Fix missing update of global BITS setting if SECTION directive specified a bit size using output format-specific extensions (e.g. USE32 for the obj output format.)
- Fix the incorrect generation of VEX-encoded instruction when static mode decorators are specified on scalar instructions, losing the decorators as they require EVEX encoding.
- Option `-MW` to quote dependency outputs according to Watcom Make conventions instead of POSIX Make conventions. See section 2.1.12.
- The obj output format now contains embedded dependency file information, unless disabled with `%pragma obj nodepend`. See section 8.4.9.
- Fix generation of dependency lists.
- Fix a number of null pointer reference and memory allocation errors.
- Always generate symbol-relative relocations for the macho64 output format; at least some versions of the XCode/LLVM linker fails for section-relative relocations.

C.1.8 Version 2.13.01

- Fix incorrect output for some types of FAR or SEG references in the obj output format, and possibly other 16-bit output formats.
- Fix the address in the list file for an instruction containing a TIMES directive.
- Fix error with TIMES used together with an instruction which can vary in size, e.g. JMP.
- Fix breakage on some uses of the DZ pseudo-op.

C.1.9 Version 2.13

- Support the official forms of the UD0 and UD1 instructions.
- Allow self-segment-relative expressions in immediates and displacements, even when combined with an external or otherwise out-of-segment special symbol, e.g.:


```
extern foo
mov eax,[foo - $ + ebx]           ; Now legal
```
- Handle a 64-bit origin in NDISASM.
- NASM can now generate sparse output files for relevant output formats, if the underlying operating system supports them.
- The macho object format now supports the `subsections_via_symbols` and `no_dead_strip` directives, see section 8.8.4.
- The macho object format now supports the `no_dead_strip`, `live_support` and `strip_static_syms` section flags, see section 8.8.1.
- The macho object format now supports the dwarf debugging format, as required by newer toolchains.
- All warnings can now be suppressed if desired; warnings not otherwise part of any warning class are now considered its own warning class called `other` (e.g. `-w-other`). Furthermore, `warning-as-error` can now be controlled on a per warning class basis, using the syntax `-w+error=warning-class` and its equivalent for all other warning control options. See section

2.1.26 for the command-line options and warning classes and section 7.13 for the [WARNING] directive.

- Fix a number of bugs related to AVX-512 decorators.
- Significant improvements to building NASM with Microsoft Visual Studio via `Mkfiles/msvc.mak`. It is now possible to build the full Windows installer binary as long as the necessary prerequisites are installed; see `Mkfiles/README`
- To build NASM with custom modifications (table changes) or from the git tree now requires Perl 5.8 at the very minimum, quite possibly a higher version (Perl 5.24.1 tested.) There is no requirement to have Perl on your system at all if all you want to do is build unmodified NASM from source archives.
- Fix the {z} decorator on AVX-512 `VMOVDQ*` instructions.
- Add new warnings for certain dangerous constructs which never ought to have been allowed. In particular, the RESB family of instructions should have been taking a critical expression all along.
- Fix the EVEX (AVX-512) versions of the `VPBROADCAST`, `VPEXTR`, and `VPINSR` instructions.
- Support contracted forms of additional instructions. As a general rule, if an instruction has a non-destructive source immediately after a destination register that isn't used as an input, NASM supports omitting that source register, using the destination register as that value. This among other things makes it easier to convert SSE code to the equivalent AVX code:

```
addps xmm1,xmm0                ; SSE instruction
vaddps ymm1,ymm1,ymm0          ; AVX official long form
vaddps ymm1,ymm0              ; AVX contracted form
```

- Fix Codeview malformed compiler version record.
- Add the `CLWB` and `PCOMMIT` instructions. Note that the `PCOMMIT` instruction has been deprecated and will never be included in a shipping product; it is included for completeness only.
- Add the `%pragma` preprocessor directive for soft-error directives.
- Add the `RDPID` instruction.

C.1.10 Version 2.12.02

- Fix preprocessor errors, especially `%error` and `%warning`, inside `%if` statements.
- Fix relative relocations in 32-bit Mach-O.
- More Codeview debug format fixes.
- If the `MASM PTR` keyword is encountered, issue a warning. This is much more likely to indicate a `MASM-ism` encountered in NASM than it is a valid label. This warning can be suppressed with `-w-ptr`, the `[warning]` directive (see section 2.1.26) or by the macro definition `%idefine ptr $%?` (see section 4.1.5).
- When an error or a warning comes from the expansion of a multi-line macro, display the file and line numbers for the expanded macros. Macros defined with `.no list` do not get displayed.
- Add macros `ilog2fw()` and `ilog2cw()` to the `ifunc` macro package. See section 6.4.1.

C.1.11 Version 2.12.01

- Portability fixes for some platforms.
- Fix error when not specifying a list file.
- Correct the handling of macro-local labels in the Codeview debugging format.
- Add `CLZERO`, `MONITORX` and `MWAITX` instructions.

C.1.12 Version 2.12

- Major fixes to the macho backend (section 8.8); earlier versions would produce invalid symbols and relocations on a regular basis.
- Support for thread-local storage in Mach-O.
- Support for arbitrary sections in Mach-O.
- Fix wrong negative size treated as a big positive value passed into backend causing NASM to crash.
- Fix handling of zero-extending unsigned relocations, we have been printing wrong message and forgot to assign segment with predefined value before passing it into output format.
- Fix potential write of oversized (with size greater than allowed in output format) relative relocations.
- Portability fixes for building NASM with the LLVM compiler.
- Add support of Codeview version 8 (cv8) debug format for win32 and win64 formats in the COFF backend, see section 8.5.3.
- Allow 64-bit outputs in 16/32-bit only backends. Unsigned 64-bit relocations are zero-extended from 32-bits with a warning (suppressible via `-w-zext-reloc`); signed 64-bit relocations are an error.
- Line numbers in list files now correspond to the lines in the source files, instead of simply being sequential.
- There is now an official 64-bit (x64 a.k.a. x86-64) build for Windows.

C.1.13 Version 2.11.09

- Fix potential stack overwrite in macho32 backend.
- Fix relocation records in macho64 backend.
- Fix symbol lookup computation in macho64 backend.
- Adjust `.symtab` and `.rela.text` sections alignments to 8 bytes in elf64 backed.
- Fix section length computation in bin backend which leded in incorrect relocation records.

C.1.14 Version 2.11.08

- Fix section length computation in bin backend which leded in incorrect relocation records.
- Add a warning for numeric preprocessor definitions passed via command line which might have unexpected results otherwise.
- Add ability to specify a module name record in rdo ff linker with `-mn` option.
- Increase label length capacity up to 256 bytes in rdo ff backend for FreePascal sake, which tends to generate very long labels for procedures.
- Fix segmentation failure when rip addressing is used in macho64 backend.
- Fix access on out of memory when handling strings with a single grave. We have sixed similar problem in previous release but not all cases were covered.
- Fix NULL dereference in disassembled on BND instruction.

C.1.15 Version 2.11.07

- Fix 256 bit VMOVNTPS instruction.
- Fix `-MD` option handling, which was rather broken in previous release changing command line api.

- Fix access to uninitialized space when handling strings with a single grave.
- Fix nil dereference in handling memory reference parsing.

C.1.16 Version 2.11.06

- Update AVX512 instructions based on the Extension Reference (319433–021 Sept 2014).
- Fix the behavior of `-MF` and `-MD` options (Bugzilla 3392280)
- Updated Win32 Makefile to fix issue with build

C.1.17 Version 2.11.05

- Add `--v` as an alias for `-v` (see section 2.1.27), for command-line compatibility with Yasm.
- Fix a bug introduced in 2.11.03 whereby certain instructions would contain multiple REX prefixes, and thus be corrupt.

C.1.18 Version 2.11.04

- Removed an invalid error checking code. Sometimes a memref only with a displacement can also set an evex flag. For example:

```
vmovdqu32 [0xabcd]{k1}, zmm0
```

- Fixed a bug in disassembler that EVEX.L'L vector length was not matched when EVEX.b was set because it was simply considered as EVEC.RC. Separated EVEX.L'L case from EVEX.RC which is ignored in matching.

C.1.19 Version 2.11.03

- Fix a bug there REX prefixes were missing on instructions inside a TIMES statement.

C.1.20 Version 2.11.02

- Add the XSAVEC, XSAVES and XRSTORS family instructions.
- Add the CLFLUSHOPT instruction.

C.1.21 Version 2.11.01

- Allow instructions which implicitly uses XMM0 (VBLENDVPD, VBLENDVPS, PBLENDVB and SHA256RND52) to be specified without an explicit xmm0 on the assembly line. In other words, the following two lines produce the same output:

```
vblendvpd xmm2,xmm1,xmm0      ; Last operand is fixed xmm0
vblendvpd xmm2,xmm1           ; Implicit xmm0 omitted
```

- In the ELF backends, don't crash the assembler if `section align` is specified without a value.

C.1.22 Version 2.11

- Add support for the Intel AVX-512 instruction set:
- 16 new, 512-bit SIMD registers. Total 32 (ZMM0 ~ ZMM31)
- 8 new opmask registers (K0 ~ K7). One of 7 registers (K1 ~ K7) can be used as an opmask for conditional execution.
- A new EVEX encoding prefix. EVEX is based on VEX and provides more capabilities: opmasks, broadcasting, embedded rounding and compressed displacements.

- opmask

```
VDIVPD zmm0{k1}{z}, zmm1, zmm3 ; conditional vector operation
                                ; using opmask k1.
```

- broadcasting


```

          VDIVPS zmm4, zmm5, [rbx]{1to16} ; {z} is for zero-masking
          ; load single-precision float and
          ; replicate it 16 times. 32 * 16 = 512
      
```
- embedded rounding


```

          VCVTSD2SI xmm6, xmm7, {rz-sae}, rax ; round toward zero. note that it
          ; is used as if a separate operand.
          ; it comes after the last SIMD operand
      
```

- Add support for ZWORD (512 bits), DZ and RESZ.
- Add support for the MPX and SHA instruction sets.
- Better handling of section redefinition.
- Generate manpages when running 'make dist'.
- Handle all token chains in mmacro params range.
- Support split [base,index] effective address:

```

    mov eax,[eax+8,ecx*4] ; eax=base, ecx=index, 4=scale, 8=disp
  
```

This is expected to be most useful for the MPX instructions.

- Support BND prefix for branch instructions (for MPX).
- The DEFAULT directive can now take BND and NOBND options to indicate whether all relevant branches should be getting BND prefixes. This is expected to be the normal for use in MPX code.
- Add {evex}, {vex3} and {vex2} instruction prefixes to have NASM encode the corresponding instruction, if possible, with an EVEX, 3-byte VEX, or 2-byte VEX prefix, respectively.
- Support for section names longer than 8 bytes in Win32/Win64 COFF.
- The NOSPLIT directive by itself no longer forces a single register to become an index register, unless it has an explicit multiplier.

```

    mov eax,[nosplit eax] ; eax as base register
    mov eax,[nosplit eax*1] ; eax as index register
  
```

C.1.23 Version 2.10.09

- Pregenerate man pages.

C.1.24 Version 2.10.08

- Fix VMOVNTDQA, MOVNTDQA and MOVLDP instructions.
- Fix collision for VGATHERQPS, VPGATHERQD instructions.
- Fix VPMOVSXBQ, VGATHERQPD, VSPLW instructions.
- Add a bunch of AMD TBM instructions.
- Fix potential stack overwrite in numbers conversion.
- Allow byte size in PREFETCHT_x instructions.
- Make manual pages up to date.
- Make F3 and F2 SSE prefixes to override 66.
- Support of AMD SVM instructions in 32 bit mode.
- Fix near offsets code generation for JMP, CALL instructions in long mode.

- Fix preprocessor parse regression when `id` is expanding to a whitespace.

C.1.25 Version 2.10.07

- Fix line continuation parsing being broken in previous version.

C.1.26 Version 2.10.06

- Always quote the dependency source names when using the automatic dependency generation options.
- If no dependency target name is specified via the `-MT` or `-MQ` options, quote the default output name.
- Fix assembly of shift operations in CPU 8086 mode.
- Fix incorrect generation of explicit immediate byte for shift by 1 under certain circumstances.
- Fix assembly of the `VPCMPGTQ` instruction.
- Fix RIP-relative relocations in the `macho64` backend.

C.1.27 Version 2.10.05

- Add the `CLAC` and `STAC` instructions.

C.1.28 Version 2.10.04

- Add back the inadvertently deleted 256-bit version of the `VORPD` instruction.
- Correct disassembly of instructions starting with byte 82 hex.
- Fix corner cases in token pasting, for example:

```
%define N 1e%++%+ 5
        dd N, 1e+5
```

C.1.29 Version 2.10.03

- Correct the assembly of the instruction:

```
XRELEASE MOV [absolute],AL
```

Previous versions would incorrectly generate `F3 A2` for this instruction and issue a warning; correct behavior is to emit `F3 88 05`.

C.1.30 Version 2.10.02

- Add the `i func` macro package with integer functions, currently only integer logarithms. See section 6.4.
- Add the `RDSEED`, `ADCX` and `ADOX` instructions.

C.1.31 Version 2.10.01

- Add missing `VPMOVMskb` instruction with `reg32`, `ymmreg` operands.

C.1.32 Version 2.10

- When optimization is enabled, `mov r64, imm` now optimizes to the shortest form possible between:

```
mov r32,imm32          ; 5 bytes
mov r64,imm32         ; 7 bytes
mov r64,imm64         ; 10 bytes
```

To force a specific form, use the `STRICT` keyword, see section 3.7.

- Add support for the Intel AVX2 instruction set.
- Add support for Bit Manipulation Instructions 1 and 2.
- Add support for Intel Transactional Synchronization Extensions (TSX).
- Add support for x32 ELF (32-bit ELF with the CPU in 64-bit mode.) See section 8.9.
- Add support for bigendian UTF-16 and UTF-32. See section 3.4.5.

C.1.33 Version 2.09.10

- Fix up NSIS script to protect uninstaller against registry keys absence or corruption. It brings in a few additional questions to a user during deinstallation procedure but still it is better than unpredictable file removal.

C.1.34 Version 2.09.09

- Fix initialization of section attributes of `bin` output format.
- Fix `mach64` output format bug that crashes NASM due to NULL symbols.

C.1.35 Version 2.09.08

- Fix `__OUTPUT_FORMAT__` assignment when output driver alias is used. For example when `-f elf` is used `__OUTPUT_FORMAT__` must be set to `elf`, if `-f elf32` is used `__OUTPUT_FORMAT__` must be assigned accordingly, i.e. to `elf32`. The rule applies to all output driver aliases. See section 5.4.

C.1.36 Version 2.09.07

- Fix attempts to close same file several times when `-a` option is used.
- Fixes for `VEXTRACTF128`, `VMASKMOVPS` encoding.

C.1.37 Version 2.09.06

- Fix missed section attribute initialization in `bin` output target.

C.1.38 Version 2.09.05

- Fix arguments encoding for `VPEXTRW` instruction.
- Remove invalid form of `VPEXTRW` instruction.
- Add `VLDDQU` as alias for `VLDQQU` to match specification.

C.1.39 Version 2.09.04

- Fix incorrect labels offset for VEX instructions.
- Eliminate bogus warning on implicit operand size override.
- `%if` term could not handle 64 bit numbers.
- The COFF backend was limiting relocations number to 16 bits even if in real there were a way more relocations.

C.1.40 Version 2.09.03

- Print `%macro` name inside `%rep` blocks on error.
- Fix preprocessor expansion behaviour. It happened sometime too early and sometime simply wrong. Move behaviour back to the origins (down to NASM 2.05.01).
- Fix uninitialized data dereference on OMF output format.

- Issue warning on unterminated `{` construct.
- Fix for documentation typo.

C.1.41 Version 2.09.02

- Fix reversed tokens when `%def tok` produces more than one output token.
- Fix segmentation fault on disassembling some VEX instructions.
- Missing `%endif` did not always cause error.
- Fix typo in documentation.
- Compound context local preprocessor single line macro identifiers were not expanded early enough and as result lead to unresolved symbols.

C.1.42 Version 2.09.01

- Fix NULL dereference on missed `%deftok` second parameter.
- Fix NULL dereference on invalid `%substr` parameters.

C.1.43 Version 2.09

- Fixed assignment the magnitude of `%rep` counter. It is limited to 62 bits now.
- Fixed NULL dereference if argument of `%strlen` resolves to whitespace. For example if nonexistent macro parameter is used.
- `%ifenv`, `%elifenv`, `%ifnenv`, and `%elifnenv` directives introduced. See section 4.4.9.
- Fixed NULL dereference if environment variable is missed.
- Updates of new AVX v7 Intel instructions.
- `PUSH imm32` is now officially documented.
- Fix for encoding the LFS, LGS and LSS in 64-bit mode.
- Fixes for compatibility with OpenWatcom compiler and DOS 8.3 file format limitation.
- Macros parameters range expansion introduced. See section 4.3.4.
- Backward compatibility on expanding of local sigle macros restored.
- 8 bit relocations for `elf` and `bin` output formats are introduced.
- Short intersegment jumps are permitted now.
- An alignment more than 64 bytes are allowed for `win32`, `win64` output formats.
- `SECTALIGN` directive introduced. See section 5.10.2.
- `nojmp` option introduced in `smartalign` package. See section 6.2.
- Short aliases `win`, `elf` and `macho` for output formats are introduced. Each stands for `win32`, `elf32` and `macho32` accordingly.
- Faster handling of missing directives implemented.
- Various small improvements in documentation.
- No hang anymore if unable to open `malloc.log` file.
- The environments without `vsnprintf` function are able to build `nasm` again.
- AMD LWP instructions updated.

- Tighten EA checks. We warn a user if there overflow in EA addressing.
- Make `-Ox` the default optimization level. For the legacy behavior, specify `-O0` explicitly. See section 2.1.24.
- Environment variables read with `%!` or tested with `%ifenv` can now contain non-identifier characters if surrounded by quotes. See section 4.11.2.
- Add a new standard macro package `%use fp` for floating-point convenience macros. See section 6.3.

C.1.44 Version 2.08.02

- Fix crash under certain circumstances when using the `%+` operator.

C.1.45 Version 2.08.01

- Fix the `%use` statement, which was broken in 2.08.

C.1.46 Version 2.08

- A number of enhancements/fixes in macros area.
- Support for converting strings to tokens. See section 4.1.9.
- Fuzzy operand size logic introduced.
- Fix COFF stack overrun on too long export identifiers.
- Fix Macho-O alignment bug.
- Fix crashes with `-fwin32` on file with many exports.
- Fix stack overrun for too long `[DEBUG id]`.
- Fix incorrect `sbyte` usage in `IMUL` (hit only if optimization flag passed).
- Append ending token for `.stabs` records in the ELF output format.
- New NSIS script which uses ModernUI and MultiUser approach.
- Visual Studio 2008 NASM integration (rules file).
- Warn a user if a constant is too long (and as result will be stripped).
- The obsoleted pre-XOP AMD SSE5 instruction set which was never actualized was removed.
- Fix stack overrun on too long error file name passed from the command line.
- Bind symbols to the `.text` section by default (ie in case if `SECTION` directive was omitted) in the ELF output format.
- Fix sync points array index wrapping.
- A few fixes for FMA4 and XOP instruction templates.
- Add AMD Lightweight Profiling (LWP) instructions.
- Fix the offset for `%arg` in 64-bit mode.
- An undefined local macro (`%$`) no longer matches a global macro with the same name.
- Fix NULL dereference on too long local labels.

C.1.47 Version 2.07

- NASM is now under the 2-clause BSD license. See section 1.1.1.
- Fix the section type for the `.strtab` section in the `elf64` output format.

- Fix the handling of COMMON directives in the obj output format.
- New `it` and `srec` output formats; these are variants of the `bin` output format which output Intel hex and Motorola S-records, respectively. See section 8.2 and section 8.3.
- `rdf2ihx` replaced with an enhanced `rdf2bin`, which can output binary, COM, Intel hex or Motorola S-records.
- The Windows installer now puts the NASM directory first in the PATH of the "NASM Shell".
- Revert the early expansion behavior of `%+` to pre-2.06 behavior: `%+` is only expanded late.
- Yet another Mach-O alignment fix.
- Don't delete the list file on errors. Also, include error and warning information in the list file.
- Support for 64-bit Mach-O output, see section 8.8.
- Fix assert failure on certain operations that involve strings with high-bit bytes.

C.1.48 Version 2.06

- This release is dedicated to the memory of Charles A. Crayne, long time NASM developer as well as moderator of `comp.lang.asm.x86` and author of the book *Serious Assembler*. We miss you, Chuck.
- Support for indirect macro expansion (`%[. . .]`). See section 4.1.3.
- `%pop` can now take an argument, see section 4.7.1.
- The argument to `%use` is no longer macro-expanded. Use `%[. . .]` if macro expansion is desired.
- Support for thread-local storage in ELF32 and ELF64. See section 8.9.4.
- Fix crash on `%ifmacro` without an argument.
- Correct the arguments to the POPCNT instruction.
- Fix section alignment in the Mach-O format.
- Update AVX support to version 5 of the Intel specification.
- Fix the handling of accesses to context-local macros from higher levels in the context stack.
- Treat WAIT as a prefix rather than as an instruction, thereby allowing constructs like `016 FSAVE` to work correctly.
- Support for structures with a non-zero base offset. See section 5.9.1.
- Correctly handle preprocessor token concatenation (see section 4.3.9) involving floating-point numbers.
- The PINSR series of instructions have been corrected and rationalized.
- Removed AMD SSE5, replaced with the new XOP/FMA4/CVT16 (rev 3.03) spec.
- The ELF backends no longer automatically generate a `.comment` section.
- Add additional "well-known" ELF sections with default attributes. See section 8.9.2.

C.1.49 Version 2.05.01

- Fix the `-w/-W` option parsing, which was broken in NASM 2.05.

C.1.50 Version 2.05

- Fix redundant REX.W prefix on `JMP reg64`.

- Make the behaviour of `-O0` match NASM 0.98 legacy behavior. See section 2.1.24.
- `-w-user` can be used to suppress the output of `%warning` directives. See section 2.1.26.
- Fix bug where `ALIGN` would issue a full alignment datum instead of zero bytes.
- Fix offsets in list files.
- Fix `%include` inside multi-line macros or loops.
- Fix error where NASM would generate a spurious warning on valid optimizations of immediate values.
- Fix arguments to a number of the CVT SSE instructions.
- Fix RIP-relative offsets when the instruction carries an immediate.
- Massive overhaul of the ELF64 backend for spec compliance.
- Fix the Geode PFRCPV and PFRSQRTV instruction.
- Fix the SSE 4.2 CRC32 instruction.

C.1.51 Version 2.04

- Sanitize macro handing in the `%error` directive.
- New `%warning` directive to issue user-controlled warnings.
- `%error` directives are now deferred to the final assembly phase.
- New `%fatal` directive to immediately terminate assembly.
- New `%strcat` directive to join quoted strings together.
- New `%use` macro directive to support standard macro directives. See section 4.6.4.
- Excess default parameters to `%macro` now issues a warning by default. See section 4.3.
- Fix `%ifn` and `%elifn`.
- Fix nested `%else` clauses.
- Correct the handling of nested `%reps`.
- New `%unmacro` directive to undeclare a multi-line macro. See section 4.3.12.
- Builtin macro `__PASS__` which expands to the current assembly pass. See section 5.8.
- `__utf16__` and `__utf32__` operators to generate UTF-16 and UTF-32 strings. See section 3.4.5.
- Fix bug in case-insensitive matching when compiled on platforms that don't use the `configure` script. Of the official release binaries, that only affected the OS/2 binary.
- Support for x87 packed BCD constants. See section 3.4.7.
- Correct the LTR and SLDT instructions in 64-bit mode.
- Fix unnecessary REX.W prefix on indirect jumps in 64-bit mode.
- Add AVX versions of the AES instructions (VAES...).
- Fix the 256-bit FMA instructions.
- Add 256-bit AVX stores per the latest AVX spec.
- VIA XCRYPT instructions can now be written either with or without REP, apparently different versions of the VIA spec wrote them differently.
- Add missing 64-bit MOVNTI instruction.

- Fix the operand size of VMREAD and VMWRITE.
- Numerous bug fixes, especially to the AES, AVX and VTX instructions.
- The optimizer now always runs until it converges. It also runs even when disabled, but doesn't optimize. This allows most forward references to be resolved properly.
- %push no longer needs a context identifier; omitting the context identifier results in an anonymous context.

C.1.52 Version 2.03.01

- Fix buffer overflow in the listing module.
- Fix the handling of hexadecimal escape codes in '...' strings.
- The Postscript/PDF documentation has been reformatted.
- The -F option now implies -g.

C.1.53 Version 2.03

- Add support for Intel AVX, CLMUL and FMA instructions, including YMM registers.
- dy, resy and yword for 32-byte operands.
- Fix some SSE5 instructions.
- Intel INVEPT, INVVPID and MOVBE instructions.
- Fix checking for critical expressions when the optimizer is enabled.
- Support the DWARF debugging format for ELF targets.
- Fix optimizations of signed bytes.
- Fix operation on bigendian machines.
- Fix buffer overflow in the preprocessor.
- SAFESEH support for Win32, IMAGEREL for Win64 (SEH).
- %? and %?? to refer to the name of a macro itself. In particular, %define keyword \$%? can be used to make a keyword "disappear".
- New options for dependency generation: -MD, -MF, -MP, -MT, -MQ.
- New preprocessor directives %pathsearch and %depend; INCBIN reimplemented as a macro.
- %include now resolves macros in a sane manner.
- %substr can now be used to get other than one-character substrings.
- New type of character/string constants, using backquotes ('...'), which support C-style escape sequences.
- %defstr and %idefstr to stringize macro definitions before creation.
- Fix forward references used in EQU statements.

C.1.54 Version 2.02

- Additional fixes for MMX operands with explicit qword, as well as (hopefully) SSE operands with oword.
- Fix handling of truncated strings with DO.
- Fix segfaults due to memory overwrites when floating-point constants were used.

- Fix segfaults due to missing include files.
- Fix OpenWatcom Makefiles for DOS and OS/2.
- Add autogenerated instruction list back into the documentation.
- ELF: Fix segfault when generating stabs, and no symbols have been defined.
- ELF: Experimental support for DWARF debugging information.
- New compile date and time standard macros.
- `%i fnum` now returns true for negative numbers.
- New `%i f token` test for a single token.
- New `%i f empty` test for empty expansion.
- Add support for the XSAVE instruction group.
- Makefile for Netware/gcc.
- Fix issue with some warnings getting emitted way too many times.
- Autogenerated instruction list added to the documentation.

C.1.55 Version 2.01

- Fix the handling of MMX registers with explicit `qword` tags on memory (broken in 2.00 due to 64-bit changes.)
- Fix the PREFETCH instructions.
- Fix the documentation.
- Fix debugging info when using `-f elf` (backwards compatibility alias for `-f elf32`).
- Man pages for `rdoff` tools (from the Debian project.)
- ELF: handle large numbers of sections.
- Fix corrupt output when the optimizer runs out of passes.

C.1.56 Version 2.00

- Added c99 data-type compliance.
- Added general x86-64 support.
- Added win64 (x86-64 COFF) output format.
- Added `__BITS__` standard macro.
- Renamed the `elf` output format to `elf32` for clarity.
- Added `elf64` and `macho` (MacOS X) output formats.
- Added Numeric constants in `dq` directive.
- Added `oword`, `do` and `reso` pseudo operands.
- Allow underscores in numbers.
- Added 8-, 16- and 128-bit floating-point formats.
- Added binary, octal and hexadecimal floating-point.
- Correct the generation of floating-point constants.
- Added floating-point option control.

- Added Infinity and NaN floating point support.
- Added ELF Symbol Visibility support.
- Added setting OSABI value in ELF header directive.
- Added Generate Makefile Dependencies option.
- Added Unlimited Optimization Passes option.
- Added %IFN and %ELIFN support.
- Added Logical Negation Operator.
- Enhanced Stack Relative Preprocessor Directives.
- Enhanced ELF Debug Formats.
- Enhanced Send Errors to a File option.
- Added SSSE3, SSE4.1, SSE4.2, SSE5 support.
- Added a large number of additional instructions.
- Significant performance improvements.
- `-w+warning` and `-w-warning` can now be written as `-Wwarning` and `-Wno-warning`, respectively. See section 2.1.26.
- Add `-w+error` to treat warnings as errors. See section 2.1.26.
- Add `-w+all` and `-w-all` to enable or disable all suppressible warnings. See section 2.1.26.

C.2 NASM 0.98 Series

The 0.98 series was the production versions of NASM from 1999 to 2007.

C.2.1 Version 0.98.39

- fix buffer overflow
- fix outas86's `.bss` handling
- "make spotless" no longer deletes `config.h.in`.
- `%(el)if(n)idn` insensitivity to string quotes difference (#809300).
- `(nasm.c) __OUTPUT_FORMAT__` changed to string value instead of symbol.

C.2.2 Version 0.98.38

- Add Makefile for 16-bit DOS binaries under OpenWatcom, and modify `mkdep.pl` to be able to generate completely pathless dependencies, as required by OpenWatcom `wmake` (it supports path searches, but not explicit paths.)
- Fix the STR instruction.
- Fix the ELF output format, which was broken under certain circumstances due to the addition of stabs support.
- Quick-fix Borland format `debug-info` for `-f obj`
- Fix for `%rep` with no arguments (#560568)
- Fix concatenation of preprocessor function call (#794686)
- Fix long label causes `coredump` (#677841)

- Use autoheader as well as autoconf to keep configure from generating ridiculously long command lines.
- Make sure that all of the formats which support debugging output actually will suppress debugging output when `-g` not specified.

C.2.3 Version 0.98.37

- Paths given in `-I` switch searched for `incbin`-ed as well as `%include`-ed files.
- Added stabs debugging for the ELF output format, patch from Martin Wawro.
- Fix `output/outbin.c` to allow `origin > 80000000h`.
- Make `-U` switch work.
- Fix the use of relative offsets with explicit prefixes, e.g. `a32 loop foo`.
- Remove `backslash()`.
- Fix the `SMSW` and `SLDT` instructions.
- `-O2` and `-O3` are no longer aliases for `-O10` and `-O15`. If you mean the latter, please say so! :)

C.2.4 Version 0.98.36

- Update `rdoff` – librarian/archiver – common rec – docs!
- Fix signed/unsigned problems.
- Fix `JMP FAR label` and `CALL FAR label`.
- Add new multisection support – map files – fix align bug
- Fix `sysexit`, `movhps/movlps reg,reg` bugs in `insns.dat`
- `Q` or `O` suffixes indicate octal
- Support Prescott new instructions (PNI).
- Cyrix `XSTORE` instruction.

C.2.5 Version 0.98.35

- Fix build failure on 16-bit DOS (Makefile.bc3 workaround for compiler bug.)
- Fix dependencies and compiler warnings.
- Add "const" in a number of places.
- Add `-X` option to specify error reporting format (use `-Xvc` to integrate with Microsoft Visual Studio.)
- Minor changes for code legibility.
- Drop use of `tmpnam()` in `rdoff` (security fix.)

C.2.6 Version 0.98.34

- Correct additional address-size vs. operand-size confusions.
- Generate dependencies for all Makefiles automatically.
- Add support for unimplemented (but theoretically available) registers such as `tr0` and `cr5`. Segment registers 6 and 7 are called `segr6` and `segr7` for the operations which they can be represented.
- Correct some disassembler bugs related to redundant address-size prefixes. Some work still remains in this area.
- Correctly generate an error for things like "SEG eax".

- Add the JMPE instruction, enabled by "CPU IA64".
- Correct compilation on newer gcc/glibc platforms.
- Issue an error on things like "jmp far eax".

C.2.7 Version 0.98.33

- New `__NASM_PATCHLEVEL__` and `__NASM_VERSION_ID__` standard macros to round out the version-query macros. `version.pl` now understands `X.YYplWW` or `X.YY.ZZplWW` as a version number, equivalent to `X.YY.ZZ.WW` (or `X.YY.0.WW`, as appropriate).
- New keyword "strict" to disable the optimization of specific operands.
- Fix the handing of size overrides with JMP instructions (instructions such as "jmp dword foo".)
- Fix the handling of "ABSOLUTE label", where "label" points into a relocatable segment.
- Fix OBJ output format with lots of externs.
- More documentation updates.
- Add `-Ov` option to get verbose information about optimizations.
- Undo a braindead change which broke `%e l i f` directives.
- Makefile updates.

C.2.8 Version 0.98.32

- Fix NASM crashing when `%macro` directives were left unterminated.
- Lots of documentation updates.
- Complete rewrite of the PostScript/PDF documentation generator.
- The MS Visual C++ Makefile was updated and corrected.
- Recognize `.rodata` as a standard section name in ELF.
- Fix some obsolete Perl4-isms in Perl scripts.
- Fix `configure.in` to work with `autoconf 2.5x`.
- Fix a couple of "make cleaner" misses.
- Make the normal `./configure && make` work with Cygwin.

C.2.9 Version 0.98.31

- Correctly build in a separate object directory again.
- Derive all references to the version number from the version file.
- New standard macros `__NASM_SUBMINOR__` and `__NASM_VER__` macros.
- Lots of Makefile updates and bug fixes.
- New `%i fmacro` directive to test for multiline macros.
- Documentation updates.
- Fixes for 16-bit OBJ format output.
- Changed the NASM environment variable to `NASMENV`.

C.2.10 Version 0.98.30

- Changed doc files a lot: completely removed old READMExx and Wishlist files, incorporating all information in CHANGES and TODO.
- I waited a long time to rename zoutieeee.c to (original) outieeee.c
- moved all output modules to output/ subdirectory.
- Added 'make strip' target to strip debug info from nasm & ndisasm.
- Added INSTALL file with installation instructions.
- Added -v option description to nasm man.
- Added dist makefile target to produce source distributions.
- 16-bit support for ELF output format (GNU extension, but useful.)

C.2.11 Version 0.98.28

- Fastcooked this for Debian's Woody release: Frank applied the INCBIN bug patch to 0.98.25alt and called it 0.98.28 to not confuse poor little apt-get.

C.2.12 Version 0.98.26

- Reorganised files even better from 0.98.25alt

C.2.13 Version 0.98.25alt

- Prettified the source tree. Moved files to more reasonable places.
- Added findleak.pl script to misc/ directory.
- Attempted to fix doc.

C.2.14 Version 0.98.25

- Line continuation character \.
- Docs inadvertently reverted - "dos packaging".

C.2.15 Version 0.98.24p1

- FIXME: Someone, document this please.

C.2.16 Version 0.98.24

- Documentation - Ndisasm doc added to Nasm.doc.

C.2.17 Version 0.98.23

- Attempted to remove rdoff version1
- Lino Mastrodomenico's patches to preproc.c (%\$\$ bug?).

C.2.18 Version 0.98.22

- Update rdoff2 - attempt to remove v1.

C.2.19 Version 0.98.21

- Optimization fixes.

C.2.20 Version 0.98.20

- Optimization fixes.

C.2.21 Version 0.98.19

- H. J. Lu's patch back out.

C.2.22 Version 0.98.18

- Added ".rdata" to "-f win32".

C.2.23 Version 0.98.17

- H. J. Lu's "bogus elf" patch. (Red Hat problem?)

C.2.24 Version 0.98.16

- Fix whitespace before "[section ..." bug.

C.2.25 Version 0.98.15

- Rdooff changes (?).
- Fix fixes to memory leaks.

C.2.26 Version 0.98.14

- Fix memory leaks.

C.2.27 Version 0.98.13

- There was no 0.98.13

C.2.28 Version 0.98.12

- Update optimization (new function of "-O1")
- Changes to test/bintest.asm (?).

C.2.29 Version 0.98.11

- Optimization changes.
- Ndisasm fixed.

C.2.30 Version 0.98.10

- There was no 0.98.10

C.2.31 Version 0.98.09

- Add multiple sections support to "-f bin".
- Changed GLOBAL_TEMP_BASE in outelf.c from 6 to 15.
- Add "-v" as an alias to the "-r" switch.
- Remove "#ifdef" from Tasm compatibility options.
- Remove redundant size-overrides on "mov ds, ex", etc.
- Fixes to SSE2, other insns.dat (?).
- Enable uppercase "I" and "P" switches.
- Case insinsitive "seg" and "wrt".
- Update install.sh (?).
- Allocate tokens in blocks.

- Improve "invalid effective address" messages.

C.2.32 Version 0.98.08

- Add "%strlen" and "%substr" macro operators
- Fixed broken c16.mac.
- Unterminated string error reported.
- Fixed bugs as per 0.98bf

C.2.33 Version 0.98.09b with John Coffman patches released 28-Oct-2001

Changes from 0.98.07 release to 98.09b as of 28-Oct-2001

- More closely compatible with 0.98 when -O0 is implied or specified. Not strictly identical, since backward branches in range of short offsets are recognized, and signed byte values with no explicit size specification will be assembled as a single byte.
- More forgiving with the PUSH instruction. 0.98 requires a size to be specified always. 0.98.09b will imply the size from the current BITS setting (16 or 32).
- Changed definition of the optimization flag:
 - O0 strict two-pass assembly, JMP and Jcc are handled more like 0.98, except that backward JMPs are short, if possible.
 - O1 strict two-pass assembly, but forward branches are assembled with code guaranteed to reach; may produce larger code than -O0, but will produce successful assembly more often if branch offset sizes are not specified.
 - O2 multi-pass optimization, minimize branch offsets; also will minimize signed immediate bytes, overriding size specification.
 - O3 like -O2, but more passes taken, if needed

C.2.34 Version 0.98.07 released 01/28/01

- Added Stepane Denis' SSE2 instructions to a *working* version of the code – some earlier versions were based on broken code – sorry 'bout that. version "0.98.07"
- Cosmetic modifications to nasm.c, nasm.h, AUTHORS, MODIFIED

C.2.35 Version 0.98.06f released 01/18/01

- Add "metalbrain"s jecxz bug fix in insns.dat
- Alter nasmdoc.src to match – version "0.98.06f"

C.2.36 Version 0.98.06e released 01/09/01

- Removed the "outforms.h" file – it appears to be someone's old backup of "outform.h". version "0.98.06e"
- fbk – finally added the fix for the "multiple %includes bug", known since 7/27/99 – reported originally (?) and sent to us by Austin Lunnen – he reports that John Fine had a fix within the day. Here it is...

- Nelson Rush resigns from the group. Big thanks to Nelson for his leadership and enthusiasm in getting these changes incorporated into Nasm!
- fbk - [list +], [list -] directives - ineptly implemented, should be re-written or removed, perhaps.
- Brian Raiter / fbk - "elfso bug" fix - applied to aoutb format as well - testing might be desirable...
- James Seter - -postfix, -prefix command line switches.
- Yuri Zaporozhets - rdoff utility changes.

C.2.37 Version 0.98p1

- GAS-like palign (Panos Minos)
- FIXME: Someone, fill this in with details

C.2.38 Version 0.98bf (bug-fixed)

- Fixed - elf and aoutb bug - shared libraries - multiple "%include" bug in "-f obj" - jcxz, jecxz bug - unrecognized option bug in ndisasm

C.2.39 Version 0.98.03 with John Coffman's changes released 27-Jul-2000

- Added signed byte optimizations for the 0x81/0x83 class of instructions: ADC, ADD, AND, CMP, OR, SBB, SUB, XOR: when used as 'ADD reg16,imm' or 'ADD reg32,imm.' Also optimization of signed byte form of 'PUSH imm' and 'IMUL reg,imm'/'IMUL reg,reg,imm.' No size specification is needed.
- Added multi-pass JMP and Jcc offset optimization. Offsets on forward references will preferentially use the short form, without the need to code a specific size (short or near) for the branch. Added instructions for 'Jcc label' to use the form 'Jnotcc \$+3/JMP label', in cases where a short offset is out of bounds. If compiling for a 386 or higher CPU, then the 386 form of Jcc will be used instead.

This feature is controlled by a new command-line switch: "O", (upper case letter O). "-O0" reverts the assembler to no extra optimization passes, "-O1" allows up to 5 extra passes, and "-O2"(default), allows up to 10 extra optimization passes.
- Added a new directive: 'cpu XXX', where XXX is any of: 8086, 186, 286, 386, 486, 586, pentium, 686, PPro, P2, P3 or Katmai. All are case insensitive. All instructions will be selected only if they apply to the selected cpu or lower. Corrected a couple of bugs in cpu-dependence in 'sns.dat'.
- Added to 'standard.mac', the "use16" and "use32" forms of the "bits 16/32" directive. This is nothing new, just conforms to a lot of other assemblers. (minor)
- Changed label allocation from 320/32 (10000 labels @ 200K+) to 32/37 (1000 labels); makes running under DOS much easier. Since additional label space is allocated dynamically, this should have no effect on large programs with lots of labels. The 37 is a prime, believed to be better for hashing. (minor)

C.2.40 Version 0.98.03

"Integrated patchfile 0.98-0.98.01. I call this version 0.98.03 for historical reasons: 0.98.02 was trashed."
--John Coffman <johninsd@san.rr.com>, 27-Jul-2000

- Kendall Bennett's SciTech MGL changes
- Note that you must define "TASM_COMPAT" at compile-time to get the Tasm Ideal Mode compatibility.
- All changes can be compiled in and out using the TASM_COMPAT macros, and when compiled without TASM_COMPAT defined we get the exact same binary as the unmodified 0.98 sources.
- standard.mac, macros.c: Added macros to ignore TASM directives before first include

- nasm.h: Added extern declaration for tasm_compatible_mode
- nasm.c: Added global variable tasm_compatible_mode
- Added command line switch for TASM compatible mode (-t)
- Changed version command line to reflect when compiled with TASM additions
- Added response file processing to allow all arguments on a single line (response file is @resp rather than -@resp for NASM format).
- labels.c: Changes islocal() macro to support TASM style @@local labels.
- Added islocalchar() macro to support TASM style @@local labels.
- parser.c: Added support for TASM style memory references (ie: mov [DWORD eax],10 rather than the NASM style mov DWORD [eax],10).
- preproc.c: Added new directives, %arg, %local, %stacksize to directives table
- Added support for TASM style directives without a leading % symbol.
- Integrated a block of changes from Andrew Zabolotny <bit@eltech.ru>:
- A new keyword %xdefine and its case-insensitive counterpart %ixdefine. They work almost the same way as %define and %idefine but expand the definition immediately, not on the invocation. Something like a cross between %define and %assign. The "x" suffix stands for "eXpand", so "xdefine" can be deciphered as "expand-and-define". Thus you can do things like this:

```

%assign ofs      0

%macro  arg      1
    %xdefine %1 dword [esp+ofs]
    %assign ofs ofs+4
%endmacro

```

- Changed the place where the expansion of %\$name macros are expanded. Now they are converted into ..@ctxnum.name form when detokenizing, so there are no quirks as before when using %\$name arguments to macros, in macros etc. For example:

```

%macro  abc      1
    %define %1 hello
%endm

abc      %$here
%$here

```

Now last line will be expanded into "hello" as expected. This also allows for lots of goodies, a good example are extended "proc" macros included in this archive.

- Added a check for "cstk" in smacro_defined() before calling get_ctx() – this allows for things like:

```

%ifdef %$abc
%endif

```

to work without warnings even in no context.

- Added a check for "cstk" in %if*ctx and %elif*ctx directives – this allows to use %if ctx without excessive warnings. If there is no active context, %if ctx goes through "false" branch.
- Removed "user error: " prefix with %error directive: it just clobbers the output and has absolutely no functionality. Besides, this allows to write macros that does not differ from built-in functions in any way.

- Added expansion of string that is output by `%error` directive. Now you can do things like:

```
%define hello(x) Hello, x!

%define %$name andy
%error "hello(%$name)"
```

Same happened with `%include` directive.

- Now all directives that expect an identifier will try to expand and concatenate everything without whitespaces in between before usage. For example, with "unfixed" nasm the commands

```
%define %$abc hello
%define __%$abc goodbye
__%$abc
```

would produce "incorrect" output: last line will expand to

```
hello goodbyehello
```

Not quite what you expected, eh? :-). The answer is that preprocessor treats the `%define` construct as if it would be

```
%define __ %$abc goodbye
```

(note the white space between `__` and `%$abc`). After my "fix" it will "correctly" expand into

```
goodbye
```

as expected. Note that I use quotes around words "correct", "incorrect" etc because this is rather a feature not a bug; however current behaviour is more logical (and allows more advanced macro usage :-).

Same change was applied to:
`%push,%macro,%imacro,%define,%idefine,%xdefine,%ixdefine,`
`%assign,%iassign,%undef`

- A new directive `[WARNING {+|-}warning-id]` have been added. It works only if the assembly phase is enabled (i.e. it doesn't work with `nasm -e`).
- A new warning type: `macro-selfref`. By default this warning is disabled; when enabled NASM warns when a macro self-references itself; for example the following source:

```
[WARNING macro-selfref]

%macro          push    1-*
    %rep        %0
        push    %1
        %rotate 1
    %endrep
%endmacro

                push    eax,ebx,ecx
```

will produce a warning, but if we remove the first line we won't see it anymore (which is The Right Thing To Do {tm} IMHO since C preprocessor eats such constructs without warnings at all).

- Added a "error" routine to preprocessor which always will set `ERR_PASS1` bit in `severity_code`. This removes annoying repeated errors on first and second passes from preprocessor.
- Added the `%+` operator in single-line macros for concatenating two identifiers. Usage example:

```

%define _myfunc _otherfunc
%define cextern(x) _ %+ x
cextern (myfunc)

```

After first expansion, third line will become "_myfunc". After this expansion is performed again so it becomes "_otherfunc".

- Now if preprocessor is in a non-emitting state, no warning or error will be emitted. Example:

```

%if 1
    mov     eax,ebx
%else
    put anything you want between these two brackets,
    even macro-parameter references %1 or local
    labels %$zzz or macro-local labels %%zzz - no
    warning will be emitted.
%endif

```

- Context-local variables on expansion as a last resort are looked up in outer contexts. For example, the following piece:

```

%push     outer
%define  %$a [esp]

    %push     inner
    %$a
    %pop
%pop

```

will expand correctly the fourth line to [esp]; if we'll define another %\$a inside the "inner" context, it will take precedence over outer definition. However, this modification has been applied only to `expand_macro` and not to `macro_define`: as a consequence expansion looks in outer contexts, but `%ifdef` won't look in outer contexts.

This behaviour is needed because we don't want nested contexts to act on already defined local macros. Example:

```

%define  %$arg1 [esp+4]
test     eax,eax
if      nz
    mov     eax,%$arg1
endif

```

In this example the "if" macro enters into the "if" context, so %\$arg1 is not valid anymore inside "if". Of course it could be worked around by using explicitly %\$arg1 but this is ugly IMHO.

- Fixed memory leak in `%undef`. The origline wasn't freed before exiting on success.
- Fixed trap in preprocessor when line expanded to empty set of tokens. This happens, for example, in the following case:

```

#define SOMETHING
SOMETHING

```

C.2.41 Version 0.98

All changes since NASM 0.98p3 have been produced by H. Peter Anvin <hpa@zytor.com>.

- The documentation comment delimiter is
- Allow EQU definitions to refer to external labels; reported by Pedro Gimeno.

- Re-enable support for RDOFF v1; reported by Pedro Gimeno.
- Updated License file per OK from Simon and Julian.

C.2.42 Version 0.98p9

- Update documentation (although the instruction set reference will have to wait; I don't want to hold up the 0.98 release for it.)
- Verified that the NASM implementation of the PEXTRW and PMOVMSKB instructions is correct. The encoding differs from what the Intel manuals document, but the Pentium III behaviour matches NASM, not the Intel manuals.
- Fix handling of implicit sizes in PSHUFW and PINSRW, reported by Stefan Hoffmeister.
- Resurrect the `-s` option, which was removed when changing the diagnostic output to `stdout`.

C.2.43 Version 0.98p8

- Fix for "DB" when NASM is running on a bigendian machine.
- Invoke `insns.pl` once for each output script, making `Makefile.in` legal for "make -j".
- Improve the Unix configure-based makefiles to make package creation easier.
- Included an RPM `.spec` file for building RPM (RedHat Package Manager) packages on Linux or Unix systems.
- Fix Makefile dependency problems.
- Change `src/rdsrc.pl` to include sectioning information in info output; required for `install-info` to work.
- Updated the RDOFF distribution to version 2 from Jules; minor massaging to make it compile in my environment.
- Split doc files that can be built by anyone with a Perl interpreter off into a separate archive.
- "Dress rehearsal" release!

C.2.44 Version 0.98p7

- Fixed opcodes with a third byte-sized immediate argument to not complain if given "byte" on the immediate.
- Allow `%undef` to remove single-line macros with arguments. This matches the behaviour of `#undef` in the C preprocessor.
- Allow `-d`, `-u`, `-i` and `-p` to be specified as `-D`, `-U`, `-I` and `-P` for compatibility with most C compilers and preprocessors. This allows Makefile options to be shared between `cc` and `nasm`, for example.
- Minor cleanups.
- Went through the list of Katmai instructions and hopefully fixed the (rather few) mistakes in it.
- (Hopefully) fixed a number of disassembler bugs related to ambiguous instructions (disambiguated by `-p`) and SSE instructions with `REP`.
- Fix for bug reported by Mark Junger: "call dword 0x12345678" should work and may add an OSP (affected `CALL`, `JMP`, `Jcc`).
- Fix for environments when "stderr" isn't a compile-time constant.

C.2.45 Version 0.98p6

- Took officially over coordination of the 0.98 release; so drop the p3.x notation. Skipped p4 and p5 to avoid confusion with John Fine's J4 and J5 releases.

- Update the documentation; however, it still doesn't include documentation for the various new instructions. I somehow wonder if it makes sense to have an instruction set reference in the assembler manual when Intel et al have PDF versions of their manuals online.
- Recognize "idt" or "centaur" for the -p option to ndisasm.
- Changed error messages back to stderr where they belong, but add an -E option to redirect them elsewhere (the DOS shell cannot redirect stderr.)
- -M option to generate Makefile dependencies (based on code from Alex Verstak.)
- %undef preprocessor directive, and -u option, that undefines a single-line macro.
- OS/2 Makefile (Mkfiles/Makefile.os2) for Borland under OS/2; from Chuck Crayne.
- Various minor bugfixes (reported by): - Dangling %s in preproc.c (Martin Junker)
- THERE ARE KNOWN BUGS IN SSE AND THE OTHER KATMAI INSTRUCTIONS. I am on a trip and didn't bring the Katmai instruction reference, so I can't work on them right now.
- Updated the License file per agreement with Simon and Jules to include a GPL distribution clause.

C.2.46 Version 0.98p3.7

- (Hopefully) fixed the canned Makefiles to include the outrdf2 and zoutieee modules.
- Renamed changes.asm to changed.asm.

C.2.47 Version 0.98p3.6

- Fixed a bunch of instructions that were added in 0.98p3.5 which had memory operands, and the address-size prefix was missing from the instruction pattern.

C.2.48 Version 0.98p3.5

- Merged in changes from John S. Fine's 0.98-J5 release. John's based 0.98-J5 on my 0.98p3.3 release; this merges the changes.
- Expanded the instructions flag field to a long so we can fit more flags; mark SSE (KNI) and AMD or Katmai-specific instructions as such.
- Fix the "PRIV" flag on a bunch of instructions, and create new "PROT" flag for protected-mode-only instructions (orthogonal to if the instruction is privileged!) and new "SMM" flag for SMM-only instructions.
- Added AMD-only SYSCALL and SYSRET instructions.
- Make SSE actually work, and add new Katmai MMX instructions.
- Added a -p (preferred vendor) option to ndisasm so that it can distinguish e.g. Cyrix opcodes also used in SSE. For example:

```

ndisasm -p cyrix aliased.bin
00000000 670F514310          paddsiw mm0,[ebx+0x10]
00000005 670F514320          paddsiw mm0,[ebx+0x20]
ndisasm -p intel aliased.bin
00000000 670F514310          sqrtps xmm0,[ebx+0x10]
00000005 670F514320          sqrtps xmm0,[ebx+0x20]

```

- Added a bunch of Cyrix-specific instructions.

C.2.49 Version 0.98p3.4

- Made at least an attempt to modify all the additional Makefiles (in the Mkfiles directory). I can't test it, but this was the best I could do.

- DOS DJGPP+"Opus Make" Makefile from John S. Fine.
- changes.asm changes from John S. Fine.

C.2.50 Version 0.98p3.3

- Patch from Conan Brink to allow nesting of %rep directives.
- If we're going to allow INT01 as an alias for INT1/ICEBP (one of Jules 0.98p3 changes), then we should allow INT03 as an alias for INT3 as well.
- Updated changes.asm to include the latest changes.
- Tried to clean up the <CR>s that had snuck in from a DOS/Windows environment into my Unix environment, and try to make sure than DOS/Windows users get them back.
- We would silently generate broken tools if insns.dat wasn't sorted properly. Change insns.pl so that the order doesn't matter.
- Fix bug in insns.pl (introduced by me) which would cause conditional instructions to have an extra "cc" in disassembly, e.g. "jnz" disassembled as "jccnz".

C.2.51 Version 0.98p3.2

- Merged in John S. Fine's changes from his 0.98-J4 prerelease; see <http://www.csoft.net/cz/johnfine/>
- Changed previous "spotless" Makefile target (appropriate for distribution) to "distclean", and added "cleaner" target which is same as "clean" except deletes files generated by Perl scripts; "spotless" is union.
- Removed BASIC programs from distribution. Get a Perl interpreter instead (see below.)
- Calling this "pre-release 3.2" rather than "p3-hpa2" because of John's contributions.
- Actually link in the IEEE output format (zoutieee.c); fix a bunch of compiler warnings in that file. Note I don't know what IEEE output is supposed to look like, so these changes were made "blind".

C.2.52 Version 0.98p3-hpa

- Merged nasm098p3.zip with nasm-0.97.tar.gz to create a fully buildable version for Unix systems (Makefile.in updates, etc.)
- Changed insns.pl to create the instruction tables in nasm.h and names.c, so that a new instruction can be added by adding it *only* to insns.dat.
- Added the following new instructions: SYSENTER, SYSEXIT, FXSAVE, FXRSTOR, UD1, UD2 (the latter two are two opcodes that Intel guarantee will never be used; one of them is documented as UD2 in Intel documentation, the other one just as "Undefined Opcode" -- calling it UD1 seemed to make sense.)
- MAX_SYMBOL was defined to be 9, but LOADALL286 and LOADALL386 are 10 characters long. Now MAX_SYMBOL is derived from insns.dat.
- A note on the BASIC programs included: forget them. insns.bas is already out of date. Get yourself a Perl interpreter for your platform of choice at <http://www.cpan.org/ports/index.html>.

C.2.53 Version 0.98 pre-release 3

- added response file support, improved command line handling, new layout help screen
- fixed limit checking bug, 'OUT byte nn, reg' bug, and a couple of rdoft related bugs, updated Wishlist; 0.98 Prerelease 3.

C.2.54 Version 0.98 pre-release 2

- fixed bug in outcoff.c to do with truncating section names longer than 8 characters, referencing beyond end of string; 0.98 pre-release 2

C.2.55 Version 0.98 pre-release 1

- Fixed a bug whereby STRUC didn't work at all in RDF.
- Fixed a problem with group specification in PUBDEFs in OBJ.
- Improved ease of adding new output formats. Contribution due to Fox Cutter.
- Fixed a bug in relocations in the 'bin' format: was showing up when a relocatable reference crossed an 8192-byte boundary in any output section.
- Fixed a bug in local labels: local-label lookups were inconsistent between passes one and two if an EQU occurred between the definition of a global label and the subsequent use of a local label local to that global.
- Fixed a seg-fault in the preprocessor (again) which happened when you use a blank line as the first line of a multi-line macro definition and then defined a label on the same line as a call to that macro.
- Fixed a stale-pointer bug in the handling of the NASM environment variable. Thanks to Thomas McWilliams.
- ELF had a hard limit on the number of sections which caused segfaults when transgressed. Fixed.
- Added ability for ndisasm to read from stdin by using '-' as the filename.
- ndisasm wasn't outputting the TO keyword. Fixed.
- Fixed error cascade on bogus expression in `%i f` – an error in evaluation was causing the entire `%i f` to be discarded, thus creating trouble later when the `%e l s e` or `%e n d i f` was encountered.
- Forward reference tracking was instruction-granular not operand-granular, which was causing 286-specific code to be generated needlessly on code of the form `'shr word [forwardref],1'`. Thanks to Jim Hague for sending a patch.
- All messages now appear on stdout, as sending them to stderr serves no useful purpose other than to make redirection difficult.
- Fixed the problem with EQUs pointing to an external symbol – this now generates an error message.
- Allowed multiple size prefixes to an operand, of which only the first is taken into account.
- Incorporated John Fine's changes, including fixes of a large number of preprocessor bugs, some small problems in OBJ, and a reworking of label handling to define labels before their line is assembled, rather than after.
- Reformatted a lot of the source code to be more readable. Included 'coding.txt' as a guideline for how to format code for contributors.
- Stopped nested `%r e p s` causing a panic – they now cause a slightly more friendly error message instead.
- Fixed floating point constant problems (patch by Pedro Gimeno)
- Fixed the return value of `insn_size()` not being checked for -1, indicating an error.
- Incorporated 3Dnow! instructions.
- Fixed the 'mov eax, eax + ebx' bug.
- Fixed the GLOBAL EQU bug in ELF. Released developers release 3.

- Incorporated John Fine's command line parsing changes
- Incorporated David Lindauer's OMF debug support
- Made changes for LCC 4.0 support (`__NASM_CDec1__`, removed register size specification warning when sizes agree).

C.3 NASM 0.9 Series

Revisions before 0.98.

C.3.1 Version 0.97 released December 1997

- This was entirely a bug-fix release to 0.96, which seems to have got cursed. Silly me.
- Fixed stupid mistake in OBJ which caused 'MOV EAX,<constant>' to fail. Caused by an error in the 'MOV EAX,<segment>' support.
- `ndisasm` hung at EOF when compiled with `lcc` on Linux because `lcc` on Linux somehow breaks `feof()`. `ndisasm` now does not rely on `feof()`.
- A heading in the documentation was missing due to a markup error in the indexing. Fixed.
- Fixed failure to update all pointers on `realloc()` within extended-operand code in `parser.c`. Was causing wrong behaviour and seg faults on lines such as 'dd 0.0,0.0,0.0,0.0,...'
- Fixed a subtle preprocessor bug whereby invoking one multi-line macro on the first line of the expansion of another, when the second had been invoked with a label defined before it, didn't expand the inner macro.
- Added `internal.doc` back in to the distribution archives – it was missing in 0.96 *blush*
- Fixed bug causing 0.96 to be unable to assemble its own test files, specifically `objtest.asm`. *blush again*
- Fixed seg-faults and bogus error messages caused by mismatching `%rep` and `%endrep` within multi-line macro definitions.
- Fixed a problem with buffer overrun in OBJ, which was causing corruption at ends of long PUBDEF records.
- Separated DOS archives into main-program and documentation to reduce download size.

C.3.2 Version 0.96 released November 1997

- Fixed a bug whereby, if 'nasm sourcefile' would cause a filename collision warning and put output into 'nasm.out', then 'nasm sourcefile -o outputfile' still gave the warning even though the '-o' was honoured. Fixed name pollution under Digital UNIX: one of its header files defined `R_SP`, which broke the enum in `nasm.h`.
- Fixed minor instruction table problems: `FUCOM` and `FUCOMP` didn't have two-operand forms; `NDISASM` didn't recognise the longer register forms of `PUSH` and `POP` (eg `FF F3` for `PUSH BX`); `TEST mem,imm32` was flagged as undocumented; the 32-bit forms of `CMOV` had 16-bit operand size prefixes; 'AAD imm' and 'AAM imm' are no longer flagged as undocumented because the Intel Architecture reference documents them.
- Fixed a problem with the local-label mechanism, whereby strange types of symbol (`EQU`s, auto-defined OBJ segment base symbols) interfered with the 'previous global label' value and screwed up local labels.
- Fixed a bug whereby the stub preprocessor didn't communicate with the listing file generator, so that the `-a` and `-l` options in conjunction would produce a useless listing file.

- Merged 'os2' object file format back into 'obj', after discovering that 'obj' _also_ shouldn't have a link pass separator in a module containing a non-trivial MODEND. Flat segments are now declared using the FLAT attribute. 'os2' is no longer a valid object format name: use 'obj'.
- Removed the fixed-size temporary storage in the evaluator. Very very long expressions (like 'mov ax,1+1+1+1+...' for two hundred 1s or so) should now no longer crash NASM.
- Fixed a bug involving segfaults on disassembly of MMX instructions, by changing the meaning of one of the operand-type flags in nasm.h. This may cause other apparently unrelated MMX problems; it needs to be tested thoroughly.
- Fixed some buffer overrun problems with large OBJ output files. Thanks to DJ Delorie for the bug report and fix.
- Made preprocess-only mode actually listen to the %line markers as it prints them, so that it can report errors more sanely.
- Re-designed the evaluator to keep more sensible track of expressions involving forward references: can now cope with previously-nightmare situations such as:


```
mov ax,foo | bar
foo equ 1
bar equ 2
```
- Added the ALIGN and ALIGNB standard macros.
- Added PIC support in ELF: use of WRT to obtain the four extra relocation types needed.
- Added the ability for output file formats to define their own extensions to the GLOBAL, COMMON and EXTERN directives.
- Implemented common-variable alignment, and global-symbol type and size declarations, in ELF.
- Implemented NEAR and FAR keywords for common variables, plus far-common element size specification, in OBJ.
- Added a feature whereby EXTERNs and COMMONs in OBJ can be given a default WRT specification (either a segment or a group).
- Transformed the Unix NASM archive into an auto-configuring package.
- Added a sanity-check for people applying SEG to things which are already segment bases: this previously went unnoticed by the SEG processing and caused OBJ-driver panics later.
- Added the ability, in OBJ format, to deal with 'MOV EAX,<segment>' type references: OBJ doesn't directly support dword-size segment base fixups, but as long as the low two bytes of the constant term are zero, a word-size fixup can be generated instead and it will work.
- Added the ability to specify sections' alignment requirements in Win32 object files and pure binary files.
- Added preprocess-time expression evaluation: the %assign (and %iassign) directive and the bare %if (and %elif) conditional. Added relational operators to the evaluator, for use only in %if constructs: the standard relationals = < > <= >= <> (and C-like synonyms == and !=) plus low-precedence logical operators &&, ^^ and ||.
- Added a preprocessor repeat construct: %rep / %exitrep / %endrep.
- Added the __FILE__ and __LINE__ standard macros.
- Added a sanity check for number constants being greater than 0xFFFFFFFF. The warning can be disabled.

- Added the `%0` token whereby a variadic multi-line macro can tell how many parameters it's been given in a specific invocation.
- Added `%rotate`, allowing multi-line macro parameters to be cycled.
- Added the `**` option for the maximum parameter count on multi-line macros, allowing them to take arbitrarily many parameters.
- Added the ability for the user-level forms of `EXTERN`, `GLOBAL` and `COMMON` to take more than one argument.
- Added the `IMPORT` and `EXPORT` directives in `OBJ` format, to deal with Windows DLLs.
- Added some more preprocessor `%if` constructs: `%ifidn / %ifidni` (exact textual identity), and `%ifid / %ifnum / %ifstr` (token type testing).
- Added the ability to distinguish `SHL AX,1` (the 8086 version) from `SHL AX,BYTE 1` (the 286-and-upwards version whose constant happens to be 1).
- Added NetBSD/FreeBSD/OpenBSD's variant of `a.out` format, complete with PIC shared library features.
- Changed NASM's idiosyncratic handling of `FCLEX`, `FDISI`, `FENI`, `FINIT`, `FSAVE`, `FSTCW`, `FSTENV`, and `FSTSW` to bring it into line with the otherwise accepted standard. The previous behaviour, though it was a deliberate feature, was a deliberate feature based on a misunderstanding. Apologies for the inconvenience.
- Improved the flexibility of `ABSOLUTE`: you can now give it an expression rather than being restricted to a constant, and it can take relocatable arguments as well.
- Added the ability for a variable to be declared as `EXTERN` multiple times, and the subsequent definitions are just ignored.
- We now allow instruction prefixes (`CS`, `DS`, `LOCK`, `REPZ` etc) to be alone on a line (without a following instruction).
- Improved sanity checks on whether the arguments to `EXTERN`, `GLOBAL` and `COMMON` are valid identifiers.
- Added `misc/exebin.mac` to allow direct generation of `.EXE` files by hacking up an `EXE` header using `DB` and `DW`; also added `test/binexe.asm` to demonstrate the use of this. Thanks to Yann Guidon for contributing the `EXE` header code.
- `ndisasm` forgot to check whether the input file had been successfully opened. Now it does. Doh!
- Added the Cyrix extensions to the `MMX` instruction set.
- Added a hinting mechanism to allow `[EAX+EBX]` and `[EBX+EAX]` to be assembled differently. This is important since `[ESI+EBP]` and `[EBP+ESI]` have different default base segment registers.
- Added support for the PharLap `OMF` extension for 4096-byte segment alignment.

C.3.3 Version 0.95 released July 1997

- Fixed yet another ELF bug. This one manifested if the user relied on the default segment, and attempted to define global symbols without first explicitly declaring the target segment.
- Added makefiles (for NASM and the RDF tools) to build Win32 console apps under Symantec C++. Donated by Mark Junker.
- Added `'macros.bas'` and `'insns.bas'`, QBasic versions of the Perl scripts that convert `'standard.mac'` to `'macros.c'` and convert `'insns.dat'` to `'insnsa.c'` and `'insnsd.c'`. Also thanks to Mark Junker.

- Changed the disassembled forms of the conditional instructions so that JB is now emitted as JC, and other similar changes. Suggested list by Ulrich Doewich.
- Added '@' to the list of valid characters to begin an identifier with.
- Documentary changes, notably the addition of the 'Common Problems' section in nasm.doc.
- Fixed a bug relating to 32-bit PC-relative fixups in OBJ.
- Fixed a bug in perm_copy() in labels.c which was causing exceptions in cleanup_labels() on some systems.
- Positivity sanity check in TIMES argument changed from a warning to an error following a further complaint.
- Changed the acceptable limits on byte and word operands to allow things like '~10111001b' to work.
- Fixed a major problem in the preprocessor which caused seg-faults if macro definitions contained blank lines or comment-only lines.
- Fixed inadequate error checking on the commas separating the arguments to 'db', 'dw' etc.
- Fixed a crippling bug in the handling of macros with operand counts defined with a '+' modifier.
- Fixed a bug whereby object file formats which stored the input file name in the output file (such as OBJ and COFF) weren't doing so correctly when the output file name was specified on the command line.
- Removed [INC] and [INCLUDE] support for good, since they were obsolete anyway.
- Fixed a bug in OBJ which caused all fixups to be output in 16-bit (old-format) FIXUPP records, rather than putting the 32-bit ones in FIXUPP32 (new-format) records.
- Added, tentatively, OS/2 object file support (as a minor variant on OBJ).
- Updates to Fox Cutter's Borland C makefile, Makefile.bc2.
- Removed a spurious second fclose() on the output file.
- Added the '-s' command line option to redirect all messages which would go to stderr (errors, help text) to stdout instead.
- Added the '-w' command line option to selectively suppress some classes of assembly warning messages.
- Added the '-p' pre-include and '-d' pre-define command-line options.
- Added an include file search path: the '-i' command line option.
- Fixed a silly little preprocessor bug whereby starting a line with a '%!' environment-variable reference caused an 'unknown directive' error.
- Added the long-awaited listing file support: the '-l' command line option.
- Fixed a problem with OBJ format whereby, in the absence of any explicit segment definition, non-global symbols declared in the implicit default segment generated spurious EXTDEF records in the output.
- Added the NASM environment variable.
- From this version forward, Win32 console-mode binaries will be included in the DOS distribution in addition to the 16-bit binaries. Added Makefile.vc for this purpose.
- Added 'return 0;' to test/objlink.c to prevent compiler warnings.
- Added the __NASM_MAJOR__ and __NASM_MINOR__ standard defines.

- Added an alternative memory-reference syntax in which prefixing an operand with '&' is equivalent to enclosing it in square brackets, at the request of Fox Cutter.
- Errors in pass two now cause the program to return a non-zero error code, which they didn't before.
- Fixed the single-line macro cycle detection, which didn't work at all on macros with no parameters (caused an infinite loop). Also changed the behaviour of single-line macro cycle detection to work like cpp, so that macros like 'extrn' as given in the documentation can be implemented.
- Fixed the implementation of WRT, which was too restrictive in that you couldn't do 'mov ax,[di+abc wrt dgroup]' because (di+abc) wasn't a relocatable reference.

C.3.4 Version 0.94 released April 1997

- Major item: added the macro processor.
- Added undocumented instructions SMI, IBTS, XBTS and LOADALL286. Also reorganised CMPXCHG instruction into early-486 and Pentium forms. Thanks to Tobias Jones for the information.
- Fixed two more stupid bugs in ELF, which were causing 'ld' to continue to seg-fault in a lot of non-trivial cases.
- Fixed a seg-fault in the label manager.
- Stopped FBLD and FBSTP from `_requiring_` the TWORD keyword, which is the only option for BCD loads/stores in any case.
- Ensured FLDCW, FSTCW and FSTSW can cope with the WORD keyword, if anyone bothers to provide it. Previously they complained unless no keyword at all was present.
- Some forms of FDIV/FDIVR and FSUB/FSUBR were still inverted: a vestige of a bug that I thought had been fixed in 0.92. This was fixed, hopefully for good this time...
- Another minor phase error (insofar as a phase error can `_ever_` be minor) fixed, this one occurring in code of the form


```
ro1 ax, forward_reference
forward_reference equ 1
```
- The number supplied to TIMES is now sanity-checked for positivity, and also may be greater than 64K (which previously didn't work on 16-bit systems).
- Added Watcom C makefiles, and misc/pmw.bat, donated by Dominik Behr.
- Added the INCBIN pseudo-opcode.
- Due to the advent of the preprocessor, the [INCLUDE] and [INC] directives have become obsolete. They are still supported in this version, with a warning, but won't be in the next.
- Fixed a bug in OBJ format, which caused incorrect object records to be output when absolute labels were made global.
- Updates to RDOFF subdirectory, and changes to outrdf.c.

C.3.5 Version 0.93 released January 1997

This release went out in a great hurry after semi-crippling bugs were found in 0.92.

- Really *did* fix the stack overflows this time. *blush*
- Had problems with EA instruction sizes changing between passes, when an offset contained a forward reference and so 4 bytes were allocated for the offset in pass one; by pass two the symbol had been defined and happened to be a small absolute value, so only 1 byte got allocated, causing instruction size mismatch between passes and hence incorrect address calculations. Fixed.

- Stupid bug in the revised ELF section generation fixed (associated string-table section for .symtab was hard-coded as 7, even when this didn't fit with the real section table). Was causing 'ld' to seg-fault under Linux.
- Included a new Borland C makefile, Makefile.bc2, donated by Fox Cutter <lmb@comtch.iea.com>.

C.3.6 Version 0.92 released January 1997

- The FDIVP/FDIVRP and FSUBP/FSUBRP pairs had been inverted: this was fixed. This also affected the LCC driver.
- Fixed a bug regarding 32-bit effective addresses of the form [other_register+ESP].
- Documentary changes, notably documentation of the fact that Borland Win32 compilers use 'obj' rather than 'win32' object format.
- Fixed the COMMENT record in OBJ files, which was formatted incorrectly.
- Fixed a bug causing segfaults in large RDF files.
- OBJ format now strips initial periods from segment and group definitions, in order to avoid complications with the local label syntax.
- Fixed a bug in disassembling far calls and jumps in NDISASM.
- Added support for user-defined sections in COFF and ELF files.
- Compiled the DOS binaries with a sensible amount of stack, to prevent stack overflows on any arithmetic expression containing parentheses.
- Fixed a bug in handling of files that do not terminate in a newline.

C.3.7 Version 0.91 released November 1996

- Loads of bug fixes.
- Support for RDF added.
- Support for DBG debugging format added.
- Support for 32-bit extensions to Microsoft OBJ format added.
- Revised for Borland C: some variable names changed, makefile added.
- LCC support revised to actually work.
- JMP/CALL NEAR/FAR notation added.
- 'a16', 'o16', 'a32' and 'o32' prefixes added.
- Range checking on short jumps implemented.
- MMX instruction support added.
- Negative floating point constant support added.
- Memory handling improved to bypass 64K barrier under DOS.
- \$ prefix to force treatment of reserved words as identifiers added.
- Default-size mechanism for object formats added.
- Compile-time configurability added.
- #, @, ~ and c{?} are now valid characters in labels.
- -e and -k options in NDISASM added.

C.3.8 Version 0.90 released October 1996

First release version. First support for object file output. Other changes from previous version (0.3x) too numerous to document.

Appendix D: Building NASM from Source

The source code for NASM is available from our website, <http://www.nasm.us/>, see section E.1.

D.1 Building from a Source Archive

The source archives available on the web site should be capable of building on a number of platforms. This is the recommended method for building NASM to support platforms for which executables are not available.

On a system which has Unix shell (sh), run:

```
sh configure
make everything
```

A number of options can be passed to `configure`; see `sh configure --help`.

A set of Makefiles for some other environments are also available; please see the file `Mkfiles/README`.

To build the installer for the Windows platform, you will need the *Nullsoft Scriptable Installer*, NSIS, installed.

To build the documentation, you will need a set of additional tools. The documentation is not likely to be able to build on non-Unix systems.

D.2 Building from the git Repository

The NASM development tree is kept in a source code repository using the `git` distributed source control system. The link is available on the website. This is recommended only to participate in the development of NASM or to assist with testing the development code.

To build NASM from the `git` repository you will need a Perl and, if building on a Unix system, GNU `autoconf`.

To build on a Unix system, run:

```
sh autogen.sh
```

to create the `configure` script and then build as listed above.

Appendix E: Contact Information

E.1 Website

NASM has a website at <http://www.nasm.us/>.

New releases, release candidates, and daily development snapshots of NASM are available from the official web site in source form as well as binaries for a number of common platforms.

E.1.1 User Forums

Users of NASM may find the Forums on the website useful. These are, however, not frequented much by the developers of NASM, so they are not suitable for reporting bugs.

E.1.2 Development Community

The development of NASM is coordinated primarily through the `nasm-devel` mailing list. If you wish to participate in development of NASM, please join this mailing list. Subscription links and archives of past posts are available on the website.

E.2 Reporting Bugs

To report bugs in NASM, please use the bug tracker at <http://www.nasm.us/> (click on "Bug Tracker"), or if that fails then through one of the contacts in section E.1.

Please read section 2.2 first, and don't report the bug if it's listed in there as a deliberate feature. (If you think the feature is badly thought out, feel free to send us reasons why you think it should be changed, but don't just send us mail saying 'This is a bug' if the documentation says we did it on purpose.) Then read section 13.1, and don't bother reporting the bug if it's listed there.

If you do report a bug, *please* make sure your bug report includes the following information:

- What operating system you're running NASM under. Linux, FreeBSD, NetBSD, MacOS X, Win16, Win32, Win64, MS-DOS, OS/2, VMS, whatever.
- If you compiled your own executable from a source archive, compiled your own executable from `git`, used the standard distribution binaries from the website, or got an executable from somewhere else (e.g. a Linux distribution.) If you were using a locally built executable, try to reproduce the problem using one of the standard binaries, as this will make it easier for us to reproduce your problem prior to fixing it.
- Which version of NASM you're using, and exactly how you invoked it. Give us the precise command line, and the contents of the `NASMENV` environment variable if any.
- Which versions of any supplementary programs you're using, and how you invoked them. If the problem only becomes visible at link time, tell us what linker you're using, what version of it you've got, and the exact linker command line. If the problem involves linking against object files generated by a compiler, tell us what compiler, what version, and what command line or options you used. (If you're compiling in an IDE, please try to reproduce the problem with the command-line version of the compiler.)
- If at all possible, send us a NASM source file which exhibits the problem. If this causes copyright problems (e.g. you can only reproduce the bug in restricted-distribution code) then bear in mind the following two points: firstly, we guarantee that any source code sent to us for the purposes of debugging NASM will be used *only* for the purposes of debugging NASM, and that we will delete all our copies of it as soon as we have found and fixed the bug or bugs in question; and secondly, we would prefer *not* to be mailed large chunks of code anyway. The smaller the file, the better. A three-line sample file that does nothing useful *except* demonstrate the problem is much easier to

work with than a fully fledged ten-thousand-line program. (Of course, some errors *do* only crop up in large files, so this may not be possible.)

- A description of what the problem actually *is*. 'It doesn't work' is *not* a helpful description! Please describe exactly what is happening that shouldn't be, or what isn't happening that should. Examples might be: 'NASM generates an error message saying Line 3 for an error that's actually on Line 5'; 'NASM generates an error message that I believe it shouldn't be generating at all'; 'NASM fails to generate an error message that I believe it *should* be generating'; 'the object file produced from this source code crashes my linker'; 'the ninth byte of the output file is 66 and I think it should be 77 instead'.
- If you believe the output file from NASM to be faulty, send it to us. That allows us to determine whether our own copy of NASM generates the same file, or whether the problem is related to portability issues between our development platforms and yours. We can handle binary files mailed to us as MIME attachments, uuencoded, and even BinHex. Alternatively, we may be able to provide an FTP site you can upload the suspect files to; but mailing them is easier for us.
- Any other information or data files that might be helpful. If, for example, the problem involves NASM failing to generate an object file while TASM can generate an equivalent file without trouble, then send us *both* object files, so we can see what TASM is doing differently from us.

Index

! operator, unary	41	A16	33
!= operator	60	a16	130
\$\$ token	40, 104	A32	33
\$		a32	130
Here token	40	A64	33
prefix	33, 37, 107	a64	130
% operator	41	a86	30, 31
%!	71	ABS	36, 82
\$\$ and \$\$\$ prefixes	64, 65	ABSOLUTE	83, 92
%% operator	41, 53	addition	41
%+	48	addressing, mixed-size	129
%,	50	address-size prefixes	33
%?	48	algebra	36
%%?	48	ALIGN	77, 79, 89, 92
%[47	smart	79
& operator	41	align, elf attribute	103
&& operator	60	ALIGNB	77
* operator	41	alignment	77
+ modifier	53	in bin sections	89
+ operator		in ELF sections	103
binary	41	in obj sections	92
unary	41	in win32 sections	96
- operator		of ELF common variables	106
binary	41	ALIGNMODE	79
unary	41	__?ALIGNMODE?__	80
..@ symbol prefix	43, 53	ALINK	109
/ operator	41	alink.sourceforge.net	109
// operator	41	all	25
< operator	60	alloc	103
<< operator	41	alternate register names	79
<= operator	60	altreg	79
<> operator	60	ambiguity	30
= operator	60	a.out	
== operator	60	BSD version	106
> operator	60	Linux version	106
>= operator	60	aout	106
>> operator	41	aoutb	106, 124
? MASM syntax	34	%arg	67
^ operator	41	arg	116, 123
^^ operator	60	as86	107
operator	40	assembler directives	81
operator	60	assembly-time options	23
~ operator	41	%assign	49
%0 parameter count	55	ASSUME	31
%00	55	AT	76
%+1 and %-1 syntax	57	auto-sync	140
16-bit mode, versus 32-bit mode	81	-b	139
64-bit displacement	134	bad-pragma	25
64-bit immediate	133	--before	29
-a option	24, 140	bin output format	20, 89

bin, multisection	90	concatenating strings	50
binary	37	condition codes as macro parameters	57
binary files	34	conditional assembly	58
bit shift	41	conditional comma operator	50
BITS	81, 89	conditional jumps	137
__?BITS?__	74	conditional-return macro	57
bitwise AND	41	constants	37
bitwise OR	40	context fall-through lookup	65
bitwise XOR	41	context stack	64, 66
block IFs	66	context-local labels	64
BND	82	context-local single-line macros	65
bnd	25	counting macro parameters	55
boot loader	89	CPU	86
boot sector	137	CPUID	38
Borland		creating contexts	64
Pascal	117	critical expression	34, 42, 49, 84
Win32 compilers	91	cv8	97
braces		-D option	23
after % sign	57	-d option	23
around macro parameters	52	daily development snapshots	295
BSD	124	.data	104, 106, 107
.bss	104, 106, 107	_DATA	113
bug tracker	295	data	105, 108
bugs	295	data structure	116, 123
BYTE	137	__?DATE?__	74
C calling convention	114, 121	__?DATE_NUM?__	74
C symbol names	112	DB	34, 38, 39
c16.mac	116, 119	dbg	108
c32.mac	123	DD	34, 38, 39
CALL FAR	42	debug information	22
case sensitivity	30, 45, 47, 49, 51, 60, 93	debug information format	21
changing sections	82	__?DEBUG_FORMAT?__	74
character constant	34, 38	decimal	37
character strings	37	declaring structures	75
circular references	45	%defalias	50
CLASS	92	DEFAULT	82
%clear	71, 73	default	105
CodeView debugging format		default macro parameters	54
coff	101	default name	89
colon	33	default-WRT mechanism	94
.COM	89, 111	%define	23, 45
comma	54	defining sections	82
command-line	19, 89	%defstr	49
commas in macro parameters	54	%deftok	49
.comment	104	%depend	63
COMMON	85, 91	design goals	30
ELF extensions to	106	DevPac	34, 43
obj extensions to	94	disabling listing expansion	58
Common Object File Format	101	division	41
common variables	85	DJGPP	101, 121
alignment in ELF	106	djlink	109
element size	94	DLL symbols	
comp.os.msdos.programmer	112	exporting	93
concatenating macro parameters	56	importing	93

DO	34, 38, 39	error messages	22
DOS	22	error reporting format	22
DOS archive		escape sequences	37
DOS source archive		EVEN	77
DQ	34, 38, 39	exact matches	58
.drectve	95	.EXE	91, 109
DT	34, 38, 39	EXE2BIN	111
DUP	31, 35	EXE_begin	110
DW	34, 38, 39	exebin.mac	110
DWORD	34	exec	103
DY	34, 38	Executable and Linkable Format	103
DZ	34	EXE_end	110
-E option	23	EXE_stack	110
-e option	23, 140	%exitrep	62
effective addresses	33, 35	EXPORT	93
element size, in common variables	94	export	107
ELF	103	exporting symbols	85
shared libraries		expressions	24, 40
16-bit code	106	extension	19, 89
debug formats	106	EXTERN	84
elf32	103	elf extensions to	106
elf64	103	obj extensions to	94
elfx32	103	rdf extensions to	108
%elif	58, 60	extracting substrings	51
%elifctx	59	-F option	21
%elifdef	59	-f option	20, 89
%elifempty	61	far call	31
%elifenv	62	far common variables	94
%elifid	61	far pointer	42
%elifidn	60	FARCODE	117, 119
%elifidni	60	%fatal	69
%elifmacro	59	__?FILE?__	73
%elifn	58, 60	fini_array	103
%elifnctx	59	FLAT	92
%elifndef	59	flat memory model	121
%elifnempty	61	flat-form binary	89
%elifnenv	62	FLOAT	87
%elifnid	61	__?FLOAT?__	87
%elifnidn	60	float	25
%elifnidni	60	__?float128h?__	39
%elifnmacro	59	__?float128l?__	39
%elifnnum	61	__?float16?__	39
%elifnstr	61	__?float32?__	39
%elifntoken	61	__?float64?__	39
%elifnum	61	__?float8?__	39
%elifstr	61	__?float80e?__	39
%eliftoken	61	__?float80m?__	39
%else	58	__?FLOAT_DAZ?__	87
endproc	116, 123	float-denorm	25
%endrep	62	floating-point	
ENDSTRUC	75, 83	constants	39, 87
environment	25, 29	packed BCD constants	40
EQU	34, 35	floating-point	31, 33, 34, 39
%error	69	float-overflow	25

__?FLOAT_ROUND?__	87	%ifempty	61
float-toolong	25	%ifenv	62
float-underflow	25	%ifid	60
follows=	90	%ifidn	60
format-specific directives	81	%ifidni	60
fp	80	%ifmacro	59
frame pointer	114, 118, 121	%ifn	58, 60
FreeBSD	106, 124	%ifnctx	59
FreeLink	109	%ifndef	59
ftp.simtel.net	109	%ifnempty	61
function	105, 107	%ifnenv	62
functions		%ifnid	61
C calling convention	114, 121	%ifnidn	60
Pascal calling convention	118	%ifnidni	60
-g option	22	%ifnmacro	59
git	293	%ifnnum	61
GLOBAL	85	%ifnstr	61
aoutb extensions to	105	%ifntoken	61
ELF extensions to	105	%ifnum	60
rdf extensions to	107	%ifstr	60
global offset table	124	%iftoken	61
_GLOBAL_OFFSET_TABLE_	104	ifunc	80
(G L)POSTFIX	86	ilog2()	80
--(g l)postfix	28	ilog2c()	80
(G L)PREFIX	86	ilog2cw()	80
--(g l)prefix	28	ilog2e()	80
..got	104	ilog2f()	80
GOT relocations	125	ilog2fw()	80
GOT	104, 124	ilog2w()	80
..gotoff	104	%imacro	51
GOTOFF relocations	125	IMPORT	93
..gotpc	104	import library	93
GOTPC relocations	125	importing symbols	84
..gottpoff	105	INCBIN	34, 38
graphics	34	%include	22, 23, 63
greedy macro parameters	53	include search path	23
GROUP	92	including other files	63
groups	41	inefficient code	137
-h	139	infinite loop	40
hexadecimal	37	__?Infinity?__	40
hidden	105	infinity	40
hle	25	informational section	95
hybrid syntaxes	30	init_array	103
-I option	22	instances of structures	76
-i option	22, 140	instruction list	143
%iassign	49	integer functions	41, 80
%idefalias	50	integer logarithms	80
%idefine	45	intel hex	90
%idefstr	49	Intel number formats	40
%ideftok	49	internal	105
IEND	76	ISTRUC	76
%if	58, 60	iterating over macro parameters	56
%ifctx	59, 66	ith	90
%ifdef	59	%ixdefine	46

Jcc NEAR	137	macro-params-single	26
JMP DWORD	129	macros	35
jumps, mixed-size	129	makefile dependencies	20, 21
-k	141	map files	90
--keep-all	29	MASM	30, 35, 80, 91
-L option	20	masm compatibility	80
-l option	20	-MD option	21
label	25	memory models	31, 113
label preceeding macro	55	memory operand	34
label prefix	43	memory references	30, 35
label-orphan	25, 33	merge	104
label-redef	25	-MF option	21
label-redef-late	26	-MG option	21
last	54	Microsoft OMF	91
.lbss	104	minifloat	39
ld86	107	Minix	107
.ldata	104	misc subdirectory	110, 116, 123
LIBRARY	107	mixed-language program	112
license	17	mixed-size addressing	129
--limit-X	29	mixed-size instruction	129
%line	29, 70	MMX registers	
__?LINE?__	73	ModR/M byte	
linker, free	109	MODULE	107
Linux		modulo operators	41
a.out	106	motorola s-records	90
as86	107	-MP option	21
ELF	103	-MQ option	21
listing file	20	MS-DOS	89
little-endian	38	MS-DOS device drivers	112
%local	68	-MT option	21
local labels	43	multi-line macros	26, 51
lock	26	multipass optimization	24
logical AND	60	multiple section names	89
logical negation	41	multiplication	41
logical OR	60	multiplier	103
logical XOR	60	multi push macro	56
.lrodata	104	multisection	90
-M option	20	-MW option	21
Mach, object file format	101	__?NaN?__	40
Mach-O, object file format	101	NaN	40
macho32	101	NASM version	73
macho64	101	nasm version history	255
MacOS X	101	nasm version id	73
%macro	51	nasm version string	73
macro	26	__NASMDEFSEG	91
macro indirection	47	nasm-devel	295
macro library	23	NASMENV	29
macro parameters range	54	nasm -h	20
macro processor	45	__?NASM_MAJOR?__	73
macro-defaults	26	__?NASM_MINOR?__	73
macro-local labels	52	nasm.out	19
macro-params	26	__?_NASM_PATCHLEVEL?__	73
macro-params-legacy	26	__?NASM_SNAPSHOT?__	73
macro-params-multi	26	__?NASM_SUBMINOR?__	73

__?NASM_VER?__	73	other preprocessor directives	70
__?NASM_VERSION_ID?__	73	out of range, jumps	137
ndisasm	139	output file format	20
near call	31	output formats	89
near common variables	94	__?OUTPUT_FORMAT?__	74
negative-rep	26	overlapping segments	41
NetBSD	106, 124	OVERLAY	92
new releases	295	overloading	
noalloc	103	multi-line macros	52
nobits	90, 103	single-line macros	46
NOBND	82	-P option	23
no_dead_strip	102	-p option	23, 63
noexec	103	paradox	42
--no-line	29, 71	PASCAL	119
.nolist	58	Pascal calling convention	118
note	103	__?PASS?__	75
not-my-pragma	26	passes, assembly	
'nowait'	31	%pathsearch	22, 63
nowrite	103	period	43
NSIS	293	Perl	
Nullsoft Scriptable Installer	293	PharLap	92
number-overflow	26	phase	27
numeric constants	34, 37	PIC	104, 106, 124
-O option	24	.plt	104
-o option	19, 139	PLT relocations	104, 126, 127
O16	33	plt relocations	127
o16	130	pointer, elf attribute	103
O32	33	%pop	64
o32	131	position-independent code	104, 106, 124
O64	33	%pragma	70
.OBJ	109	--pragma	28
obj	91	pragma	27
object	105, 108	pragma-bad	27
obsolete	26	pragma-empty	27
obsolete-nop	26	pragma-na	27
obsolete-removed	26	pragma-unknown	27
obsolete-valid	27	precedence	40
octal	37	pre-defining macros	23, 46
OF_DEFAULT	20	preferred	41
OFFSET	30	pre-including files	23
OMF	91	preinit_array	103
omitted parameters	54	preprocess-only mode	24
one's complement	41	preprocessor	23, 24, 35, 41, 45
OpenBSD	106, 124	preprocessor expressions	24
operands	33	preprocessor loops	62
operand-size prefixes	33	preprocessor variables	49
operating system	89	primitive directives	81
writing	129	PRIVATE	91
operators	40	private_extern	102
ORG	89, 111, 112, 137	proc	107, 116, 123
orphan-labels	27	procedure linkage table	104, 126, 127
OS/2	91, 92	processor mode	81
osabi	103	progbits	90, 103
other	27	program entry point	94, 109

program origin	89	SEGMENT	82
protected	105	ELF extensions to	91
pseudo-instructions	34	segment address	41
ptr	27	segment alignment	
PUBLIC	85, 91	in bin	89
pure binary	89	in obj	92
%push	64	segment names, Borland Pascal	119
__?QNaN?__	40	segment override	31, 33
quick start	30	segments	41
QWORD	34	groups of	92
-r	139	separator character	29
rdf	107	shared libraries	106, 124
rdo ff subdirectory	107	shared library	105
redirecting errors	22	sh if t command	55
regsize	27	SIB byte	
REL	36, 82	signed division	41
relational operators	60	signed modulo	41
release candidates	295	single-line macros	26, 45
Relocatable Dynamic Object File Format	107	size, of symbols	105
relocations, PIC-specific	104	smar talign	79
removing contexts	64	__?SNaN?__	40
renaming contexts	66	snapshots, daily development	295
%rep	35, 62	Solaris x86	103
repeating	35, 62	-soname	127
%repl	66	sound	34
reporting bugs	295	source-listing file	20
REQUIRED	84	square brackets	30, 35
RESB	31, 34	srec	90
RESD	34	STACK	91
RES0	34	stack relative preprocessor directives	67
RESQ	34	%stacksize	68
REST	34	standard macro packages	79
RESW	34	standard macros	73
RESY	34	standardized section names	82, 95, 103, 106, 107
RESZ	34	..start	94, 109
.rodata	104	start=	90
%rotate	55	STATIC	85
rotating macro parameters	55	stderr	22
-s option	22, 140	stdout	22
searching for include files	63	%strcat	50
__?SECT?__	82, 83	STRICT	42
SECTALIGN	78	string constant	34
SECTION	82	string constants	38
ELF extensions to	103	string length	50
macho extensions to	101	string manipulation in macros	50
win32 extensions to	95	strings	37
section alignment		elf attribute	103
in bin	89	%strlen	50
in ELF	103	strong	105
in obj	92	STRUC	75, 83, 116, 123
in win32	96	structure data types	75
section, bin extensions to	89	stub preprocessor	24
SEG	41, 91	subsections_via_symbols	102

%substr	51	unknown-pragma	27
subtraction	41	unknown-warning	27
suppressing preprocessing	24	%unmacro	58
switching between sections	82	unrolled loops	35
. . sym	104	unsigned division	41
symbol sizes, specifying	105	unsigned modulo	41
symbol types, specifying	105	UPPERCASE	30, 93
symbols		%use	63, 79
exporting from DLLs	93	__?USE_*?__	75
importing from DLLs	93	USE16	82, 92
synchronisation	140	USE32	82, 92
. SYS	89, 112	user	27
-t	24	user-defined errors	69
TASM	24	user-level assembler directives	73
tasm	30, 91	user-level directives	81
. tbss	104	__?UTC_DATE?__	74
TBYTE	31	__?UTC_DATE_NUM?__	75
. tdata	104	__?UTC_TIME?__	74
test subdirectory	109	__?UTC_TIME_NUM?__	75
testing		UTF-16	39
arbitrary numeric expressions	60	UTF-32	39
context stack	59	UTF-8	38
exact text identity	60	__?utf16?__	39
multi-line macro existence	59	__?utf16be?__	39
single-line macro existence	59	__?utf16le?__	39
token types	60	__?utf32?__	39
. text	104, 106, 107	__?utf32be?__	39
_TEXT	113	__?utf32le?__	39
thread local storage		--v	28
in ELF	105	-v option	28
in macho	102	VAL	109
__?TIME?__	74	valid characters	33
__?TIME_NUM?__	74	variable types	30
TIMES	34, 35, 42, 137, 138	version	28
TLINK	111	version number of NASM	73
tls	102, 104, 105	v follows=	90
. . tlsie	105	Visual C++	95
trailing colon	33	vstart=	90
TWORD	31, 34	-W option	24
type, of symbols	105	-w option	24
-U option	23	%warning	69
-u option	23, 139	[WARNING]	28, 87
unary operators	41	warning classes	25
%undef	23, 49	warnings	24
undefining macros	23	warn-stack-empty	28
underscore, in C symbols	112	weak	105, 106
Unicode	38, 39	website	295
uninitialized	34	-Werror option	28
uninitialized storage	31	win64	97, 133
Unix		Win64	91, 95, 121
SCO	103	Windows	109
source archive		Windows 95	
System V	103	windows debugging formats	97
UnixWare	103	Windows NT	

-Wno-error option	28
write	103
writing operating systems	129
WRT	41, 91, 102, 104, 105, 106
WRT ..got	125
WRT ..gotoff	125
WRT ..gotpc	125
WRT ..plt	127
WRT ..sym	126
WWW page	
www.delorie.com	109
www.pcorner.com	109
-X option	22
x2ftp.oulu.fi	109
x32	103
%xdefine	46
-Z option	22
zeroing	28
zext-reloc	28